## mbeddr C Extensions User's Guide

Markus Voelter

independent/item is

**Abstract.** This document describes the *mbeddr.ext* package that currently contains physical units, exceptions, components and state machines.



This document is part of the mbeddr project at http://mbeddr.com.

This document is licensed under the Eclipse Public License 1.0 (EPL).

# Table of Contents

mb	oeddr	C Extensions User's Guide
	Mar	kus Voelter
1	Phys	sical Units
	1.1	Basic SI Units in C programs
		Derived Units
		Convertible Units 5
		Extension with new Units
2	Com	ponents
	2.1	Basic Interfaces and Components
	2.2	Contracts
3	Stat	e Machines
4	Exce	eptions

## 1 Physical Units

Physical Units are new types that, in addition to specifying their actual data type, also specify a physical unit (see Fig. 1). New literals are introduced to support specifying values for these types that include the physical unit. The typing rules for the existing operators (+, \* or >) are overridden to perform the correct type checks for types with units. The type system also performs unit computations to, for example, handle an speed = length/time correctly.

```
derived unit mps = m s<sup>-1</sup> for speed
convertible unit kmh for speed
conversion kmh -> mps = val * 0.27

int8_t/mps/ calculateSpeed(int8_t/m/ length, int8_t/s/ time) {
  int8_t/mps/ s = length / time;
  if ( s > 100 mps) { s = [100 kmh → mps]; }
  return s;
}
```

Fig. 1. The *units* extension comes with the sevel SI units predefined and lets users define arbitrary derived units (such as the mps in the example). It is also possible to defined convertible units that require a numeric conversion factor to get back to SI units. Type checks ensure that the values associated with unit literals use the correct unit and perform unit computations (as in speed equals length divided by time). Errors are recorded if incompatible are used together (e.g. if we were to add length and time). To support this feature, the typing rules for the existing operators (such as + or /) have to be overridden.

To use physical units use the com.mbeddr.physicalunits devkit in your model.

#### 1.1 Basic SI Units in C programs

Once the devkit is included, types can be annotated with physical units. We have defined the seven SI units in mbeddr:

```
int8_t/m/ length;
int8_t/s/ time;
```

It is also possible to define composite units. To add additional components press enter after the first one (the m in the example below):

```
^{-1} int8_t/m s / speed;
```

To change the exponent, use intentions on the unit. Types with units can also be typedef'ed to make using them more convenient:

```
typedef int8_t/m s / as speed_t;
```

If you want to assign a value to the variable, you have to use literals with units, otherwise you will get compile errors:

```
int8_t/m/ length = 3 m;
```

Note that units are computed correctly:

```
speed_t aSpeed = 10 m / 5 s;
speed_t anotherSpeed = 10 m + 5 s; // error; adding apples and oranges
```

Of course, the type system is fully aware of the types and "pulls them through":

```
int8_t/m/ someLength;
int8_t/m/ result = 10 m + someLength;
```

To get values "into" and out of the units world, you can use the stripunit and introduceunit expressions:

```
int8_t/m/ someLength = 10 m;
int8_t justSomeValue = stripunit[someLength];
int8_t/m/ someLength = introduceunit[justSomeValue -> m];
```

## 1.2 Derived Units

A derived unit is one that combines several SI units. For example,  $N = kg\frac{m}{s^2}$  or  $mps = \frac{m}{s}$ . Such derived units can be defined with the units extension as well.

To define derived units, create a UnitContainer in your model. There you can define derived units (Fig. 2).

Unit computations in C programs work as expected; compatibility is checked by reducing both to-be-compared units to their SI base units.

## Unit Declarations

```
derived unit N = kg m s<sup>-2</sup> for force
derived unit Pa = N m<sup>-2</sup> for pressure
```

Fig. 2. Derived units are combinations of other units.

#### 1.3 Convertible Units

The derived units discussed in the previous section are still within the SI system and require no value conversions. For convertible units, this is different. They can be declared in the unit container as well; but they need conversion rules to be usable (Fig. 3).

```
Unit Declarations
convertible unit F for temperature
convertible unit C for temperature

Conversion Rules
conversion F -> C = val * 9 / 5 + 32
conversion C -> F = (val - 32) * 5 / 9
```

Fig. 3. Convertible units require the definition of conversion rules.

Typically, a convertible unit is a non-SI unit, and the conversion rules map it back to the SI world. Notice how in the conversion rule the val keyword represents the value in the original unit.

Conversions in the C programs do not happen automatically, since such a conversion produced runtime overhead. Instead, an explicit conversion has to be used which relies on the conversion rule defined in the units container. A conversion can be added with an intention.

```
int8_t/F/ tempInF = 10 F;
int8_t/C/ tempInC = [tempInF -> C];
```

## 1.4 Extension with new Units

The units extension can also be "misused" to work with other type annotations such as money, time or coordinate systems. To achieve this, you have to define new elementary unit declarations in a language extension. Here is some example code with coordinate systems:

```
int8_t/#global/ aGlobalVariable = 10#global;
int8_t/K/ aTemp = aGlobalVariable; // error; #global != K
aGlobalVariable = 10K; // error; #global != K
aGlobalVariable = 230#local; // error; #global != #local
```

In the example above, #global and #local are two different coordinate systems; technically, both are subtypes of ElementaryUnitDeclaration:

Even though these are not technically *convertible* units, we can still define conversion rules:

```
Conversion Rules

conversion #global -> #local = val + 20

conversion #local -> #global = val - 20
```

The C code can then use conversions as shown above:

```
int8_t/#local/ aLocalVariable = 20#local;
aGlobalVariable = [aLocalVariable -> #global];
```

The coordinate systems extension is especially useful if combined with a new type and literal, for example, for vectors:

```
intvec/#global/ globalVector = (10,20)#global;
intvec/#local/ localVector = (20,20)#global;
```

### 2 Components

Modularization supports the divide-and-conquer approach, where a big problem is broken down in to a set of smaller problems that are easier to understand and solve. To make modules reusable in different contexts, modules should define a contract that prescribes how it must be used by client modules. Separating the module contract from the implementation also supports different implementations of the same contract.

Object oriented programming, as well as component-based development exploit this notion. However, C does not support any form of modularization beyond separating sets of functions, <code>enums</code>, <code>typedefs</code> etc. into different .c and .h files. mbeddr, in contrast supports a rich component model.

#### 2.1 Basic Interfaces and Components

To use the components in your C programs, please include the com.mbeddr.components devkit.

Interfaces An interface is essentially a set of operation signatures, similar to function prototypes in C. query marks functions as not performing any state changes; they are assumed to be invokable any number of times without side effects (something we do not verify automatically at this time).

```
exported interface DriveTrain {
   void driveForwardFor(uint8_t speed, uint32_t ms)
   void driveBackwardFor(uint8_t speed, uint32_t ms)
   void driveContinouslyForward(uint8_t speed)
   void driveContinouslyBackward(uint8_t speed)
   void stop()
   query uint8_t currentSpeed()
}
```

Components Components can provide and require interfaces via ports. A provided port means that the component implements the provided interface's operations, and clients can invoke them. These invocations happen via required ports. A required port expresses an expectation of a component to be able to call operations on the port's interface. The example below shows a component RobotChassis that provides the DriveTrain interface shown above, and requires two instances of EcRobot\_Motor.

```
exported component RobotChassis {
    provides DriveTrain dt
    requires EcRobot_Motor motorLeft
    requires EcRobot_Motor motorRight

    void dt_driveForwardFor(uint8_t speed, uint32_t ms) <- op dt.driveForwardFor {
        motorLeft.set_speed(((int8_t) speed));
        motorRight.set_speed(((int8_t) speed));
        ...
}
...
}</pre>
```

Note how the dt\_driveForwardFor runnable implements the operation driveForwardFor from the dt provided port. The two signatures are automatically synchronized. Inside components, the operations on required ports can be invoked in the familiar dot notation.

Components can be instantiated. Each component instance generally must get all its required ports connected to provided ports provided by other instances. However, a required port may be marked as optional (this is toggled via an intention), in which case, for a given instance, the required port may *not* be connected. Invocations on this required port make no sense in this case, which is why code invoking operations on an optional port must be wrapped in a with port (optionalReqPort) { ...} statement. The body of the with port is not executed if the port is not connected. The IDE reports an error at editing time if an invocation on an optional port is *not* wrapped this way.

```
exported component RobotChassis {
    provides DriveTrain dt
    requires EcRobot_Motor motorLeft
    requires EcRobot_Motor motorRight
    requires optional ILogging log

    void dt_driveForwardFor(uint8_t speed, uint32_t ms) <- op dt.driveForwardFor {
        with port(log) {
            // other stuff
            log.error(...)
            // more other stuff
        }
        ...
}</pre>
```

Components can have fields. These get values for each of the component instances created:

```
exported component OrienterImpl extends nothing {
  ports:
    ...
  contents:
    field int16\_t[5] headingBuffer
    field int8\_t headingIndex

  void orienter\_orientTowards(int16\_t heading, uint8\_t speed, DIRECTION dir) <- ... {
      headingIndex = heading;
    }
}</pre>
```

Fields can be marked as init fields (via an intention). In this case, when a component is instantiated, a value for the field has to be specified. We will show this below.

We have seen above how a component runnable is tied to the invocation of an operation on a provided port (using <- op port.operation). This triggering mechanism can also be used for other events, for example, to react to component instantiation. This effectively supports constructors:

```
exported component OrienterImpl extends nothing {
  contents:
    void init() <- on init {
      compass.initAbsolute();
      compass.heading();
}</pre>
```

Instantiation A key difference of mbeddr components compared to C++ classes is that mbeddr component instances are assumed to be allocated and connected during program startup (embedded software typically allocates all memory at program startup to avoid failing during execution), not at arbitrary points in the execution of a program (as in C++ classes). The following piece of code shows an instance configuration:

```
exported instance configuration defaultInstances extends nothing {
  instance RobotChassis chassis
  instance EcRobot_Motor_Impl motorLeft(motorAddress = NXT_PORT_B)
  instance EcRobot_Motor_Impl motorRight(motorAddress = NXT_PORT_C)
  connect chassis.motorLeft to motorLeft.motor
  connect chassis.motorRight to motorRight.motor
}
```

It allocates two instances of the EcRobot\_Motor\_Impl component (each with a different value for its motorAddress init parameter) as well as a single instance of RobotChassis. The chassis' required ports are connected to the provided ports of the two motors. Note that an instance configuration just defines instances and port connections. The actual allocation and initialization of the underlying data structures happens separately in the startup code of the application, for example, in a main function:

```
int32_t main(int32_t argc, int8_t*[] argv) {
  initialize defaultInstances;
  ...
}
```

To be able to call "into" component instances from regular, non-component C code, adapters can be used. They can be defined inside of instance configurations as well as outside of them. Here is an example:

```
exported instance configuration instances extends nothing {
  instances:
    instance EcRobot_Display_Impl i_display
  connectors:
    ...
  adapter:
    adapt i_display.displayPort as disp
}

void main() {
  initialize instances;
    disp.show("some message");
}
```

Transformation Configuration Components must be able to work potentially with various off-the-shelf middleware solutions such as AUTOSAR. In this case, components will have to be translated differently. Consequently, the transformation for components has to be configured. This happens — like any other configuration — in the BuildConfiguration:

```
Configuration Items
components: no middleware
wire statically: false
```

The default configuration uses the no middleware generator, where components are transformed to plain C function. mbeddr components support polymorphic invocations in the sense that a required port only specifies an *interface*, not the implementing *component*. This way, different implementations can be connected to the same required port (we implement this via a function pointer in the generated C code). This is roughly similar to C++ classes. However, to optimize performance, the generators can also be configured to connect instances statically. In this case, an invocation on a required port is implemented as a direct function call, avoiding additional overhead. This optimization can be performed globally or specifically for a single port. Polymorphism is not supported in this case — users trade flexibility for performance. To do this, select wire statically: true. You then have to reference the instance configuration you intend to use:

```
components: no middleware
wire statically: true instance config: instances
```

If you connect a specific component port to different provided ports in different instances of this component, an error will be reported.

You can also make the decision to wire statically (without polymorphism) on a port-by-port basis, directly in the component (via an intention):

```
{\tt requires} \ {\tt EcRobot\_Compass} \ {\tt compass} \ {\tt restricted} \ {\tt to} \ {\tt OrienterImpl.orienter}
```

In this case you specify not just the interface but also the particular component and port. This allows the generator to directly refer to the implementing C function — without any overhead.

#### 2.2 Contracts

An additional difference to C++ classes is that mbeddr interfaces support contracts. Operations can specify pre and post conditions, as well as sequencing constraints. Here is the interface from above, but with contract specifications:

```
exported interface DriveTrain {
  void driveForwardFor(uint8_t speed, uint32_t ms)
    pre(0) speed < 100
    post(1) currentSpeed() == 0
    protocol init -> init
  void driveContinouslyForward(uint8_t speed)
    pre(0) speed <= 100
    post(1) currentSpeed() == speed
    protocol init -> forward
  void accelerateBy(uint8_t speed)
    post(1) currentSpeed() == old(currentSpeed()) + speed
    protocol forward -> forward
  query uint8_t currentSpeed()
}
```

The first operation, driveForwardFor, requires the speed parameter to be below 100. After the operation finishes, currentSpeed is zero (notice how the query operation currentSpeed() is called as part of the post condition). The protocol specifies that, in order to call the operation, the protocol has to be in the init state. The post condition for driveContinouslyForward expresses that after executing this method the current speed will be the one passed into the operation — in other words, it keeps driving. This is also reflected by the protocol specification which expresses that the protocol will be in the forward state. The accelerateBy operation can only be called legally while the protocol is in the forward state, and it remains in this state. The post condition shows how the value of a query operation before the execution of the function can be accessed.

The contract is specified on the *interface*. However, the code that checks the contract is generated into the components (i.e. the implementations of the interface operations). The contracts are then checked at runtime.

To add a pre- or postcondition or a protocol, use an intention on the operation. In the inspector, you will have to provide a reference to a message definition that will be **reported** in case the condition or the protocol fails.

- 2.3 Mocks
- 3 State Machines
- 4 Exceptions