Prevent SiteScope UI From Stopped Unexpectedly

Friday, July 12, 2024 2:00 AM

Issue

he default for this is 20 minutes, but depending on environment the initial logging out can happen after less than 20 minutes.

When not working with SiteScope for some time, all of a sudden the SiteScope GUI turns into a kind of grey, and one gets this sliding bar



and usually thinks something is wrong with SiteScope, as it's the same behavior one can observe when restarting SiteScope.

Resolution

To get around the GUI timeout - which in fact is a security feature - perform the following steps:

1. Change this settings :

   in <SiteScope>\groups\master.config
   change
   _maxSessionTimeMinutes=20 (default)
   to
   _maxSessionTimeMinutes=-1

   and restart SiteScope – done.

2. From SiteScope Start Menu -> Access the Config Wizard



3. Choice Sizing



4. Increase to the Recommended Values then click Finish



5. Restart the SiteScoep Service

Note: Sizing changes can be made only if the physical memory of the SiteScope server is larger than the maximum JVM heap size (Xmx) that the Configuration Tool has configured (4 GB for a 64-bit installation).
Click Next to complete the sizing operation.