

Dr. Gavin McArdle

Email: gavin.mcardle@ucd.ie

Office: A1.09 Computer Science

RECAP

Modulation Schemes

- Baseband Modulation
 - Manchester Encoding, NRZ, NRZI, 4B/5B
- Passband Modulation
 - Carrier signal
 - •Increasing bits through phase, frequency and amplitude key shifting.
 - Constellation Diagrams

TODAY'S PLAN

Link Layer

- Framing
 - Byte/Bit stuffing
- Errors
 - Detection
 - Correction

THE LINK LAYER

Moving <u>up</u> to the Link Layer

Application

Transport

Network

Link

Physical

- HTTP, DNS, CDNs

- TCP, UDP

- IP, NAT, BGP

- Ethernet, 802.11

- wires, fiber, wireless


SCOPE OF THE LINK LAYER

- Responsible for delivering frames of information over a single link
- Establishes connections between neighbouring nodes to send data.
- Implements the actual topology of the local network that allows the internet layer to present an addressable interface.
- Achieves this by sending data to a physical address of another node in the network (MAC Address).
- Handles transmission errors and regulates the flow of data.

SCOPE OF THE LINK LAYER


Concerns how to transfer messages between links

- Messages are <u>frames</u>, of limited size
- Builds on the physical layer




IN TERMS OF LAYERS ...

Link layer accepts <u>packets</u> from the network layer, and encapsulates them into <u>frames</u> that it sends using the physical layer; reception is the opposite process



TYPICAL IMPLEMENTATION OF LAYERS




TOPICS OF THE LINK LAYER

- 1. Framing
- Delimiting start/end of frames
- 2. Error detection and correction
- Handling errors
- 3. Retransmissions
- Handling loss
- 4. Multiple Access
- 802.11, classic Ethernet
- 5. Switching
- Modern Ethernet

FRAMING

- The Physical layer gives us a stream of bits. How do we interpret it as a sequence of frames?
- Framing provides a way for a sender to transmit a set of bits that are meaningful to the receiver
- The advantage of using frames is that data is broken up into recoverable chunks that can easily be checked for corruption.



FRAMING METHODS

We'll look at:

- Byte count
- Byte stuffing
- Bit stuffing

In practice, the physical layer often helps to identify frame boundaries


- Ethernet, 802.11
- Protocols

BYTE COUNT

First try:

- Let's start each frame with a length field
- It's simple, and hopefully good enough ...


BYTE COUNT



BYTE COUNT

Difficult to re-synchronize after framing error

Want a way to scan for a start of frame



BYTE STUFFING

Better idea:

Have a special flag byte value that means start/end of frame
 Complications


- Replace ("stuff") the flag inside the frame with an escape code
- Have to escape the escape code too!
- Longer, but easy to resynchronize after error

FLAG	Header	Payload field	Trailer	FLAG
------	--------	---------------	---------	------

BYTE STUFFING


Rules:

- Replace each FLAG in data with ESC FLAG
- Replace each ESC in data with ESC ESC




BYTE STUFFING

Now any unescaped FLAG is the start/end of a frame



FRAMING - BYTE STUFFING



BIT STUFFING

Can stuff at the bit level too

- Call a flag six consecutive 1s
- On transmit, after five 1s in the data, insert a 0
- On receive, a 0 after five 1s is deleted


BIT STUFFING

Example:



BIT STUFFING


So how does it compare with byte stuffing?



EXAMPLE PROTOCOLS

- PPP is a Point-to-Point Protocol
 - uses Byte Stuffing
 - used to frame IP packets that are sent in Synchronous Optical Networking (SONET) links
 - Flag: FLAG is 0x7E
- HDLC (High-level Data Link Control)
 - uses Bit Stuffing
 - used in serial connections e.g. USB
 - some Point-to-Point networks
 - Flag: 0111 1110
- Wifi
 - Preamble and Start Frame Delimiter
 - 80 bits alternation 1s and 0s followed by 1111 0011 1010 0000 (F3A0)
- Ethernet
 - Preamble and Start Frame Delimiter
 - 56 bits 80 bits alternation 1s and 0s followed by 10101011 (0xD5)

Think of SONET as a bit stream, and PPP as the framing that carries an IP packet over the link



Framing uses byte stuffing

FLAG is Ox7E and ESC is Ox7D

1	1	1	1 or 2	Variable	2 or 4	1
Flag 01111110	Address 11111111	Control 00000011	Protocol	Payload	Checksum	Flag 01111110
	J			Flag Address Control Protocol	Flag Address Control Protocol Payload	Flag Address Control Protocol Payload Checksum

Byte stuffing method:

- To stuff (unstuff) a byte, add (remove) ESC (0x7D), and XOR next byte with 0x20
- Removes FLAG from the contents of the frame completely

Esc: 0x7D: 1111101

Flag: 0x7E: 1111110 ________ 1111110

0x20:0100000

XOR

→ 0100000 1011110

XOR Rules

Inp	Output		
Α	В	Output	
0	0	0	
0	1	1	
1	0	1	
1	1	0	

Byte stuffing method:

- To stuff (unstuff) a byte, add (remove) ESC (0x7D), and XOR byte with 0x20
- Removes FLAG from the contents of the frame completely 0x7E (flag) appears in the data so we escape it using 0x7D and XORing 0x7E with 0x20 - results in 5E

Byte stuffing method:

- To stuff (unstuff) a byte, add (remove) ESC (0x7D), and XOR byte with 0x20
- Removes FLAG from the contents of the frame completely 0x7E (flag) appears in the data so we escape it using 0x7D and XORing 0x7E with 0x20 results in 5E 0x7D(Esc character) appears in the data we escape it using 0x7D and the XORing 0x7D (next byte) with 0x20 results in 5D

Before Framing:

41 **7D** 42 **7E** 50 70 46

After Byte Studding and Framing:

7E 41 7D 5D 42 7D 5E 50 70 46 7E


ERROR HANDLING

Reliability is a concern that cuts across the layers


Some bits will be received in error due to noise. What can we do?

- Detect errors with codes »
- Correct errors with codes »
- Retransmit lost frames


PROBLEM - NOISE MAY FLIP RECEIVED BITS



PROBLEM - NOISE MAY FLIP RECEIVED BITS



PROBLEM - NOISE MAY FLIP RECEIVED BITS



APPROACH - ADD REDUNDANCY

Error detection codes

 Add <u>check bits</u> to the message bits to let some errors be detected

Error correction codes

Add more <u>check bits</u> to let some errors be corrected

Key issue is how to structure the code to detect many errors with few check bits and modest computation

EXAMPLE

A simple code to handle errors:

- Send two copies. There is an error if different.
 - Message: 010010

How good is this code?

- How many errors can it detect/correct?
- Correct: None
 - 010:011
- Detect: Maybe three
 - If there are 3 differences between the parts
- How many errors will make it fail?

EXAMPLE

A simple code to handle errors:

- Send two copies. There is an error if different.
 - Message: 010010

How good is this code?

- How many errors can it detect/correct?
- Correct: None
 - 010:011
- Detect: Maybe up to three
 - If there are 3 differences between the parts
- How many errors will make it fail?2 errors will make it fail
 - 011:011

50% of overhead on error detection!

EXAMPLE


We want to handle more errors with less overhead

- Will look at better codes; they are applied mathematics
- But, they can't handle all errors
- And they focus on accidental errors

USING ERROR CODES

Codeword consists of D data plus R check bits (=systematic block code)

- operate on a block of bits of a time e.g. A frame,
- append check bitsData bits Check bits




Sender:

Compute R check bits based on the D data bits; send the codeword of D+R bits

USING ERROR CODES

Receiver:

- Receive D+R bits with unknown errors
- Recompute R check bits based on the D data bits; error if R doesn't match R'



HAMMING DISTANCE (HD)

Distance is the number of bit flips needed to change D+R₁ to D+R₂

000 -> 111 = number of bit flips needed is 3 = distance between codewords

<u>Hamming distance</u> of a code is the minimum distance between any pair of codewords (from all codewords).

Above we have just 2 code words and the HD is 3

HAMMING DISTANCE

Error detection:

- For a code of HD d+1, up to d errors will always be detected
- HD = d + 1 = 3 -> d = 2
- Can detect up to 2 bit errors

None are valid code words so will be detected

HAMMING DISTANCE

Error correction:

For a code of HD 2d+1, up to d errors can always be corrected by mapping to the closest codeword

$$-$$
 HD = 2d+ 1 = 3

-d = 1

Valid codewords: 000 111

Received Code words: 010

Received Code words: 110

Received Code words: 010