Virtual Memory Management



School of Computer Science, UCD

Scoil na Ríomheolaíochta, UCD

Learning Outcomes

- Understand the technique of caching and its implementation in Virtual Memory
- Understand how the principle of locality and its role in VM
- Understand the techniques of demand paging, page faults and trashing
- Understand replacement policies for pages in memory
- Understand multi-level tables and inverted page tables




Caching Concept

- **Cache:** a repository for copies that can be accessed more quickly than the original
 - Make frequent case fast and infrequent case less dominant
- Caching underlies many of the techniques that are used today to make computers fast
 - Can cache: memory locations, address translations, pages, file blocks, file names, network routes, etc...
- Only good if:
 - Frequent case frequent enough and
 - Infrequent case not too expensive
- Important measure: Average Access time =
 (Hit Rate x Hit Time) + (Miss Rate x Miss Time)




Why Bother with Caching

Processor-DRAM Memory Gap (latency)




Another Major Reason to Deal with Caching




- Cannot afford to translate on every access
 - At least three DRAM accesses per actual DRAM access
 - Or: perhaps I/O if page table partially on disk!
- Even worse: What if we are using caching to make memory access faster than DRAM access???
- Solution? Cache translations!
 - Translation Cache: TLB ("Translation Lookaside Buffer")



Why Does Caching Help? Locality!




- Temporal Locality (Locality in Time):
 - Keep recently accessed data items closer to processor
- **Spatial Locality** (Locality in Space):
 - Move contiguous blocks to the upper levels





Memory Hierarchy in a Modern Conputer System

- Take advantage of the principle of locality to:
 - Present as much memory as in the cheapest technology
 - Provide access at speed offered by the fastest technology



Virtual Memory

Characteristics of paging and segmentation:

- The address space of a process may be broken up into pieces (pages or segments)
- Memory references within a process are logical addresses, dynamically translated into physical addresses
- By virtue of the page/segment table, pages/segments of a process need not be contiguously located in main memory
- Last but not least: it is not necessary that all pages/ segments of a process be simultaneously in main memory during execution: part of the process may be disk
- **Virtual memory (VM):** illusion supported by system hardware and software that a process has a vast and linear expanse of available memory (much bigger than the main memory unit)
 - Main memory can be seen as a cache for the disk
 - Logical addresses are also called *virtual addresses* in the context of VM



Real Programs and VM

- The VM scheme is appealing: is it practical as well?
- An examination of a real program shows that it can usually be divided into two parts:
 - 1. Parts frequently needed
 - 2. Parts rarely or never needed:
 - Code handling unusual error conditions
 - Code handling certain options and features rarely used
 - Allocation of more memory than strictly needed (arrays, tables. . .)




 Also, memory references within a program tend to be clustered (principle of *locality of references*)

Locality in a Memory-reference Pattern


- Program Memory
 Access Patterns have
 temporal and spatial
 locality
 - Group of Pages
 accessed along a
 given time slice called
 the "Working Set"
 - Working Set defines minimum number of pages needed for process to behave well
- Not enough memory for Working Set⇒Thrashing
 - Better to swap out process?





Working Set Model

 As a program executes it transitions through a sequence of "working sets" consisting of varying sized subsets of the address space




Real Programs and VM

- Therefore, it is possible to make <u>intelligent</u>
 <u>guesses</u> about which pieces of the address space
 of the process will most likely be needed in the
 near future
 - If guesses are good, then a system using VM will perform efficiently
- If guesses are poor, the system will suffer from thrashing
 - It will spend too much time swapping processes' pieces between memory and disk, rather than executing instructions
 - Disk accesses are much slower than memory accesses




Demand Paging

- Modern programs require a lot of physical memory
 - Memory per system growing faster than 25%-30%/year
- But they don't use all their memory all of the time
 - 90-10 rule: programs spend 90% of their time in 10% of their code
 - Wasteful to require all of user's code to be in memory
- Solution: use main memory as cache for disk





Illusion of Infinite Memory



- Disk is larger than physical memory ⇒
 - In-use virtual memory can be bigger than physical memory
 - Combined memory of running processes much larger than physical memory
 - More programs fit into memory, allowing more concurrency
- Principle: Transparent Level of Indirection (page table)
 - Supports flexible placement of physical data
 - Data could be on disk or somewhere across network
 - Variable location of data transparent to user program
 - Performance issue, not correctness issue



Virtual Memory Features

- VM is commonly implemented by demand paging
 - When a program is loaded, the OS brings into main memory only a few pages of it (including its starting point)
 - Further pages are then brought to memory or swapped to disk as needed
 - The *resident set* is the portion of the process that is in main memory at a given time
- VM system supported by
 - Hardware: paging mechanism, which generates
 page faults when pages in disk are referenced
 - Software: page swapping management (OS algorithm)



What is in a Page Table Entry?

- What is in a Page Table Entry (or PTE)?
 - Pointer to next-level page table or to actual page
 - Permission bits: present (sometimes "valid"), read-only, read-write, write-only
- Example: Intel x86 architecture PTE:

Page Frame Number (Physical Page Number)	Free (OS)	0	L	D	Α	PCD	PWT	U	W	Р
31-12	11-9	8	7	6	5	4	3	2	1	0

- P: Present: Set to 1 if piece in main memory. Page fault when not
- W: Writeable
- U: User accessible
- PWT: Page write transparent: external cache write-through
- PCD: Page cache disabled (page cannot be cached)
 - A: Accessed: page has been accessed recently
 - D: Dirty (PTE only): page has been modified recently
 - L: $L=1 \Rightarrow 4MB$ page (directory only).

Main entry: if page in memory: frame number

if page in disk: address in disk, or index to a table Bottom 22 bits of virtual address serve as offset




Demand Paging Mechanisms

- PTE helps us implement demand paging
 - Present (or "Valid") ⇒ Page in memory, PTE points at physical page
 - Not Present (or "Not Valid") ⇒ Page not in memory; use info in PTE to find it on disk when necessary
- Suppose user references page with invalid PTE?
 - Memory Management Unit (MMU) traps to OS
 - Resulting trap is a "Page Fault"
 - What does OS do on a Page Fault?:
 - Choose an old page to replace
 - If old page modified ("D=1"), write contents back to disk
 - Change its PTE and any cached TLB to be invalid
 - Load new page into memory from disk
 - Update page table entry, invalidate TLB for new entry
 - Continue thread from original faulting location
 - TLB for new page will be loaded when thread continued!
 - While pulling pages off disk for one process, OS runs another process from ready queue
 - Suspended process sits on wait queue



Steps in Handling a Page Fault






VM Advantages

- Programs not constrained by the physical memory space
 - Can be as large as the virtual address space will allow
 - Timeline:
 - 1970s: 32-bit virtual addresses → 4 GB of memory
 - 2000s: 64-bit virtual addresses → 16 EB of memory
 - In both periods, that amount of real memory would cost millions of euro
- Better multiprogramming: more processes can be maintained in memory at any given time
 - More likely that one of these processes will be in ready state
- Less I/O is needed to load a program or to swap it
 - increase in CPU utilisation and throughput



Thrashing




- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
 - Low CPU utilization
 - Operating system spends most of its time swapping to disk
- *Thrashing* = a process is busy swapping pages in and out



- Questions:
 - How do we detect Thrashing?
 - What is best response to Thrashing?

Page Faults and Thrashing

- The page fault rate is a good indicator of thrashing
- In order to minimise thrashing, the OS should vary the size of a process's resident set (resident set management) according to some rules:
 - If a process is faulting heavily, allocate more frames to it
 - If faulting very little, take away some frames from it





Memory Management in VM

In a system with VM, the OS must mainly deal with two memory management issues:

1. Replacement policy

- What happens when a page fault occurs and there is no free frame to swap a page in?
- The OS must select a frame for replacement (to be swapped out to disk) when a new page must be brought in
- Restrictions are usually placed on the page replacement policy:
 - Much of the kernel and control structures of the OS are held on <u>locked</u> frames (cannot be replaced)


2. Resident set management

- Choice of dynamic or static number of frames for each active process
- Choice of replacement type allowed; examples:
 - Limited to pages of the process that caused the page fault
 - Encompassing any frame in main memory



Replacement Policy and Locality

- A good replacement policy should exploit the principle of locality of references
- If memory references were random rather than localised, we would not be able to pin down the working set efficiently
- The cost of being wrong is high: must go to disk
- Must keep important pages in memory, not toss them out





Optimal/Minimum (Min)

- Replaces page that will not be referenced forlongest period of time
- Minimum number of page faults, but impossible to implement (knowledge of future events required)
- Standard yardstick used to gauge other algorithms
- Example Suppose we have the same reference stream:
 - ABCABDADBCB

Ref:	A	В	С	A	В	D	A	D	В	С	В
Page:	Α									С	
2		В									
3			С			D					

 Where will D be brought in? Look for page not referenced farthest in future

MIN: 5 faults

LRU (Last Recently Used)

- Replaces the page that has not been referenced for the longest period of time
- By the principle of locality: it is likely that this page will not be referenced in the near future either
- Almost as good as the optimal policy, but difficult to implement (overheads associated to time keeping)
- Example: A B C D A B C D A B C D

Ref:	Α	В	С	D	A	В	С	D	Α	В	С	D
Page:												
1	A			D			С			В		
a å å2 UCD		В			A			٥			С	
DUBLIN 3			С			В			A			٥

First In First Out (FIFO)

- Frames traversed as a circular buffer, triggered by replacements
- Pages are removed in round-robin style
- Rationale: a page fetched long ago may be now out of use (when main memory is composed by many frames)
- Simple to implement, but some replacements will not be good
- Example: Suppose we have 3 page frames, 4 virtual pages, and following reference stream:
 - ABCABDADBCB

Ref:	A	В	С	Α	В	D	A	D	В	С	В
Ref: Page:											
1	A					D				С	
2		В					A				
3			С						В		

- FIFO: 7 faults.
- When referencing D, replacing A is bad choice, since need A again right away

Page Size Considerations

- Page size is invariably a power of 2, but how do we select it?
- No single best answer:
 - Small page size leads to large page table
 - Example: for a VM of 4 MB (2²²) we would have 4096 pages of 1024 bytes, but only 512 pages of 8192 bytes
 - Memory is better used with smaller page sizes
 - On average, half of the last page is wasted
 - I/O transfer time is small compared to seek and latency, which favours larger pages
 - However locality improves with smaller page size (higher resolution)
- The historical trend is towards larger pages
 - 1990: typically around 4096 bytes; currently: 4 MB and higher



Page Table Structure

- <u>Issue</u>: page tables can take a big portion of memory
 - 2^{m-n} entries required for an m-bit long virtual address with n page offset bits
 - Example: with m = 32 and 4 KB (2¹²) page size → $2^{20} = (1,048,576)$ entries
 - This problem is even more severe with modern 64bit addresses


Solutions:



- Hierarchical paging
- Inverted page table

Hierarchical Paging (Two Levels)


- **Two-level page table:** the m-n page number bits are divided into two sections
 - 1. The first points at an entry in the outer page table, which gives a frame corresponding to a page of the page table proper
 - The second points at an entry within that page of the page table
- Example (using same values as in previous slide): m n = 20 can be divided into two 10-bit numbers
 - Virtual address:





- The 2¹⁰ outer page table entries fit within one 4 KB page
- We only need one frame for the outer page table, and enough frames to reference the pages actually used by the process


Fix for Sparse Address Space: The Two-level



Summary: Two-level Paging Virtual memory view Page Tables Physical memory view *111*1 1111 (level 2) stack 11101 stack 1110 0000 11100 *111*1 0000 10111 01 10110 Page Table *110*0 0000 (level 1) stack null 10000 null 01111 01 01110 heap null *100*0 0000 heap 0111 000 null 01101 data 01100 0101 000 01011 01 data 01010 *010*0 0000 00101 00100 code page2# 00011 0001 0000 code 00010 0000 0000


offset

Summary: Two-level Paging



Inverted Page Table

- For large m a good solution is an inverted page table
 - the inverted page table has one entry per frame of physical memory (so there is only one)
 - each entry includes a PID and page number






- Issue: sequential search (linear inverted page table)
 - for this reason it is usually hashed to speed up access, using linked lists for collisions
 - If no match found: page fault

Inverted Page Table

- With all previous examples ("Forward Page Tables")
 - Size of page table is at least as large as amount of virtual memory allocated to processes
 - Physical memory may be much less
 - Much of process space may be out on disk or not in us






- Answer: use a hash table
 - Called an "Inverted Page Table"
 - Size is independent of virtual address space
 - Directly related to amount of physical memory
 - Very attractive option for 64-bit address spaces
- Cons: Complexity of managing hash changes
 - Often in hardware!

Summary: Inverted Table

page # offset



Address Translation Comparison

	Advantages	Disadvantages
Simple Segmentation	Fast context switching: Segment mapping maintained by CPU	External fragmentation
Paging (single- level page)	No external fragmentation, fast easy allocation	Large table size ~ virtual memory Internal fragmentation
Paged segmentation	Table size ~ # of pages in virtual	Multiple memory references per page access
Two-level pages	memory, fast easy allocation	
Inverted Table	Table size ~ # of pages in physical memory	Hash function more complex



Conclusion

- **Cache:** A repository for copies that can be accessed more quickly than original
- Virtual Memory: Illusion supported by system hardware and software that a process has a vast and linear expanse of available memory
- **Principle of Locality:** Program likely to access a relatively small portion of the address space at any instant of time.
 - Temporal Locality, Spatial Locality
- VM is commonly implemented by demand paging
- Working Set: Set of pages touched by a process recently
- Resident Set: Portion of process that is in main memory at a given time
- Thrashing: A process is busy swapping pages in and out
 - Process will thrash if working set doesn't fit in memory
 - Need to swap out a process



Conclusion (cont'd)

- A good replacement policy should exploit the principle of locality of references
- Replacement policies
 - **FIFO:** Place pages on queue, replace page at end
 - MIN: Replace page that will be used farthest in future (optimal)
 - LRU: Replace page used farthest in past
- Multi-Level Tables
 - Virtual address mapped to series of tables
 - Permit sparse population of address space
- Inverted Page table
 - Size of page table related to physical memory size

