COMP 10280 Programming I (Conversion)

John Dunnion

School of Computer Science University College Dublin

COMP 10280 Programming I (Conversion)/Lecture 19

Outline

Representing Numbers

Decimal Integers

Binary Integers

Octal Integers

Hexadecimal Integers

Signed numbers

Floating-point numbers

resenting Numbers Decimal Integers Binary Integers Octal Integers Hexadecimal Integers Signed numbers Floatin

Representing Numbers

- We have seen previously how to represent numbers
- In everyday life, we normally (but not always!) use denary or decimal (Base 10) digits to represent numbers: 0–9
- In computer systems, we use binary (Base 2) digits to represent numbers: 0 and 1
- For convenience, humans often interpret a binary number as an octal (Base 8) or hexadecimal (Base 16) number
- To regard a binary number in octal, we take the number in groups of three bits
- To regard a binary number in hexadecimal, we take the number in groups of four bits

Representing decimal integers (1)

- In everyday life, we use a positional number system
- In a positional number system, the value of a digit is determined by its position in the number
- Consider the number 4592:
 - The 4 is worth 4000 (it appears in the 1000s position)
 - The 5 is worth 500 (it appears in the 100s position)
 - The 9 is worth 90 (it appears in the 10s position)
 - The 2 is worth 2 (it appears in the 1s (units) position)
- Formally, the digits in a decimal number are weighted by increasing powers of 10: they use Base 10
- Thus 4592 can be written as

$$4 \times 10^3 + 5 \times 10^2 + 9 \times 10^1 + 2 \times 10^0$$

• (Recall that $10^0 = 1$)

presenting Numbers Decimal Integers Binary Integers Octal Integers Hexadecimal Integers Signed numbers Floating-p

Representing decimal integers (2)

- The Least Significant Digit is the rightmost one
- This is the 2 in 4592
- It has the lowest power of 10 weighting
- Digits towards the right-hand side are called the "low-order digits" (lower powers of 10)
- The Most Significant Digit is the leftmost one
- This is the 4 in 4592
- It has the highest power of 10 weighting
- Digits towards the left-hand side are called the "high-order digits" (higher powers of 10)

The largest *n*-digit decimal integer

- What is the largest n-digit number?
- It is made up of n successive 9s
- The largest four-digit decimal number is 9999
- 9999 is 10⁴ 1

Representing binary integers (1)

- Binary numbers are numbers in Base 2
- There are only two digits: 0 and 1
- Binary numbers also use a positional number system
- Formally, the digits in a decimal number are weighted by increasing powers of 2: they use Base 2
- Consider the number 1011
- 1011 can be written as

$$1 \times 2^3 + 0 \times 2^2 + 1 \times 2^1 + 1 \times 2^0$$

- (Recall that $2^0 = 1$)
- In the number 1011:
 - The first 1 is worth 2³ (or 8) (it appears in the 2³ position)
 - The second 1 is worth 2¹ (or 2) (it appears in the 2¹ position)
 - The third 1 is worth 2⁰ (or 1) (it appears in the 2⁰ position)

esenting Numbers Decimal Integers Binary Integers Octal Integers Hexadecimal Integers Signed numbers Floating

Representing binary integers (2)

- The Least Significant Digit is the rightmost one
- In binary numbers, we refer to the Least Significant Bit:
 "bit" = "binary digit"
- This is the rightmost 1 in 1011
- It has the lowest power of 2 weighting
- Bits towards the right-hand side are called the "low-order bits" (lower powers of 2)
- The Most Significant Bit is the leftmost one
- This is the leftmost 1 in 1011
- It has the highest power of 2 weighting
- Bits towards the left-hand side are called the "high-order bits" (higher powers of 2)

The largest *n*-digit binary integer

- What is the largest n-digit binary number?
- It is made up of n successive 1s
- The largest four-digit number is 1111
- 1111 is 2⁴ 1

Converting from binary to decimal

- Convert the following binary numbers to decimal:
- 1011

•
$$1011 = 1 \times 2^3 + 0 \times 2^2 + 1 \times 2^1 + 1 \times 2^0 = 8 + 2 + 1 = 11$$

• 0111 1111

• 0111 1111 =
$$0 \times 2^7 + 2^6 + 2^5 + 2^4 + 2^3 + 2^2 + 2^1 + 2^0 = 0 + 64 + 32 + 16 + 8 + 4 + 2 + 1 = 127$$

- 1000 1000
- $1000\ 1000 = 2^7 + 2^3 = 128 + 8 = 136$

Converting from decimal to binary (1)

- To convert a number from decimal to another base, we successively divide the number by the new base
- The remainder after each division becomes a digit in the new base until the result of the division is 0
- The result is read upwards
- Example: Convert 39 to binary

| Division | Quotient | Remainder |
|----------|----------|-----------|
| 39 / 2 | 19 | 1 |
| 19/2 | 9 | 1 |
| 9/2 | 4 | 1 |
| 4 / 2 | 2 | 0 |
| 2/2 | 1 | 0 |
| 1 / 2 | 0 | 1 |
| 0 / 2 | STOP | |

• Thus $39_{10} = 100111_2$

Converting from decimal to binary (2)

Example: Convert 4592 to binary

| Division | Quotient | Remainder |
|----------|----------|-----------|
| 4592 / 2 | 2296 | 0 |
| 2296 / 2 | 1148 | 0 |
| 1148 / 2 | 574 | 0 |
| 574 / 2 | 287 | 0 |
| 287 / 2 | 143 | 1 |
| 143 / 2 | 71 | 1 |
| 71 / 2 | 35 | 1 |
| 35 / 2 | 17 | 1 |
| 17 / 2 | 8 | 1 |
| 8/2 | 4 | 0 |
| 4/2 | 2 | 0 |
| 2/2 | 1 | 0 |
| 1/2 | 0 | 1 |
| 0/2 | STOP | |

• Thus $4592_{10} = 10001111110000_2$

Representing octal integers (1)

- Octal numbers are numbers in Base 8
- There are eight digits: 0–7
- Octal numbers also use a positional number system
- Formally, the digits in an octal number are weighted by increasing powers of 8: they use Base 8
- Consider the number 5738
- 573₈ can be written as

$$5\times 8^2 + 7\times 8^1 + 3\times 8^0 = 379_{10}$$

- (Recall that $8^0 = 1$)
- In the number 573₈:
 - The 5 is worth 5×8^2 (or 320) (it appears in the 8^2 position)
 - The 7 is worth 7×8^1 (or 56) (it appears in the 8^1 position)
 - The 3 is worth 3×8^0 (or 3) (it appears in the 8^0 position)

Converting from decimal to octal (1)

Example: Convert 379 to octal

| Division | Quotient | Remainder |
|----------|----------|-----------|
| 379 / 8 | 47 | 3 |
| 47 / 8 | 5 | 7 |
| 5/8 | 0 | 5 |
| 0/2 | STOP | |

• Thus $379_{10} = 573_8$

Converting from decimal to octal (2)

Example: Convert 4592 to octal

| Division | Quotient | Remainder |
|----------|----------|-----------|
| 4592 / 8 | 574 | 0 |
| 574 / 8 | 71 | 6 |
| 71 / 8 | 8 | 7 |
| 8/8 | 1 | 0 |
| 1/8 | 0 | 1 |
| 0/8 | STOP | |

• Thus $4592_{10} = 10760_8$

presenting Numbers Decimal Integers Binary Integers Octal Integers Hexadecimal Integers Signed numbers Floating-

Interpreting a binary number as octal

- We can interpret a binary number as an octal number by taking the binary digits in groups of three from the right to left (lowest-significant digit to highest-significant digit)
- $4592_{10} = 1\,0001\,1111\,0000_2$
- Re-arranging the binary number in groups of three bits:
- 1 000 111 110 000
- Convert each group of three bits into an octal digit:
- 10760
- 10760₈

Representing hexadecimal integers (1)

- Hexadecimal numbers are numbers in Base 16
- There are 16 digits: 0, 1, 2, 3, 4, 5, 6, 7, 8, 9, A, B, C, D, E and F
- A represents 10, B represents 11, ..., F represents 15
- Hexadecimal numbers use a positional number system
- Formally, the digits in a hexadecimal number are weighted by increasing powers of 16: they use Base 16
- Consider the number 9B3₁₆
- 9B3₁₆ can be written as

$$9\times 16^2 + 11\times 16^1 + 3\times 16^0 = 2304 + 176 + 3 = 2483_{10}$$

- In the number 9B38:
 - The 9 is worth 9×16^2 (or 2304) (it appears in the 16^2 position)
 - The B is worth 11×16^1 (or 176) (it appears in the 16^1 position)
 - The 3 is worth 3×16^0 (or 3) (it appears in the 16^0 position)

Converting from decimal to hexadecimal (1)

· Example: Convert 379 to hexadecimal

| Division | Quotient | Remainder |
|-----------|----------|-----------|
| 2483 / 16 | 155 | 3 |
| 155 / 16 | 9 | 11 |
| 9 / 16 | 0 | 9 |
| 0 / 16 | STOP | |

• Thus $2483_{10} = 9B3_{16}$

Converting from decimal to hexadecimal (2)

Example: Convert 4592 to hexadecimal

| Division | Quotient | Remainder |
|-----------|----------|-----------|
| 4592 / 16 | 287 | 0 |
| 287 / 16 | 17 | 15 |
| 17 / 16 | 1 | 1 |
| 1 / 16 | 0 | 1 |
| 0 / 16 | STOP | |

• Thus $4592_{10} = 11F0_{16}$

Interpreting a binary number as hexadecimal

- We can interpret a binary number as a hexadecimal number by taking the binary digits in groups of four from the right to left (lowest-significant digit to highest-significant digit)
- $4592_{10} = 1\,0001\,1111\,0000_2$
- Convert each group of four bits into a hexadecimal digit:
- 11F0
- 11F0₁₆

Signed numbers

- Humans use a symbol, + or to represent whether a number is positive (> 0) or negative (< 0)
- · Computers don't have such symbols
- Computers have to use a 1 or a 0 to represent sign
- There are three common techniques for representing signed numbers:
 - Signed magnitude
 - · One's complement
 - Two's complement

Signed magnitude representation

- Sometimes called sign-magnitude or sign and magnitude representation
- In signed magnitude representation, we designate the leftmost bit (most significant bit) as a sign bit
- The sign bit indicates whether a number is positive or negative:
 - · 0 sign bit: positive number
 - 1 sign bit: negative number
- The remaining bits give the magnitude of the number
- +13 would be represented as 0000 1101
- -13 would be represented as 1000 1101

Issues with signed magnitude representation

- The range of signed magnitude numbers is -2^{n-1} to $+2^{n-1}$
- Advantages:
 - · Conceptually simple
 - Symmetric range
- Disadvantages:
 - Difficult to do arithmetic with negative values
 - Two representations of zero
 - +0: 0000 0000
 - -0: 1000 0000

One's complement representation

- In one's complement representation, a negative number is represented by applying the bitwise NOT operator to a number
- "Flip the bits"
- Example:
- +13 would be represented as 0000 1101
- -13 would be represented as 1111 0010

Representing numbers in one's complement representation

| Number | Bits |
|--------|-----------|
| +0 | 0000 0000 |
| +1 | 0000 0001 |
| +2 | 0000 0010 |
| +126 | 0111 1110 |
| +127 | 0111 1111 |
| -0 | 1111 1111 |
| -1 | 1111 1110 |
| -2 | 1111 1101 |
| -126 | 1000 0001 |
| -127 | 1000 0000 |

Issues with one's complement representation

- The range of signed magnitude numbers is $-2^{n-1} 1$ to $+2^{n-1} 1$
- The most significant digit acts as a sign bit
- The most significant digit represents $-2^{n-1} 1$
- Advantages:
 - Easier to do arithmetic with negative values
 - Symmetric range
- Disadvantages:
 - · More difficult for humans to understand
 - Two representations of zero
 - +0: 0000 0000
 - · -0: 1111 1111

Two's complement representation

- In two's complement representation, a negative number is represented by applying the bitwise NOT operator to a number and adding one
- "Flip the bits and add one"
- Examples:
- +13 would be represented as 0000 1101
- -13 would be represented as 1111 0011
- +30 would be represented as 0001 1110
- -30 would be represented as 1110 0010

Representing numbers in two's complement representation

| Number | Bits |
|--------|-----------|
| +0 | 0000 0000 |
| +1 | 0000 0001 |
| +2 | 0000 0010 |
| +126 | 0111 1110 |
| +127 | 0111 1111 |
| -1 | 1111 1111 |
| -2 | 1111 1110 |
| -3 | 1111 1101 |
| -127 | 1000 0001 |
| -128 | 1000 0000 |

Issues with two's complement representation

- The range of two's complement numbers is -2^{n-1} to $+2^{n-1}-1$
- The most significant digit acts as a sign bit
- The most significant digit represents -2ⁿ⁻¹
- Advantages:
 - Arithmetic with negative values is identical to arithmetic with positive values
 - · Single representation of zero
- Disadvantages:
 - More difficult for humans to understand
 - · Asymmetric range

Floating-point numbers

- A representation of real numbers
- An approximation
- A trade-off between precision (accuracy) and range
- In general, a real number is represented approximately by a floating-point number:
 - A fixed number of significant digits: the mantissa (or the coefficient, or the significand, according to the IEEE Standard)
 - The exponent (the scale that is applied to the mantissa)

Representing floating-point numbers (1)

- Consider the number 123.456
- This can be represented by 123456×10^{-3}
- It can also be represented by $1.23456 \times 10^{+2}$
- This is the normalised form. In Base 2, the 1.23456 is called a normalised significand
- It can also be represented by $0.123456 \times 10^{+3}$
- In Base 2, the .123456 is called a normed significand

Representing floating-point numbers (2)

- What do we need to store?
- The normalised/normed significand
- The exponent
- The sign of the number
- We do not need to store:
- The position of the decimal/binary point
- · The base of the exponent

presenting Numbers Decimal Integers Binary Integers Octal Integers Hexadecimal Integers Signed numbers Floating

Single-precision floating-point

- Usually used to represent the float type in the C language family
- 32 bits (Four 8-bit bytes)
- · One sign bit
- 23 bits for the significand (about seven decimal digits)
- 7 bits for the exponent
- Largest number: 3.4 × 10³⁸
- Smallest number: 1.2×10^{-38}

presenting Numbers Decimal Integers Binary Integers Octal Integers Hexadecimal Integers Signed numbers Floating

Double-precision floating-point

- Usually used to represent the double type in the C language family
- 64 bits (eight 8-bit bytes)
- One sign bit
- 52 bits for the significand (about 16 decimal digits)
- 11 bits for the exponent
- Largest number: 1.8 × 10³⁰⁸
- Smallest number: 5.0×10^{-324}

Issues with floating-point representation

- Only an approximation
- Often (usually?) converting from decimal to binary
- Overflow: The number is too large to be represented in the exponent field
- Underflow: The number is too small to be represented in the exponent field
- To reduce the chances of underflow/overflow, we can use 64-bit double-precision representation
- Two representations of zero. These must be considered to be equal when compared
- There are special positive and negative infinity values,
 +INF and -INF
- There are special Not a Number values (NaN). These represent the result of various undefined calculations (eg multiplying 0 and infinity)

Showing the imprecision of floating-point arit

Floating-point program example (1)

Consider the following Python 2.x program:

```
x = 0.0
for i in range(10):
    x += 0.1
    print 'x is', x

if x == 1.0:
    print x, 'is equal to 1.0.'
else:
    print x, 'is not equal to 1.0.'
```

Floating-point program example (2)

This produces the following output:

```
x is 0.1
x is 0.2
x is 0.3
x is 0.4
x is 0.5
x is 0.6
x is 0.7
x is 0.8
x is 0.9
x is 1.0
1.0 is not equal to 1.0.
```

Showing the imprecision of floating-point arit

Floating-point program example (3)

Here is the equivalent Python 3 program:

```
x = 0.0
for i in range(10):
    x += 0.1
    print('x is', x)

if x == 1.0:
    print(x, 'is equal to 1.0.')
else:
    print(x, 'is not equal to 1.0.')
```

Floating-point program example (4)

This produces the following output:

```
x is 0.1
x is 0.2
x is 0.30000000000000004
x is 0.4
x is 0.5
x is 0.6
x is 0.7
x is 0.799999999999999
x is 0.899999999999999
x is 0.999999999999999
```