



Bayanaty Integration with Anoud

Service Specification Document

1. Purpose.....	
2. Technical Specifications	
3. Application Constants.....	
4. Service Operations	
4.1. Bayanaty with Chassis Number	
4.1.1 Vehicle Details Info.....	
4.1.2 Vehicle Imported Details Info	4
4.1.3 Vehicle Sepcification Info	5
4.2. Bayanaty without Chassis Number	8
4.2.1 Vehicle Valuation Info	8
4.2.2 Vehicle BodyType Info.....	9
4.2.3 Vehicle EngineCapacity Info	10
4.2.4 Vehicle Trims Info.....	11

1. Purpose

This document details web service specifications for the development of the BAYANATY APIs. It contains details about the operations included as part of these API's service along with its request and response parameters.

2. Technical Specifications

Service URL	https://www.devapi.anoudapps.com/qicservices/aggregator
Bayanaty Service URL	https://www.devapi.anoudapps.com/qicservices/aggregator/bayanaty
Header Parameter	Company ('002' for Dubai), Authorization (Basic Authentication)
Service description	This API service provides following functionalities – 1. Vehicle Detail Services 2. Vehicle Imported Detail Services 3. Vehicle Specification Check Services 4. Vehicle Valuation Services

3. Application Constants

Application User ID	<aggregator specific>
Application Password	<aggregator specific>

4. Service Operations

4.1 Bayanaty with Chassis Number

4.1.1 Vehicle Details Info

Service Method Name

Name	Description	Return Type
vehicleDetails	To Get the Vehicle Details by providing the chassis number	JSON Object

Input Parameters

Name	Type	Description	Name
Vin	STRING	Yes	Chassis Number

Response Parameters

Name	Type	Description
StatusCode	NUMBER	Status code representing success/failure
ImportedDetails	ARRAY	List of Imported details Array. Refer " Imported Details "
VehicleFeatures	ARRAY	List of Vehicle Feature Array. Refer " VehicleFeatures "
errMessage	STRING	Error Message (if any)
respCode	STRING	Success/Failure Codes
vin	STRING	Chassis number
companyCode	STRING	002

Imported Details

Name	Type	Description
Vin	STRING	Vehicle Identification Number
Imported	BOOLEAN	Indicates if the vehicle was imported
GccSpec	BOOLEAN	Indicates GCC specifications
Faults	BOOLEAN	Indicates if faults were found
Mileage	NUMBER	Recorded mileage of the vehicle

VehicleFeatures

Name	Type	Description
vin	STRING	Chassis Number
PrimaryFeatures	ARRAY	List of Vehicle Primary Feature Array. Refer " PrimaryFeatures "
OtherFeatures	ARRAY	List of Vehicle Other Features Array. Refer " OtherFeatures "
EngineDetails	ARRAY	List of Vehicle Engine Details Array. Refer " EngineDetails "
VehicleValues	ARRAY	List of Vehicle Values Array. Refer " VehicleValues "

PrimaryFeatures

Name	Type	Description
ModelYear	NUMBER	Manufacturing model year
ProductionDate	STRING	Production date of the vehicle
Make.Id	NUMBER	Make identifier
Make.Value	STRING	Make value (e.g., "Toyota")
Model.Id	NUMBER	Model identifier
Model.Value	STRING	Model value (e.g., "Camry")
Trim.id	NUMBER	Trim id
Trim.Value	STRING	Trim value (e.g., "LE", "XSE")
BodyType.id	NUMBER	BodyType id
BodyType.Value	STRING	Body type (e.g., "Sedan")
EngineCapacity.id	NUMBER	Engine Capacity id
EngineCapacity.Value	STRING	Engine capacity value
ExteriorColour.id	NUMBER	Exterior color
Doors	NUMBER	Number of doors
Seats	NUMBER	Number of seats
ApproxMileage	NUMBER	Approximate mileage

OtherFeatures

Name	Type	Description
DriveTrain.id	NUMBER	Drivetrain id
DriveTrain.value	STRING	Drivetrain value
DriveTrain.desc	STRING	Drivetrain type (e.g., "AWD")
Steering.id	NUMBER	Steering type (e.g., "Left")
Transmission.id	NUMBER	Transmission id
Transmission.Value	STRING	Transmission type (e.g., "Automatic")
FuelType.id	STRING	Fuel type (e.g., "Petrol")

EngineDetails

Name	Type	Description
EngineNumber	STRING	Engine serial number
CapacityLiters	STRING	Engine capacity in liters
CapacityCc	NUMBER	Engine capacity in cc
Cylinders	NUMBER	Number of engine cylinders
BrakeHorsePower	NUMBER	Horsepower rating
Torque	NUMBER	Engine torque value

VehicleValues

Name	Type	Description
CurrencyCode	STRING	Currency code (e.g., "SAR")
Maximum	NUMBER	Maximum vehicle value
Actual	NUMBER	Actual evaluated vehicle value
Minimum	NUMBER	Minimum vehicle value

4.1.2 Vehicle Imported Details**Service Method Name**

Name	Description	Return Type
vehicleImpDetails	To get Vehicle Imported Information available.	JSON Object

Input Parameters

Name	Type	Required	Description
Vin	STRING	Yes	Chassis Number

Response Parameters

Name	Type	Description
StatusCode	NUMBER	Status code representing success/failure
importedDetails	ARRAY	List of imported details Array. Refer " vehicleImpDetails "

Anoud Bayanaty Integration

errMessage	STRING	Error Message (if any)
respCode	STRING	Success/Failure Codes
vin	STRING	Chassis number
companyCode	STRING	002

ImportedDetails

Name	Type	Description
vin	STRING	Currency code (e.g., "SAR")
imported	Boolean	Indicates if the vehicle was imported
gccSpec	Boolean	To indicate GCC specifications
faults	Boolean	Indicates if fault was found
mileage	NUMBER	Mileage value of vehicle

4.1.3 Vehicle Specification Info

Service Method Name

Name	Description	Return Type
getVehicleSpecDetails	Used to update Vehicle Specification Information to the Lead	JSON Object

Input Parameters

Name	Type	Required	Description
Vin	STRING	Yes	Chassis Number

Response Parameters

Name	Type	Description
StatusCode	NUMBER	Status code representing success/failure
VehicleFeatures	ARRAY	List of vehicleFeatures Array. Refer " vehicleFeatures "

VehicleFeatures

Name	Type	Description
Vin	STRING	Chassis Number
primaryFeatures	ARRAY	List of primaryFeatures Array. Refer “primaryFeatures”

PrimaryFeatures

Name	Type	Description
ModelYear	NUMBER	Vehicle model year
ProductionDate	STRING	Production date of the vehicle
Make.Id	NUMBER	Make ID
Make.Value	STRING	Make name
Model.Id	NUMBER	Model ID
Model.Value	STRING	Model name
Trim.Id	NUMBER	Trim ID
Trim.Value	STRING	Trim name
BodyType.Id	NUMBER	Body type ID
BodyType.Value	STRING	Body type name
EngineCapacity.Id	NUMBER	Engine capacity ID
EngineCapacity.Value	STRING	Engine capacity (e.g., "2.5L")
ExteriorColour.Id	NUMBER	Exterior color ID
ExteriorColour.Value	STRING	Exterior color name
Doors	NUMBER	Number of doors

Anoud Bayanaty Integration

Seats	NUMBER	Number of seats
ApproxMileage	NUMBER	Approximate mileage

4.2 Bayanaty without Chassis Number

4.2.1 Vehicle Valuation Info

Service Method Name

Name	Description	Return Type
vehicleValuation	Get Vehicle Valuation Details	JSON Object

Input Parameters

Name	Type	Required	Description
ModelYear	NUMBER	Yes	Manufacturing model year of the vehicle
Makeld	NUMBER	Yes	Identifier of the vehicle make
ModelId	NUMBER	Yes	Identifier of the vehicle model
TrimId	NUMBER	Yes	Identifier of the vehicle trim
BodyTypeId	NUMBER	Yes	Identifier of the body type
EngineCapacityId	NUMBER	Yes	Identifier of the engine capacity
TransmissionId	NUMBER	No	Identifier of the transmission type
IsGccSpec	BOOLEAN	Yes	Indicates if the vehicle is GCC specification
Mileage	NUMBER	No	Current or expected mileage of the vehicle
Vin	STRING	No	Vehicle Identification Number
IsBrandNew	BOOLEAN	No	Indicates if the vehicle is brand new
ValuationDate	STRING	No	Date of the valuation in ISO 8601 format (e.g., 2025-05-28T11:13:07.642Z)

Response Parameters

Name	Type	Description
StatusCode	NUMBER	Status code representing success/failure
Description	STRING	Description of the response
VehicleValues	ARRAY	List of VehicleValues Array. Refer "VehicleValues".
errMessage	STRING	Error Message (if any)
respCode	STRING	Success/Failure Codes
vin	STRING	Chassis number
companyCode	STRING	002

VehicleValues

Name	Type	Description
currencyCode	STRING	Currency code of the vehicle value.
maximum	NUMBER	Maximum value of the Vehicle
actual	NUMBER	Actual value of the Vehicle
minimum	NUMBER	Minimum value of the Vehicle

4.2.2 Vehicle Body Type Info

Service Method Name

Name	Description	Return Type
bodyType	To get Vehicle Body Type Details	JSON Object

Input Parameters

Name	Type	Required	Description
ModelYear	NUMBER	Yes	Manufacturing model year of the vehicle
Makeld	NUMBER	Yes	Identifier of the vehicle make
ModelId	NUMBER	Yes	Identifier of the vehicle model
TrimId	NUMBER	Yes	Identifier of the vehicle trim

Response Parameters

Name	Type	Description
StatusCode	NUMBER	Status code representing success/failure
vehicleFeatures	ARRAY	List of vehicleFeatures Array. Refer “vehicleFeatures”
errMessage	STRING	Error Message (if any)
respCode	STRING	Success/Failure Codes
companyCode	STRING	002

VehicleFeatures

Name	Type	Description
primaryFeatures	ARRAY	List of primaryFeatures Array. Refer “primaryFeatures”

PrimaryFeatures

Name	Type	Description
bodyTypeList.id	NUMBER	BodyTypeList id
bodyTypeList.value	STRING	BodyTypeList id value

4.2.3 Vehicle Engine Capacity Info

Service Method Name

Name	Description	Return Type
engineCapacities	Get Vehicle Engine Capacity Details	JSON Object

Input Parameters

Name	Type	Required	Description
ModelYear	NUMBER	Yes	Manufacturing model year of the vehicle
Makeld	NUMBER	Yes	Identifier of the vehicle make
ModelId	NUMBER	Yes	Identifier of the vehicle model
TrimId	NUMBER	Yes	Identifier of the vehicle trim
BodyTypeId	NUMBER	Yes	Identifier of the body type

Response Parameters

Name	Type	Description
StatusCode	NUMBER	Status code representing success/failure
vehicleFeatures	ARRAY	List of vehicleFeatures Array. Refer “vehicleFeature”
errMessage	STRING	Error Message (if any)
respCode	STRING	Success/Failure Codes
companyCode	STRING	002

VehicleFeatures

Name	Type	Description
otherFeatures	ARRAY	List of otherFeatures Array. Refer “otherFeatures”

OtherFeatures

Name	Type	Description
engineCapacitiesList.id	NUMBER	Id of engineCapacitiesList
engineCapacitiesList.value	STRING	Value of the engineCapacitiesList

4.2.4 Vehicle Trims Info

Service Method Name

Name	Description	Return Type
trims	Get Vehicle trim Id Details	JSON Object

Input Parameters

Name	Type	Required	Description
ModelYear	NUMBER	Yes	Manufacturing model year of the vehicle
Makeld	NUMBER	Yes	Identifier of the vehicle make
ModelId	NUMBER	Yes	Identifier of the vehicle model

Response Parameters

Name	Type	Description
StatusCode	NUMBER	Status code representing success/failure
vehicleFeatures	ARRAY	List of vehicleFeatures Array. Refer " vehicleFeatures "
errMessage	STRING	Error Message (if any)
respCode	STRING	Success/Failure Codes
companyCode	STRING	002

VehicleFeatures

Name	Type	Description
primaryFeatures	ARRAY	List of primaryFeatures Array. Refer " primaryFeatures "

PrimaryFeatures

Name	Type	Description
trimList.id	NUMBER	Id of trimList
trimList.value	STRING	Value of the trimList.