

Odoo IoT für Digital Signage Administrator Manual

Abilium GmbH / University of Bern (PSE FS26)

Contents

1	Introduction	2
2	Start Odoo and install the module	2
2.1	Docker quick start	2
2.2	Install TRMNL in Odoo	2
2.3	Before pairing devices (Docker / LAN)	3
3	Set up the TRMNL display	3
3.1	Hardware and captive portal	3
3.2	When the device appears in Odoo	3
4	Configure the display (profile)	3
4.1	Create a profile	5
4.2	After saving	5
5	Administrator reference	6
5.1	TRMNL menu	6
5.2	Display Policy	6
5.3	System parameters	6
6	Troubleshooting	6
7	Further reading	7
8	Development team	7

Introduction

This manual is for **Odoo administrators** who install and operate the TRMNL module. The TRMNL menu (**Devices, Profiles, Display Policy**) is visible only to **Settings / Administrator** users (`base.group_system`).

Repository: https://github.com/Abilium-GmbH/pse_trmnl_odoo_connector

For end-user pairing details and profile layout options, see the User Guide in `docs/overleaf/`.

Start Odoo and install the module

Docker quick start

From the repository root:

1. Clone the project and run `make` (starts PostgreSQL and Odoo; on a fresh database installs `base` and `trmnl`).
2. Open <http://localhost:8069>. Default login: `admin / admin`.
3. See `README.md` and `docs/development.md` for `make watch`, `make test`, and other commands.

Install TRMNL in Odoo

1. Open **Apps** (Figure 1).
2. Remove the **Apps** filter from the search bar so modules are visible.
3. Search for **TRMNL** (Figure 2).
4. Click **Activate** or **Install** on the TRMNL module card.




Figure 1: Odoo Apps screen before searching for TRMNL.

Dependencies: the module manifest requires only `base` and `web`. Installing TRMNL does **not** automatically install the Odoo **Calendar** app. Install Calendar separately if you need calendar profiles on `calendar.event`.

On install, a `post_init_hook` seeds default and unauthorized fallback images as public attachments.




Figure 2: Search result for the TRMNL module.

Before pairing devices (Docker / LAN)

Set reachable URLs in **Settings** → **Technical** → **System Parameters**:

- `web.base.url` = your LAN address, e.g. `http://192.168.1.50:8069` (not `localhost`).
- Optionally `trmnl.public_base_url` to the same value.

Polls may use the request Host header at runtime, but that value is **not** saved automatically. Set the parameters manually to avoid profile **URL Warning** issues.

Set up the TRMNL display

Hardware and captive portal

1. Turn on the device and connect your phone or laptop to the **TRMNL** Wi-Fi network.
2. Open the captive portal (typically `http://10.254.0.1`).
3. Open **Advanced** and click **Soft Reset** first if the device was previously linked to TRMNL cloud.
4. Click **Custom Server** and enter your Odoo URL, e.g. `http://192.168.1.50:8069`.
5. Return to **Wi-Fi Configuration**, select your network, enter the password, and click **Connect**.

When the device appears in Odoo

Open **TRMNL** → **Devices**. Device records are created by the hardware; you cannot click **New** on the list.

Depending on **Display Policy** (default: **Respond with an error**), the device may first appear as **Unknown Device** or **Token Mismatch**. Use **Accept Device** when a token has been stored, or change the policy under **TRMNL** → **Display Policy**.

Configure the display (profile)




Figure 3: TRMNL captive portal: Wi-Fi configuration, Advanced settings, Soft Reset, Custom Server, and API Server field.

Create a profile

Open **TRMNL** → **Profiles** → **New**.

The figure consists of two screenshots of the TRMNL web interface. The top screenshot shows the 'New' profile form. It has a purple header with 'TRMNL', 'Devices', 'Profiles', and 'Display Policy'. The 'Profiles' tab is active. The form has sections: 'IDENTITY' with 'Name' (circled 1), 'Device', and 'Active' (toggle); 'DATA SOURCE' with 'Odoo Model' (circled 3); and 'DEVICE DELIVERY STATUS' with 'Device Last Polled', 'Next Expected Poll', and 'Device Refresh Rate'. A red circle 2 highlights the 'Name' label. A red circle 5 highlights the top navigation bar. The bottom screenshot shows the 'Render Preview' button (circled 4) and the form filled with example data: Name 'ExampleProfile', Device 'TRMNL-9F2AC8', Active 'On', Odoo Model 'TRMNL Profile', View Type 'List', and Users.

Figure 4: Profile form: (1) name field, (2) name label, (3) Data Source, (4) Render Preview after a model is selected, (5) standard Odoo save.

#	Area	What to do
1–2	Name	Enter a label for the profile (e.g. “Office calendar”).
	Device	Select the registered TRMNL.
	Active	Leave enabled so the profile can be used for display.
3	Data Source	Choose Odoo Model (only models from installed apps). After selection, default layout options are filled automatically.
4	Render Preview	Appears once a model is selected. Generates the PNG stored in Odoo (same bytes the device downloads).

After saving

- Click **Render Preview** to verify the PNG in the form.

- Wait for the device poll, or set **Refresh Rate** to 1 minute on the device record for testing.
- If multiple profiles exist on one device, the **lowest sequence** active profile is used.

Administrator reference

TRMNL menu

Menu	Purpose
TRMNL → Devices	Device list, telemetry, refresh rate, logs, Accept / Reset / Remove.
TRMNL → Profiles	Configure rendered content and preview PNGs.
TRMNL → Display Policy	Global rule for unknown or token-mismatched devices.

Display Policy

Policy	Behavior
Respond with an error (default)	Unauthorized image; manual Accept Device when ready.
Automatically accept the device	Adopts token and serves display on the same poll.
Send a reset command	Returns {"status": 500} and deletes the device record.

System parameters

Key	Purpose
web.base.url	Public Odoo base URL reachable from devices.
trmnl.public_base_url	Optional override for profile image URLs.
trmnl.display_unknown_device_policy	error, auto_accept, or factory_reset.
trmnl.api_debug	Set True for verbose API logging.

Troubleshooting

Issue	Action
Device not in Odoo	Check Custom Server URL, firewall, Soft Reset, Wi-Fi.
Unauthorized image	Check Display Policy; Accept Device if needed.
Profile URL Warning	Set web.base.url / trmnl.public_base_url manually.
No device logs	/api/log only works for Accepted devices with valid token.
Calendar empty on device	Use model Calendar Event and install Calendar app.

Further reading

Document	Content
<code>user_guide.pdf</code>	User Guide (pairing, layouts, troubleshooting)
<code>design_documentation.md</code>	Architecture, HTTP API, security
<code>development.md</code>	Make targets and tests

Development team

Role	Name
Key Account Manager	Timur Umut Turgul
Chief Deliverable Officer	Sascha Friedli
Quality Evangelist	Leila Ayinkamiye
Master Tracker	Claudio Berger