MY SITUATION ROOM

Platform Administrator Manual

Election observation & real-time collation

An AI Brains Ventures production

This is the guide for **you, the platform owner** (AI Brains Ventures). Your account is the **platform administrator**: the only role that can create and control **Command Centres** (the top-level accounts you hand to clients). Each client then runs their own Command Centre, creates their own Situation Rooms, and their observers report from the field — all sealed off from every other client.

> Audience separation: you create and switch Command Centres on and off. You **cannot** see any client's rooms, observers, photos or audit — that isolation is enforced in the database, by design, for trust. The only thing that crosses between centres is **vote counts**, and only between centres of the same state that you have left in the pool (section 2).

---

0. The three levels at a glance

Level	Who	Logs in at	Creates
Command Centre	A client organisation (e.g. a party, an observer group)	`/command/`	Situation Rooms + operators
Situation Room	An LGA / area supervisor	`/room/`	Observer codes
Observer	A field agent at a polling unit	the Android app or `/observer/`	reports (video, GPS, tallies, EC8A)

You operate at the very top: you create the **Command Centres** themselves.

---

1. Signing in as the administrator

1. Open `https://mysituationroom.com.ng/command/`.
2. Enter your **operator name** (`admin`) and **passcode**.
   - On a brand-new server the first passcode is printed **once** in the server log at first boot (or set by `COMMAND_PASSCODE`). Change it immediately (section 7).
3. If you turned on **two-step login**, enter the 6-digit code from your authenticator app.

You land in the **Main Command Centre**. Because you are the administrator you also see three extra tabs the clients never see: **Command Centres**, **Marketing**, and **Locations**.

---

2. Creating a Command Centre for a client

This is your main job. Go to the **Command Centres** tab.

1. Under **New Command Centre**:
   - **Name** — the client's name, e.g. `Kano State Command` or `Blue Party National`.
   - **State (optional)** — pick one to auto-fill that state's LGAs, wards and polling units for the client. Leave blank for a multi-state client.
   - **First operator name** — *leave blank* and the system makes a unique one from the name (`kano-state-command`, then `-2` if taken). Type one only if you want a specific login name; it

must be unique across the whole platform.
   - **State Collation Officer — name / phone (optional)** — creates the state-level Collation Officer 3 for this client with a sign-in QR.
   - **Operator passcode / Confirm** — *leave blank* to auto-generate a strong one, or type your own (min 8 characters) and confirm it. Use **Show** to check what you typed.
2. Click **Create Command Centre**.
3. A **sign-in card with a QR code** pops up (Copy / Print), and a ready-to-send invite is copied to your clipboard, e.g.:

   ```
   Kano State Command — My Situation Room
   Login: https://mysituationroom.com.ng/command/
   Operator: kano-state-command
   Passcode: REY4YXQDAM
   Open the link, choose "Command Centre", and sign in...
   ```

4. **Send that to the client** (WhatsApp, email), or print the card. They can type the operator name and passcode, or simply **scan the QR** to sign in. That's everything they need to start.

Viewing a client's login again

On the client's row, **Sign-in** shows the operator name, passcode and QR you issued — no need to reset. If the client has since chosen their own passcode it cannot be viewed (Share issues a new one). Issued passcodes are kept encrypted (AES-256-GCM, key derived from `JWT_SECRET`); if you ever change `JWT_SECRET`, old passcodes can no longer be viewed and need a reset.

Re-sending or resetting a client's login

On the client's row in the **Command Centres** list, click **Share**. This **sets a fresh passcode** (the old one stops working) and copies a new invite to send. Use it if a client lost their passcode or you suspect it leaked.

Changing the state a Command Centre is locked to

In the **Command Centres** list, the **State** column is a drop-down for you only. A client whose Command Centre has a state sees that state fixed everywhere (room creation, search, collation) and cannot change it. "— all states —" leaves it unlocked (as your own Main Command Centre is).

Pooling vote counts across Command Centres of the same state

When several Command Centres share a state, **Global Collation** adds their vote counts together (state → LGA → ward → polling unit), counting each polling unit once and telling each client how much comes from "external observers". Situation Rooms get the same for their LGA: rooms covering the same LGA, in the same or different Command Centres, are added together. **Only vote counts are pooled** — never maps, video, audio, photos, observers or messages.

The **Pool votes** tick-box in the Command Centres list controls this per centre (on by default for a centre that has a state). **Untick it for any client whose figures must stay private** — for example

when two clients in the same state are competitors. A centre that is not pooled neither contributes to nor sees the state-wide total.

Archiving and deleting (only you can)

Clients can suspend or deactivate their own rooms, but **only the platform administrator can archive or delete** — Command Centres, Situation Rooms and election data.

- **Archive** (Command Centres tab → **Archive**, or **Archive** on a room) switches it off and hides it everywhere (lists, collation, broadcasts). **Nothing is deleted.**
- **Situation Rooms tab.** Besides your own Main Command Center's rooms, it lists the rooms of **every client Command Center** (centre name, room, area, status, observer count) with Archive / Delete, so a client's room is never hard to find. Only the room's details are shown here; its observers, maps and results stay inside the client's own Command Center.
- **The Archive tab** (next to Command Centers) is where you find it all: **archived Command Centres**, **archived Situation Rooms** and **Stored records** (the copies kept when something was deleted or cleared). Press **Review** on any of them to read its results right there — votes by party, every polling unit with its status and figures, and every observer with theirs. **Restore** brings an archived item back (then **Enable** / activate it); **Delete** removes it for good (a stored copy is kept).
- **Delete** removes things **with everything under them**, and asks you to **type the ID** to confirm:
  - deleting a **Command Centre** deletes **all its Situation Rooms and every observer** under them, its operators, messages and audit trail;
  - deleting a **Situation Room** deletes **all its observers** and their results, photos and clips.
- **Stored records.** Nothing collected is lost silently. Before anything is deleted or cleared, a full copy — observers, tallies, results, EC8A records, incidents, radio, messages and audit — is saved to **Stored records** (Archive tab: **Review** it on screen or **Download** it as a file), and the photos, clips and radio audio are moved to the server's `archive` folder. They stay until you remove them on the server. Everything live is also in the database, which is backed up automatically (every 30 minutes by default).
- **Rooms** (on a Command Centre row) opens that centre's rooms: archive, restore or delete any of them, **Delete ALL rooms**, or **Clear data** (removes a room's observers and results but keeps the room).
- **Clear all election data** empties a whole Command Centre of results and observers but keeps the centre, its rooms and operators — handy after a demo or a rehearsal.
- You cannot archive or delete your own Command Centre. **Rooms listed on your own Situation Rooms tab belong to your Main Command Centre**: deleting another Command Centre does not touch them — use **Delete** on a room there, or **Rooms → Delete ALL rooms** on the Main Command Centre row.

Your Global Collation covers every state

On your own Global Collation tab the search lists **every state on the platform** and the totals add up all active Command Centres (vote counts only — never maps, video, audio or observer details). A switch limits it to your own centre.

Turning a Command Centre off / on

On the client's row, click **Disable (suspends its rooms)**. The client can no longer log in and all their Situation Rooms are suspended — use this at the end of an engagement or for non-payment. Click **Enable** to switch it back on. You cannot disable your own (`CC-MAIN`).

> **Deleting:** there is deliberately no one-click "delete a Command Centre" button, so a client's election record is never wiped by accident. Disabling is the safe, reversible equivalent. If a client must be permanently removed, do it on the server with a database operation and a backup first — ask your engineer.

---

3. Loading the location data (states → LGAs → wards → PUs)

Clients pick polling units from this list, so it must be loaded. **Locations** tab:

- **Fetch for a state** — choose a state and pull its official breakdown automatically.
- **Import a file** — upload an Excel/CSV of `state, lga, ward, pu` if you have your own dataset.
- You'll see counts per state once loaded.

Do this once per state you operate in. When you set a state on a Command Centre (section 2), that client is scoped to it automatically.

---

4. Marketing & link tracking (your sales tool)

The **Marketing** tab is yours alone — it drives client acquisition.

- **Tracking links** — type a label (e.g. `inec-kano`, `whatsapp-batch-1`) and copy the generated `…/pitch?ref=<label>` link. Share a different label with each person/channel.
- **Opens** — total opens, **different devices**, **repeat opens (same device)**, unique visitors, today, by label and by day.
- **Same device or shared?** — for each tracking link: opens, how many **different devices** opened it, and how many opens were the **same device coming back**. One device = it stayed with the person you sent it to; **Shared · N devices** = the link was forwarded and opened by others. *Recent opens* marks every open **New device** or **Same device · open #N**. A device is recognised by a small random ID the page keeps in the browser (no personal data). Opening in a private window, clearing browser data, or switching browser (for example WhatsApp's built-in browser and Chrome) looks like a new device, so treat "shared" as a strong hint, not proof.
- **Devices & browsers** — what people viewed on, and where they came from.
- **Leads & contacts** — people who filled the **Request a demo** form on the pitch page (name, phone, organisation), each a click-to-WhatsApp link, with CSV export.

> A web page **cannot** read a visitor's phone number — no browser allows it. The Leads list shows people who *chose* to leave their details or who messaged your WhatsApp.

The public pitch page itself is at `/pitch` and the demo button opens your WhatsApp (+234 812 733 7603).

5. Your own live demo (for prospects)

See `DEMO-GUIDE.md`. In short: run the system, `npm run seed:demo` fills a believable Kano election ("Kano State Command (Demo)") you can walk a client through, and re-running it resets the demo. It never touches real client data.

6. The Android apps

Three apps are built by CI and published on the landing page automatically:

- **Observer app** — `/download/app`
- **Situation Room app** — `/download/room`
- **Collation Officer app** — `/download/officer`

All three also run in any browser. You don't build these by hand — a push that changes the app rebuilds them (see `mobile/README.md`). On the landing page each shows a **Download (.apk)** button and a QR code once built.

7. Securing your own account

App Settings tab:

- **Change your passcode** — do this on day one; use a long, unique one.
- **Two-step login (TOTP)** — enable it and scan the QR with Google Authenticator / Authy. After this, every login needs the 6-digit code. Strongly recommended for the administrator.
- **App name** — the platform name shown on login screens.
- **Add operators** — you can add more administrator-side operators if needed; each gets their own name + passcode and (optionally) their own two-step login. Disable or reset any of them here.
- If an operator loses their phone, you can **clear their two-step login** so they can set it up again on a new device.

See `SECURITY.md` for the full checklist (branch protection, firewall, backups, 2FA).

7a. Help

The landing page has a **Help & user manual** button that opens the operator manual for anyone, without signing in (`/help`). Your administrator manual is never public.

The **Help** tab shows both manuals inside the app — this one (visible to you only) and the client operator manual — each with a **Download PDF** button, handy for onboarding emails.

8. Audit log

Audit Log tab records every significant action with a timestamp — logins, Command Centre creation, passcode resets, and more. It's your record of who did what. (Each client has their own, separate audit log inside their own Command Centre.)

9. Live field video — what to tell clients

If a client asks "can two of us watch the same observer at once?" — **yes**. The observer's phone streams once and everyone authorised in that command/room sees the same live feed simultaneously, can talk back, and can push it to an external broadcast via **Restream**. Nothing extra to configure as long as LiveKit is running (it is, in the standard deployment). For people **outside** the client's team, the client uses **Share Live View**: a view-only page (collation, map, video, optional talk-back) opened with a link and a passcode — see the operator manual, section 5a.

10. Quick reference — what only YOU can do

- Create / name Command Centres and assign a state.
- Generate and re-issue client login invites (Share).
- Enable / disable a client's Command Centre.
- Load location datasets for new states.
- See platform-wide Marketing and Leads.
- Set the platform name and your own security.

Everything *inside* a Command Centre — rooms, observers, results — is the client's to run, with the operator guide below.