Automatic Control

Steady state properties of stable LTI systems

Automatic Control – M. Canale

Steady state response

Consider a <u>strictly proper</u>, <u>asymptotically stable</u> and <u>minimal</u> (=> BIBO stable) <u>LTI SISO dynamical system</u> described by the transfer function:

$$H(s) = \frac{N_{H}(s)}{D_{H}(s)} = \frac{N_{H}(s)}{(s - p_{1})^{\mu_{1}}(s - p_{2})^{\mu_{2}}\cdots(s - p_{h})^{\mu_{h}}} = \frac{N_{H}(s)}{\prod_{s=0}^{n_{h}}(s - p_{s})^{\mu_{s}}}$$

with n_h distinct poles p_i , i = 1, ..., n_h of multiplicity μ_i^{-1} and such that $\mathbb{R}e(p_i) < 0$, $\forall i$

For such a system, let's study the zero state output response y(t) in the presence of an input u(t) with Laplace transform given by:

$$U(s) = \frac{N_{U}(s)}{D_{U}(s)} = \frac{N_{U}(s)}{(s - q_{1})^{m_{i}}(s - q_{2})^{m_{i}}...(s - q_{n_{u}})^{m_{u}}} = \frac{N_{U}(s)}{\prod_{j=1}^{n_{u}}(s - q_{j})^{m_{j}}}$$

Steady state analysis of stable LTI systems

Automatic Control – M. Canale

Steady state response

$$H(s) = \frac{N_{H}(s)}{D_{H}(s)} = \frac{N_{H}(s)}{(s - p_{1})^{\mu_{1}}(s - p_{2})^{\mu_{2}} \cdots (s - p_{h})^{\mu_{h}}} = \frac{N_{H}(s)}{\prod_{i=1}^{n_{s}}(s - p_{i})^{\mu_{i}}}$$

$$U(s) = \frac{N_{U}(s)}{D_{U}(s)} = \frac{N_{U}(s)}{(s - q_{1})^{m_{1}}(s - q_{2})^{m_{2}} \cdots (s - q_{n_{e}})^{m_{e}}} = \frac{N_{U}(s)}{\prod_{i=1}^{n_{e}}(s - q_{i})^{m_{i}}}$$

For simplicity, suppose that the polynomials $D_H(s)$ and $D_U(s)$ have not common roots.

The output can be computed as

$$Y(s) = H(s)U(s) = \frac{N_{H}(s)}{\prod_{i=1}^{n_{s}} (s - p_{i})^{\mu_{i}}} \cdot \frac{N_{U}(s)}{\prod_{j=1}^{n_{s}} (s - q_{j})^{m_{j}}}$$

Steady state response

$$Y(s) = H(s)U(s) = \frac{N_{H}(s)}{\prod_{i=1}^{n}(s - p_{i})^{\mu_{i}}} \cdot \frac{N_{U}(s)}{\prod_{j=1}^{n}(s - q_{j})^{m_{j}}} =$$

$$= \frac{R_{1,1}}{s - p_{1}} + \frac{R_{1,2}}{(s - p_{1})^{2}} + \dots + \frac{R_{1,n_{i}}}{(s - p_{1})^{n_{i}}} + \frac{R_{2,1}}{s - p_{2}} + \frac{R_{2,2}}{(s - p_{2})^{2}} + \dots + \frac{R_{2,n_{i}}}{(s - p_{2})^{n_{i}}} +$$

$$+ \dots + \frac{R_{h,1}}{s - p_{h}} + \frac{R_{h,2}}{(s - p_{h})^{2}} + \dots + \frac{R_{h,n_{h}}}{(s - p_{h})^{n_{h}}} +$$

$$+ \frac{Q_{1,1}}{s - q_{1}} + \frac{Q_{1,2}}{(s - q_{1})^{2}} + \dots + \frac{Q_{1,m_{i}}}{(s - q_{1})^{m_{i}}} + \frac{Q_{2,1}}{s - q_{2}} + \frac{Q_{2,2}}{(s - q_{2})^{2}} + \dots + \frac{Q_{2,m_{h}}}{(s - q_{2})^{m_{h}}} +$$

$$+ \dots + \frac{Q_{n_{h},1}}{s - q_{n_{h}}} + \frac{Q_{n_{h},2}}{(s - q_{n_{h}})^{2}} + \dots + \frac{Q_{n_{h},m_{h}}}{(s - q_{n_{h}})^{m_{h}}} =$$

$$= \sum_{j=1}^{n} \sum_{k=1}^{n} \frac{R_{j,k}}{(s - p_{j})^{k}} + \sum_{j=1}^{n} \sum_{k=1}^{m} \frac{Q_{j,k}}{(s - q_{j})^{k}}$$

Automatic Control – M. Canale

AC_L06 5

Steady state response

$$Y(s) = H(s)U(s) = \frac{N_{H}(s)}{\prod_{i=1}^{n_{s}} (s - p_{i})^{\mu_{i}}} \cdot \frac{N_{U}(s)}{\prod_{j=1}^{n_{s}} (s - q_{j})^{m_{j}}}$$

$$Y(s) = \sum_{j=1}^{n_s} \sum_{k=1}^{\mu_i} \frac{R_{j,k}}{(s - p_j)^k} + \sum_{j=1}^{n_s} \sum_{k=1}^{m_i} \frac{Q_{j,k}}{(s - q_j)^k}$$

$$y(t) = \sum_{j=1}^{n_s} \sum_{k=1}^{\mu_j} R_{j,k} \frac{t^{k-1}}{(k-1)!} e^{\rho_j t} + \sum_{j=1}^{n_s} \sum_{k=1}^{m_j} Q_{j,k} \frac{t^{k-1}}{(k-1)!} e^{q_j t}$$

i.e. the output response y(t) is a linear combination of the

- system natural modes;
- input modes.

Steady state response

$$Y(s) = H(s)U(s) = \sum_{j=1}^{n} \sum_{k=1}^{\mu_{i}} \frac{R_{j,k}}{(s-p_{j})^{k}} + \sum_{j=1}^{n} \sum_{k=1}^{m_{i}} \frac{Q_{j,k}}{(s-q_{j})^{k}}$$

$$Y(t) = R_{1,1}e^{\rho,t} + R_{1,2}te^{\rho,t} \dots + R_{1,n_{i}} \frac{t^{n_{i}-1}}{(n_{1}-1)!}e^{\rho,t} + \\
+ R_{2,1}e^{\rho,t} + R_{2,2}te^{\rho,t} \dots + R_{2,n_{i}} \frac{t^{n_{i}-1}}{(n_{2}-1)!}e^{\rho,t} + \dots$$

$$+ R_{h,1}e^{\rho,t} + R_{h,2}te^{\rho,t} \dots + R_{h,n_{i}} \frac{t^{n_{i}-1}}{(n_{h}-1)!}e^{\rho,t}$$

$$+ Q_{1,1}e^{q,t} + Q_{1,2}te^{q,t} + \dots + Q_{1,m_{i}} \frac{t^{m_{i}-1}}{(m_{1}-1)!}e^{q,t} + \\
+ Q_{2,1}e^{q,t} + Q_{2,2}te^{q,t} + \dots + Q_{2,m_{i}} \frac{t^{m_{i}-1}}{(m_{2}-1)!}e^{q,t} + \\
+ \dots + Q_{n_{i},1}e^{q,t} + Q_{n_{i},2}te^{q,t} + \dots + Q_{n_{i},m_{i}} \frac{t^{m_{i}-1}}{(m_{q}-1)!}e^{q,t} =$$

$$= \sum_{j=1}^{n} \sum_{k=1}^{n_{i}} R_{j,k} \frac{t^{k-1}}{(k-1)!}e^{\rho,t} + \sum_{j=1}^{n} \sum_{k=1}^{m_{i}} Q_{j,k} \frac{t^{k-1}}{(k-1)!}e^{q,t}$$

Automatic Control – M. Canale

AC L06 6

Steady state response

$$y(t) = \sum_{j=1}^{n_s} \sum_{k=1}^{\mu_j} R_{j,k} \frac{t^{k-1}}{(k-1)!} e^{\rho_j t} + \sum_{j=1}^{n_s} \sum_{k=1}^{m_j} Q_{j,k} \frac{t^{k-1}}{(k-1)!} e^{q_j t}$$

The output response is the sum of two contributions.

The first one (i.e. $y_{tr}(t)$) depends on the system natural modes only, while the second (i.e. $y_{ss}(t)$) depends on the input modes only.

Recalling that the system has been assumed asymptotically stable

(i.e.
$$\mathbb{R}e(p_i) < 0$$
, $j = 1, ..., n_h$), then, when $t \rightarrow \infty$:

- 1. $y_{tr}(t) \rightarrow 0$ (all the system natural modes are convergent) $y_{tr}(t) \rightarrow$ **transient response**.
- 2. $y(t) \rightarrow y_{ss}(t)$ (i.e. for sufficiently high time instant, the system output coincides with $y_{ss}(t)$) $y_{ss}(t) \rightarrow$ **steady-state response**.

Steady state response

Remark

In the presence of common roots in the polynomials $D_H(s)$ and $D_U(s)$, the output response is the sum of three terms. In particular

- 1. a term that includes all the poles of H(s) that are not poles of $U(s) \rightarrow$ transient response.
- 2. a "mixed term" that includes the common poles of H(s) and U(s)
 → transient response (since such poles have strictly negative real part).
- 3. a term that includes all the poles of U(s) that are not poles of $H(s) \rightarrow$ **steady-state response**.


Thus, the output response can be still represented as the sum of a transient response $y_{tr}(t)$ such that $y_{tr}(t) \rightarrow 0$ and a steady state response $y_{ss}(t)$ such that $y(t) \rightarrow y_{ss}(t)$.

Automatic Control - M. Canale

AC_L06 9

Example 1

$$y(t) = 1.1547e^{-0.5t}\cos(0.866t + 2.618)\varepsilon(t) + \varepsilon(t)$$



t (s)

Example 1

$$H(s) = \frac{1}{s^2 + s + 1} = \frac{1}{(s + 0.5 - j0.866)(s + 0.5 + j0.866)}$$

$$U(s) = \frac{1}{s}, (u(t) = \varepsilon(t))$$

$$Y(s) = H(s)U(s) = \frac{1}{s(s + 0.5 - j0.866)(s + 0.5 + j0.866)} = \frac{-0.5 + j0.2887}{(s + 0.5 - j0.866)} + \frac{-0.5 - j0.2887}{(s + 0.5 + j0.866)} + \frac{1}{s}$$

$$Y(t) = \underbrace{1.1547e^{-0.5t}\cos(0.866t + 2.618)\varepsilon(t)}_{y_{tr}(t)} + \underbrace{\varepsilon(t)}_{y_{ss}(t)}$$

Automatic Control - M. Canale

AC L06 10

Example 2

$$H(s) = \frac{1}{s^2 + s + 1} = \frac{1}{(s + 0.5 - j0.866)(s + 0.5 + j0.866)}$$

$$U(s) = \frac{1.5}{s^2 + 1.5^2}, (u(t) = \sin(1.5t))$$


$$Y(s) = H(s)U(s) = \frac{1}{(s + 0.5 - j0.866)(s + 0.5 + j0.866)(s - j1.5)(s + j1.5)} =$$

$$= \frac{-0.1967 + j0.1639}{(s + 0.5 - j0.866)} + \frac{-0.1967 - j0.1639}{(s + 0.5 + j0.866)} + \frac{0.1967 - j0.3975}{(s - j1.5)} + \frac{0.1967 + j0.0.3975}{(s + j1.5)}$$

$$Y(t) = \frac{0.8871e^{-0.5t}\cos(0.866t - 1.1113)\varepsilon(t)}{v_{tr}(t)} + \frac{0.5121\cos(1.5t + 2.4469)\varepsilon(t)}{v_{ss}(t)}$$

Example 2

$$u(t) = \sin(1.5t) \qquad y(t) = 0.8871e^{-0.5t}\cos(0.866t - 1.1113)\varepsilon(t) + \frac{10.5121\cos(1.5t + 2.4469)\varepsilon(t)}{2.5121\cos(1.5t + 2.4469)\varepsilon(t)}$$



Automatic Control – M. Canale

AC L06 13

Steady-state properties

Steady-state properties of an LTI system concern the time behavior of the output (and state) for sufficiently high time values.

LTI asymptotically stable system have the property that, for the class of input signals with real rational Laplace transform such as exponential functions, the output (and state) response at steady state (i.e. for sufficiently high time values) has the same shape as the input (except for scaling factors and time shifts)

Special cases of input signals belonging to the considered class, such as

- step signals;
- harmonic signals (sinusoid, ...).

and their linear combinations are of practical interest for the analysis and design of control systems.

Steady state properties computation

Automatic Control – M. Canale

Steady-state response: step input

Let

$$H(s) = \frac{b_m s^m + b_{m-1} s^{m-1} + \dots + b_1 s + b_0}{s^n + a_{n-1} s^{n-1} + \dots + a_1 s + a_0}$$

be the transfer function (tf) of a stable LTI system.

The steady-state response $y_{ss}(t)$ due to a step input signal of amplitude \bar{u} :

$$u(t) = \overline{u}\,\varepsilon(t) \to U(s) = \frac{\overline{u}}{s}$$

is given by
$$y_{ss}(t) = \overline{y}\varepsilon(t) \rightarrow \overline{y} = \lim_{s \to 0} sY(s) = \overline{u} \cdot \lim_{s \to 0} sH(s) = \lim_{s \to 0} sH(s)$$

$$= \overline{u} \cdot H(0) = \overline{u} \cdot \frac{b_0}{a_0}$$



Example

A minimal LTI system is described by the tf:

$$H(s) = \frac{1}{(s+2)(s+10)}$$

compute, if possible, the steady state output response in the presence of a step input with amplitude 2.

The poles of H(s) are -2 e -10.

- \Rightarrow the system is BIBO stable.
- \Rightarrow the system is asymptotically stable.
- \Rightarrow the steady state response can be computed.

Since $u(t) = \bar{u}\varepsilon(t) = 2\varepsilon(t) \Rightarrow$ the steady state response is

$$y_{ss}(t) = \overline{y} \varepsilon(t) = H(0)\overline{u} \varepsilon(t) = \frac{1}{20} 2 \varepsilon(t) = 0.1 \varepsilon(t)$$

Automatic Control - M. Canale

AC_L06 17

Steady-state response: sinusoidal input

Let

$$H(s) = \frac{b_m s^m + b_{m-1} s^{m-1} + \dots + b_1 s + b_0}{s^n + a_{n-1} s^{n-1} + \dots + a_1 s + a_0}$$

be the tf of a stable LTI system.

The steady-state response $y_{ss}(t)$, $t \ge 0$, due to a sinusoidal input signal of amplitude \bar{u} and frequency ω_0 :

$$u(t) = \overline{u} \sin(\omega_0 t)$$

is given by(*)

$$y_{ss}(t) = \overline{y}(\omega_0)\sin(\omega_0 t + \varphi(\omega_0))$$

$$\rightarrow \overline{y}(\omega_0) = \overline{u} \cdot |H(j\omega_0)|, \varphi(\omega_0) = \angle(H(j\omega_0))$$

(*) for a complete proof see, e.g., N. S. Nise, "Control System Engineering", 5th Edition, Wiley, 2008

Automatic Control – M. Canale

AC_L06 19



Steady-state response: step input

- Evaluation with Matlab of $\lim_{s \to 0} H(s)$ for a stable tf
- Statement dcgain:

```
>> s=tf('s');
>> H=1/((s+2)*(s+10));
>> K = dcgain(H)
K = 0.05
```

- The statement dcgain can also be used to compute the generalized steady-state gain (generalized dc-gain) K = lim s'H(s)
- Consider for example the tf $H(s) = \frac{1}{s(s+2)^2}$, r=1>> s=tf('s'); >> $H=1/(s*(s+2)^2)$; >> K = dcgain(s*H)

Automatic Control - M. Canale

AC_L06 18



K = 0.25

Example

A minimal LTI system is described by the tf:

$$H(s) = \frac{1}{(s+2)(s+10)}$$

compute, if possible, the steady state output response in the presence of a sinusoidal input $u(t) = 2\sin(0.5t) \varepsilon(t)$.

The system is asymptotically stable (see Example 1). \Rightarrow the steady state response can be computed.

Since $u(t) = \overline{u} \sin(\omega_0 t) \varepsilon(t) = 2 \sin(0.5t) \varepsilon(t)$,

⇒ the steady state response is:

$$y_{ss}(t) = \overline{y} \sin(\omega_0 t + \varphi) \varepsilon(t) = \overline{y} \sin(0.5t + \varphi) \varepsilon(t)$$

$$\overline{y} = |H(j\omega_0)| \cdot \overline{u} = 2|H(j0.5)|$$

$$\varphi = \arg H(j\omega_0) = \arg H(j0.5)$$



Example

$$y_{ss}(t) = \overline{y}\sin(\omega_0 t + \varphi)\varepsilon(t) = \overline{y}\sin(0.5t + \varphi)\varepsilon(t)$$

$$\overline{y} = |H(j\omega_0)| \cdot \overline{u} = 2|H(j0.5)|$$

$$\varphi = \arg H(j\omega_0) = \arg H(j0.5)$$

$$|\mathcal{H}(j0.5)| = |(j0.5 + 2)(j0.5 + 10)|^{-1} = |j0.5 + 2|^{-1} |j0.5 + 10|^{-1} =$$

$$= \left(\sqrt{0.5^2 + 2^2} \sqrt{0.5^2 + 10^2}\right)^{-1} = \left(\sqrt{4.25} \sqrt{100.25}\right)^{-1} = 0.0484$$

$$\arg H(j0.5) = \arg \left(\frac{1}{[(j0.5 + 2)(j0.5 + 10)]} \right) =$$

$$= \arg(1) - \arg(j0.5 + 2) - \arg(j0.5 + 10) =$$


$$= 0 - \arctan(0.5/2) - \arctan(0.5/10) = -0.2949 \text{ rad}$$

Automatic Control – M. Canale

AC_L06 21

Frequency response function

The function $H(j\omega): \mathbb{R}^+ \to \mathbb{C}$ of the variable $\omega \in \mathbb{R}^+$ is referred to as the **frequency response function** of the system.



$$H(j\omega) = \text{Re}[H(j\omega)] + \text{Im}[H(j\omega)] \rightarrow \text{Cartesian representation}$$

$$H(j\omega) = |H(j\omega)| e^{j\angle H(j\omega)} \rightarrow \text{Polar representation}$$

Steady-state: sinusoidal input

- Evaluation of magnitude and phase of a tf with MatLab
- Command bode

The magnitude value is <u>not</u> expressed in dB, but in linear scale, the phase value is expressed in degrees.

Automatic Control – M. Canale

AC_L06 22