

# Pickup - Ground Freight - LTL Web Service Developer Guide

July 09, 2018



#### **Important Information**

#### **UPS Developer Kit APIs**

Your development of an application using UPS Developer Kit APIs is governed by the UPS Technology Agreement you entered into with UPS. The following are key legal requirements from these agreements for the UPS Developer Kit APIs. For more information on all requirements for the UPS Developer Kit APIs, please refer to the UPS Technology Agreement.

Defined terms used but not defined in this document have the meaning set forth in the UPS Technology Agreement.

#### **Key Legal Requirements for UPS Developer APIs**

#### Permitted Territories

This document can only be used in the countries of the Permitted Territory as defined in the UPS Technology Agreement, as applicable.

#### Use

The application must not be designed to allow distribution of information received through the UPS Developer Kit APIs to third parties, other than to persons having a bona fide interest in such information (e.g., the shipper, receiver, or the third party paver, or to your service providers authorized by UPS).

#### Consent to Use of UPS Mark

- All screens or forms generated by your application including information received through the UPS
  Developer Kit APIs must include (1) the UPS Mark positioned in reasonable proximity to the Information and
  of an appropriate size to readily identify the source of the Information as UPS and (2) the following language
  at the bottom of every screen that displays the UPS Mark: "UPS, the UPS brand mark, and the Color Brown
  are trademarks of United Parcel Service of America, Inc. All Rights Reserved." Except as set forth in the
  preceding sentence, you have no right to use the UPS Mark without the prior written approval of UPS.
- You shall not use the UPS Mark in association with any third party trademarks in a manner that might suggest co-branding or otherwise create potential confusion as to source or sponsorship of the application, or ownership of the UPS Mark.
- The UPS Mark shall be used only as provided by UPS electronically or in hard copy form. The UPS Mark may not be altered in any manner, including proportions, colors, elements, etc., or animated, morphed or otherwise distorted in perspective or dimensional appearance.
- The UPS Mark may not be combined with any other symbols, including words, logos, icons, graphics, photos, slogans, numbers, or other design elements. A minimum amount of empty space must surround the UPS Mark separating it from any other object, such as type, photography, borders, edges, etc. The required area of empty space around the UPS Mark must be 1/3x, where x equals the height of the UPS Mark.

#### Copyright and Proprietary Notice

In your application and any POD Letters you prepare, you must include a prominent reproduction of UPS's copyright and proprietary notices in a form and format specified by UPS (See the Copyright section of this document).

#### Display of Information

The application must not display information concerning any other provider of shipping services or such other shipping services on any page, whether comprising one or more frames, displaying information your application receives from the UPS Developer Kit APIs. Your application must present all data within each field received through the UPS Developer Kit APIs without amendment, deletion, or modification of any type.

#### **Notice**

In all communications with UPS concerning this document, please refer to the document date located on the cover.

### Copyright

© 2018 United Parcel Service of America, Inc. All Rights Reserved. Confidential and Proprietary

The use, disclosure, reproduction, modification, transfer, or transmittal of this work for any purpose in any form or by any means without the written permission of United Parcel Service is strictly prohibited.

#### **Trademarks**

Some of the UPS corporate applications use United States city, state, and postal code information obtained by United Parcel Service of America, Inc. under a non-exclusive license from the United States Postal Service.

## **Table of Contents**

Chapter 1: Introduction	5
Release Features	6
Chapter 2: Understanding the Pickup Ground Freight API	
Business Rules	7
Chapter 3: Customer Integration Environment (CIE)	8
Integration Testing	8
Production	8
Server Availability Check	8
Chapter 4: Pickup Ground Freight API Elements	g
Accessing the Freight Pickup Web Service API	g
Element Constraints	g
FreightPickupRequest Top Level Containers	10
FreightPickupRequest XPath Table	11
FreightPickupResponse Top Level Containers	20
FreightPickupResponse XPath Table	20
Chapter 5: Cancel Pickup Ground Freight API Elements	22
FreightCancelPickupRequest Top Level Containers	22
FreightCancelPickupRequest XPath Table	22
FreightCancelPickupResponse Top Level Containers	23
FreightCancelPickupResponse XPath Table	23
Chapter 6: Pickup Ground Freight API Examples	25
FreightPickupRequest Example	25
FreightPickupResponse Example	26
FreightCancelPickupRequest Example	28
FreightCancelPickupResponse Example	28
Chapter 7: Pickup Ground Freight LTL API FAQs	30
Appendices	31
Error Codes (WS)	32
Common Error Codes	32
Pickup Ground Freight Error Codes	33
Country or Territory Codes	39
LTL Event Types	39
Packaging Type Codes	39
POM Number Type Values	41
Service Codes	41

## **Chapter 1: Introduction**

In this document, you will find guidance and instructions for integrating the Pickup Ground Freight LTL Web Service into your application, service, or system.

#### In this guide, you will find:

- New release features
- Pickup Ground Freight LTL Web Service API functionality and business rules
- Web service API request and response schema
- · FAQs for the Pickup Ground Freight API
- Pickup Ground Freight error response code descriptions
- Service code references

#### This guide applies to the following API:

• SOAP API for the Pickup Ground Freight LTL Web Service

#### This guide does not apply to the following APIs:

Pickup Package Web Service API

#### **Intended Audience**

This guide is intended for developers who will be integrating the Pickup Ground Freight LTL Web Service API into their application, service, or system.

#### Required Knowledge & Skills

This guide assumes you have a basic understanding of the following:

- Concepts and instructions in the Introduction to the UPS Developer Kit guide
- XML syntax and structure
- Web services
- Software development

#### How to Use this Guide

- If this is your first time working with the UPS Developer Kit, begin with the Introduction to the UPS Developer Kit guide. This guide serves as the foundation for all API-specific developer guides.
- If you are experienced with the UPS Developer Ground Freights but have not yet worked with the Pickup Ground Freight API, continue with Chapter 2: Understanding the Pickup Ground Freight API. There you will find an overview of the Pickup Ground Freight functionality and business rules.
- Chapter 3: Customer Integration Environment contains information on UPS integration environments.
- Chapter 4: Pickup Ground Freight API Elements contains an overview of the top-level containers and elements that comprise the Pickup Ground Freight request and response.
- Request and response examples are located in Chapter 6: Pickup Ground Freight API Examples.
- Reference tables, services codes, and error codes are located in the Appendices.

### **Release Features**

### **July 2018**

No change.

### January 2018

No change.

### **July 2017**

No change.

### January 2017

No change.

### July 2016

No change.

## Chapter 2: Understanding the Pickup Ground Freight API

### **Business Rules**

#### General

- UPS expects schema elements/tags as defined in the XPath and presented in the schema structure without spelling or structural deviations. Elements/tags that are not defined in the schema or do not conform to the schema structure will be ignored by UPS.
- · Only users that plan to ship packages manifested, tendered, and delivered by UPS can use the API.
- · Any customers/developers abusing or data mining the API will have their access revoked.
- To access API documentation the user must have or create a UPS profile.
- To access testing and production sites the user must have an Access Key. To get an Access Key you must have a
  UPS profile and an associated shipping account. For additional information, refer to the UPS Developer Kit User
  Guide.

#### **Pickup Package Rules**

Package shipments require a pickup to be scheduled via the Pickup Package API.

#### **LTL Freight Country or Territory Origins**

LTL Freight country or territory origins include US, CA & MX. The US territory means the contiguous 48 states of the US and Washington DC. While we service Hawaii, Alaska, Guam, Puerto Rico and the US Virgin Islands, those rates can only be obtained by calling UPS Freight Customer Service at (800) 333-7400.

## Chapter 3: Customer Integration Environment (CIE)

The Customer Integration Environment allows customers to test their application prior to launch. This environment is intended for integration testing of customer applications with the UPS servers.

Once your application has been thoroughly tested, you should redirect the application to the UPS Production Environment.



No stress testing should ever be performed by customers against any UPS systems.

To access testing and production sites the user must have an Access Key. You can request an Access Key after establishing a UPS profile and associating your shipping account.

#### System Availability

The Customer Integration Environment is available 24 hours a day, 7 days a week. Note, the system is occasionally down for server maintenance.

#### LTL Freight Country or Territory Origins

LTL Freight country or territory origins include US, CA & MX. The US territory means the contiguous 48 states of the US and Washington DC. While we service Hawaii, Alaska, Guam, Puerto Rico and the US Virgin Islands, those rates can only be obtained by calling UPS Freight Customer Service at (800) 333-7400.

### **Integration Testing**



All API URLs are case sensitive.

For integration testing, direct your Pickup Ground Freight LTL Web Service to:

https://wwwcie.ups.com/webservices/FreightPickup

#### **Production**



All API URLs are case sensitive.

Once testing is complete, direct your Pickup Ground Freight LTL Web Service API to the production URL:

https://onlinetools.ups.com/webservices/FreightPickup

## **Server Availability Check**

All of the UPS services work using HTTPS POST. If the server is available, it will reply with the service name, remote user, server port, server name, and servlet path.

To see this in action, type the following URL in your web browser: https://wwwcie.ups.com/webservices/FreightPickup

Server Name:	FreightPickupWS	
Remote User:	Null	
Server Port:	443	
Server Name:	www.cie.ups.com	
Servlet Path:	/FreightPickup	

## Chapter 4: Pickup Ground Freight API Elements

### **Accessing the Freight Pickup Web Service API**

Access the Service at:	http://onlinetools.ups.com/webservices/FreightPickup
Service Operation:	CreatePickup
Rate Operation:	Type: Request-Response (client sends a request to UPS and the UPS server replies with a response)
	SOAPAction Header: http://onlinetools.ups.com/webservices/FreightPickupBinding

#### **Element Constraints**

The Request and Response XPath tables contain the full hierarchy of the API elements.



UPS expects schema elements/tags as defined in the XPath and presented in the schema structure i.e., no spelling or structural deviations. Elements/tags that are not defined in the schema or do not conform to the schema structure will be ignored by UPS.

Element constraints are defined as follows:

#### Required

- Yes indicates the element must be present in the request or response.
- Yes\* indicates the element must be present in the request if the parent container is present in the request.
- No indicates the element is optional and may be used if it applies to the request.
- Cond indicates the element is required under certain conditions.

#### **Type**

- · Container holds a group of related elements.
- · String consists of alphanumeric characters, spaces, and decimals.


#### Length

• The maximum number of characters that can be present in a String. Length is not applicable (N/A) to Containers.

#### **Max Allowed**

The maximum number of elements or containers that can be present in the parent container.

## FreightPickupRequest Top Level Containers



## FreightPickupRequest XPath Table

Name	Constraint	Description
/FreightPickupRequest		'
FreightPickupRequest	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Freight Pickup Request container.
/FreightPickupRequest/Request		
Request	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Request container.
/FreightPickupRequest/Request/	RequestOption	
RequestOption	Required: No Type: String Max Allowed: UNB Length: 115	Type of shipping. Valid value: 1 - Ground
/FreightPickupRequest/Request/	TransactionRefere	ence
TransactionReference	Required: No Type: Container Max Allowed: 1 Length: N/A	TransactionReference identifies transactions between client and server.
/FreightPickupRequest/Request/	TransactionRefere	ence/CustomerContext
CustomerContext	Required: No Type: String Max Allowed: 1 Length: 1512	The client uses CustomerContext to synchronize request/response pairs. The client establishes CustomerContext, which can contain any information you want, as long as it is valid XML; it is echoed back by the server.
/FreightPickupRequest/PickupRe	equestConfirmatio	nNumber
PickupRequestConfirmationNumber	Required: Cond Type: String Max Allowed: 1 Length: 35	Confirmation number of pickup ground freight shipment to modify. Only use if requesting a pickup modification. If this element is populated, it must contain a valid confirmation number and all previously supplied populated elements in the original request must be present.
/FreightPickupRequest/Destination	onPostalCode	
DestinationPostalCode	Required: No Type: String Max Allowed: 1 Length: 10	Destinations postal code.
/FreightPickupRequest/Destination	onCountryCode	
DestinationCountryCode	Required: Yes Type: String Max Allowed: 1 Length: 2	Destinations country or territory code.
/FreightPickupRequest/Requeste	er	
Requester	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Requester container. Also referred to as caller.

Name	Constraint	Description
/FreightPickupRequest/Re	equester/ThirdPartyIndic	ator
ThirdPartyIndicator	Required: No Type: String Max Allowed: 1 Length: 0	Indicates whether the requester is Consignee, Third Party, Shipper, other.
/FreightPickupRequest/Re	equester/AttentionName	
AttentionName	Required: Yes Type: String Max Allowed: 1 Length: 35	Requesters name.
/FreightPickupRequest/Re	equester/EMailAddress	
EMailAddress	Required: Yes Type: String Max Allowed: 1 Length: 50	Requesters email address.
/FreightPickupRequest/Re	equester/Name	
Name	Required: Yes Type: String Max Allowed: 1 Length: 35	Requesters company name.
/FreightPickupRequest/Re	equester/Phone	
Phone	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Phone container
/FreightPickupRequest/Re	equester/Phone/Number	
Number	Required: Yes Type: String Max Allowed: 1 Length: 15	Requesters phone number
/FreightPickupRequest/Re	equester/Phone/Extension	on
Extension	Required: No Type: String Max Allowed: 1 Length: 4	Requesters phone extension.
/FreightPickupRequest/Sh	nipFrom	
ShipFrom	Required: Yes	ShipFrom container.
	Max Allowed: 1 Length: N/A	
/FreightPickupRequest/Sh	nipFrom/AttentionName	
AttentionName	Required: Yes Type: String Max Allowed: 1 Length: 35	Contact name at the ship from location.

Name	Constraint	Description	
/FreightPickupRequest/ShipFrom/Name			
Name	Required: Yes Type: String Max Allowed: 1 Length: 35	The ship from locations name or company name.	
/FreightPickupRequest/Sh	ipFrom/Address		
Address	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Address container.	
/FreightPickupRequest/Sh	ipFrom/Address/Addres	sLine	
AddressLine	Required: Yes Type: String Max Allowed: 3 Length: 35	The Ship from street address.	
/FreightPickupRequest/Sh	ipFrom/Address/City		
City	Required: Yes Type: String Max Allowed: 1 Length: 30	The Ship from city.	
/FreightPickupRequest/Sh	nipFrom/Address/StatePr	rovinceCode	
StateProvinceCode	Required: Cond Type: String Max Allowed: 1 Length: 5	The Ship from locations state or province code. Required for certain countries or territories.	
/FreightPickupRequest/Sh	nipFrom/Address/PostalC	Code	
PostalCode	Required: No Type: String Max Allowed: 1 Length: 10	The ship from locations postal code.	
/FreightPickupRequest/Sh	nipFrom/Address/Country	yCode	
CountryCode	Required: Yes Type: String Max Allowed: 1 Length: 2	The ship from locations country or territory code.	
/FreightPickupRequest/Sh	/FreightPickupRequest/ShipFrom/Phone		
Phone	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Phone container.	
/FreightPickupRequest/Sh	ipFrom/Phone/Number		
Number	Required: Yes Type: String Max Allowed: 1 Length: 15	The ship from locations phone number.	

Name	Constraint	Description	
/FreightPickupRequest/ShipFrom/Phone/Extension			
Extension	Required: No Type: String Max Allowed: 1 Length: 4	The ship from locations phone extension.	
/FreightPickupRequest/Sh	ipFrom/EMailAddress		
EMailAddress	Required: No Type: String Max Allowed: 1 Length: 50	Ship from email address.	
/FreightPickupRequest/Sh	ipTo		
ShipTo	Required: Cond Type: Container Max Allowed: 1 Length: N/A	ShipTo container. Must be populated if request is a Pickup Notifications for LTL request and BOLID does not exist in the request.	
/FreightPickupRequest/Sh	ipTo/AttentionName		
AttentionName	Required: Cond Type: String Max Allowed: 1 Length: 25	Contact name at the ship to location.	
/FreightPickupRequest/Sh	ipTo/Address		
Address	Required: Cond Type: Container Max Allowed: 1 Length: N/A	Address container.	
/FreightPickupRequest/Sh	ipTo/Address/AddressL	ine	
AddressLine	Required: Cond Type: String Max Allowed: 1 Length: 35	The Ship to street address.	
/FreightPickupRequest/Sh	ipTo/Address/City		
City	Required: Cond Type: String Max Allowed: 1 Length: 30	The Ship to city.	
/FreightPickupRequest/Sh	/FreightPickupRequest/ShipTo/Address/StateProvinceCode		
StateProvinceCode	Required: Cond Type: String Max Allowed: 1 Length: 5	The Ship to location's state or province code.	
/FreightPickupRequest/Sh	ipTo/Address/PostalCod	de	
PostalCode	Required: Cond Type: String Max Allowed: 1 Length: 10	The ship to location's postal code.	

Name	Constraint	Description
/FreightPickupRequest/Sh	ipTo/Address/CountryC	ode
CountryCode	Required: Cond Type: String Max Allowed: 1 Length: 2	The ship to location's country or territory code.
/FreightPickupRequest/Sh	ipTo/Phone	
Phone	Required: Cond Type: Container Max Allowed: 1 Length: N/A	Phone container.
/FreightPickupRequest/Sh	ipTo/Phone/Number	
Number	Required: Cond Type: String Max Allowed: 1 Length: 15	The ship to location's phone number. Format: (###)###-###
/FreightPickupRequest/Sh	ipTo/Phone/Extension	
Extension	Required: Cond Type: String Max Allowed: 1 Length: 4	The ship to location's phone extension.
/FreightPickupRequest/Sh	ipTo/EMailAddress	
EmailAddress	Required: Cond Type: String Max Allowed: 1 Length: 50	Ship to email address.
/FreightPickupRequest/Pic	ckupDate	
PickupDate	Required: Yes Type: String Max Allowed: 1 Length: 8	Date of the Pickup. Format:YYYYMMDD
/FreightPickupRequest/Ea	rliestTimeReady	
EarliestTimeReady	Required: Yes Type: String Max Allowed: 1 Length: 4	The earliest time a shipment is ready to be picked up. The time is on a 24 hour clock. Format: HHMM HH = Hour values 00 to 23 MM = Minute values 00 to 59
/FreightPickupRequest/Lat	testTimeReady	
LatestTimeReady	Required: Yes Type: String Max Allowed: 1 Length: 4	The latest time a shipment can be picked up. Can be also referred as the Closing Time for a pickup time window. The time is on a 24 hour clock.  Format: HHMM  HH = Hour values 00 to 23  MM = Minute values 00 to 59
/FreightPickupRequest/Sh	ipmentServiceOptions	
ShipmentServiceOptions	Required: No Type: Container Max Allowed: 1 Length: N/A	ShipmentServiceOptions container.


Name	Constraint	Description
/FreightPickupRequest/ShipmentServiceOptions/FreezableProtectionIndicator		
FreezableProtectionIndicator	Required: No Type: String Max Allowed: 1 Length: 0	FreezableProtectionIndicator container.
/FreightPickupRequest/Shipmen	tServiceOptions/Li	mitedAccessPickupIndicator
LimitedAccessPickupIndicator	Required: No Type: String Max Allowed: 1 Length: 0	Indicates there is limited access for pickups.
/FreightPickupRequest/Shipmen	tServiceOptions/Li	mitedAccessDeliveryIndicator
LimitedAccessDeliveryIndicator	Required: No Type: String Max Allowed: 1 Length: 0	Indicates there is limited access for deliveries.
/FreightPickupRequest/Shipmen	tServiceOptions/E	xtremeLengthIndicator
ExtremeLengthIndicator	Required: No Type: String Max Allowed: 1 Length: 0	ExtremeLengthIndicator container (greater than 15ft)
/FreightPickupRequest/Shipmen	tDetail	
ShipmentDetail	Required: Cond Type: Container Max Allowed: UNB Length: N/A	ShipmentDetail container. Request will contain either ShipmentDetail or ExistingShipmentID container. Not both.
/FreightPickupRequest/Shipmen	tDetail/HazmatIndi	icator
HazmatIndicator	Required: No Type: String Max Allowed: 1 Length: 0	The presence of the tag HazmatIndicator indicates that the commodity is of type dangerous goods. Required if one or more commodities within the shipment is hazardous.
/FreightPickupRequest/Shipmen	tDetail/Packaging	Гуре
PackagingType	Required: Yes* Type: Container Max Allowed: 1 Length: N/A	PackagingType container.
/FreightPickupRequest/ShipmentDetail/PackagingType/Code		
Code	Required: Yes Type: String Max Allowed: 1 Length: 3	The code for the UPS packaging type associated with the shipment. For valid values, see Packaging Type Codes in the Appendix.
/FreightPickupRequest/Shipmen	tDetail/Packaging	Γype/Description
Description	Required: No Type: String Max Allowed: 1 Length: 35	A text description of the code for the UPS packaging type associated with the shipment.

Name	Constraint	Description	
/FreightPickupRequest/ShipmentDetail/NumberOfPieces			
NumberOfPieces	Required: Yes* Type: String Max Allowed: 1 Length: 6	Number of pieces.	
/FreightPickupRequest/Shipm	nentDetail/Description	OfCommodity	
DescriptionOfCommodity	Required: Yes* Type: String Max Allowed: 1 Length: 35	Description of the line item.	
/FreightPickupRequest/Shipm	nentDetail/Weight		
Weight	Required: Yes* Type: Container Max Allowed: 1	Weight container.	
/FreightPickupRequest/Shipm	nentDetail/Weight/Uni	itOfMeasurement	
UnitOfMeasurement	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Weight UnitOfMeasurement container.	
/FreightPickupRequest/Shipm	nentDetail/Weight/Uni	tOfMeasurement/Code	
Code	Required: Yes Type: String Max Allowed: 1 Length: 3	The code associated with the unit of measure for the weight. Valid value: LBS - Pounds	
/FreightPickupRequest/Shipm	nentDetail/Weight/Uni	itOfMeasurement/Description	
Description	Required: No Type: String Max Allowed: 1 Length: 35	A text description of the code for the unit of measure associated with the weight.	
/FreightPickupRequest/Shipm	nentDetail/Weight/Val	ue	
Value	Required: Yes Type: String Max Allowed: 1 Length: 16	The value for the weight associated with the shipment. Valid characters: 0-9 and "." (Decimal). Maximum of 2 digits after the decimal.	
/FreightPickupRequest/Existir	ngShipmentID		
ExistingShipmentID	Required: Cond Type: Container Max Allowed: 1 Length: N/A	ExistingShipmentID container. Request will contain either ShipmentDetail or ExistingShipmentID container. Not both.	
/FreightPickupRequest/Existir	/FreightPickupRequest/ExistingShipmentID/ShipmentNumber		
ShipmentNumber	Required: Yes* Type: String Max Allowed: 1 Length: 9	The PRO Number assigned to the shipment.	
/FreightPickupRequest/Existin	ngShipmentID/BOLID	)	
BOLID	Required: Yes* Type: String Max Allowed: 1 Length: 35	The retrieval key for the stored BOL.	

Name	Constraint	Description
/FreightPickupRequest/PO	М	
POM	Required: No Max Allowed: 1 Length: N/A	An identifier associated to the pickup request when the user elects to include Pickup Notifications for LTL.
/FreightPickupRequest/PO	M/POMNumber	
POMNumber	Required: Cond Type: String Max Allowed: 1 Length: 16	Identifies the kind of number used to identify the Pickup Notifications for LTL shipment.  Must provide a POMNumber if the POMNumberType field is populated.
/FreightPickupRequest/PO	M/POMNumberType	
POMNumberType	Required: No Type: String Max Allowed: 1 Length: 23	Identifies the type used to identify the Pickup Notifications for LTL shipments. Must provide if POMNumber is populated. For valid values, see POM Number Type Values in the Appendix. The values must match a type defined, case sensitive.
/FreightPickupRequest/PO	M/PickupNotifications	
PickupNotifications	Required: No Type: Container Max Allowed: 1 Length: N/A	Container for pre-pickup notifications events
/FreightPickupRequest/PO	M/PickupNotifications/C	ompanyName
CompanyName	Required: No Type: String Max Allowed: 1 Length: 35	Name of company
/FreightPickupRequest/PO	M/PickupNotifications/E	MailNotification
EMailNotification	Required: No Type: Container Max Allowed: 5 Length: N/A	Container for email notifications
/FreightPickupRequest/PO	M/PickupNotifications/E	MailNotification/EMailAddress
EMailAddress	Required: No Type: String Max Allowed: 1 Length: 50	Email address which should receive pre-pickup notification
/FreightPickupRequest/PO	M/PickupNotifications/E	MailNotification/EventType
EventType	Required: No Type: String Max Allowed: 4 Length: 2	Type of event for Pickup Notifications for LTL. Allows up to four events. For valid values, see LTL Event Types in the Appendix. The values must match a type defined, case sensitive.
/FreightPickupRequest/PO	M/PickupNotifications/F	ailedEMail
FailedEMail	Required: No Type: String Max Allowed: 1 Length: 50	Alternate email address to receive notifications regarding a failed email.

Name	Constraint	Description
/FreightPickupRequest/PickupRepuest/PickupRequest/PickupRe	ckupInstructions	
PickupInstructions	Required: No Type: String Max Allowed: 1 Length: 500	Pickup Instructions.
/FreightPickupRequest/Ac	IditionalComments	
AdditionalComments	Required: No Type: String Max Allowed: 1 Length: 500	The location of the freight. Example: Loading Dock A
/FreightPickupRequest/Ha	andlingInstructions	
HandlingInstructions	Required: No Type: String Max Allowed: 1 Length: 500	Handling Instructions text
/FreightPickupRequest/Sp	ecialInstructions	
SpecialInstructions	Required: No Type: String Max Allowed: 1 Length: 150	Special Instructions text
/FreightPickupRequest/De	eliveryInstructions	
DeliveryInstructions	Required: No Type: String Max Allowed: 1 Length: 500	Delivery Instructions text

## FreightPickupResponse Top Level Containers




## FreightPickupResponse XPath Table

Name	Constraint	Description		
/FreightPickupResponse		'		
FreightPickupResponse	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Freight Pickup Response container.		
/FreightPickupResponse/F	Response			
Response	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Response container.		
/FreightPickupResponse/F	Response/ResponseSta	ttus		
ResponseStatus	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Response Status container.		
/FreightPickupResponse/F	Response/ResponseSta	ttus/Code		
Code	Required: Yes Type: String Max Allowed: 1 Length: 1	Identifies the success or failure of the transaction.1 = Successful		
/FreightPickupResponse/F	Response/ResponseSta	utus/Description		
Description	Required: Yes Type: String Max Allowed: 1 Length: 135	Describes Response Status Code. Returns text of Success.		
/FreightPickupResponse/F	Response/Alert			
Alert	Required: No Type: Container Max Allowed: UNB Length: N/A	Alert container. There can be zero to many alert containers with code and description		
/FreightPickupResponse/F	/FreightPickupResponse/Response/Alert/Code			
Code	Required: Yes* Type: String Max Allowed: 1 Length: 110	Warning code returned by the system.		
/FreightPickupResponse/F	Response/Alert/Descript	tion		
Description	Required: Yes* Type: String Max Allowed: 1 Length: 1150	Warning messages returned by the system.		

Name	Constraint	Description	
/FreightPickupResponse/Re	sponse/TransactionR	eference	
TransactionReference	Required: No Type: Container Max Allowed: 1 Length: N/A	Transaction Reference container.	
/FreightPickupResponse/Re	sponse/TransactionR	eference/CustomerContext	
CustomerContext	Required: No Type: String Max Allowed: 1 Length: 1512	The CustomerContext Information which will be echoed during response.	
/FreightPickupResponse/Re	sponse/TransactionR	eference/TransactionIdentifier	
TransactionIdentifier	Required: No Type: String Max Allowed:1 Length: 35	The Unique TransactionIdentifier Information for that transaction. This will be present only if requested in the request.	
/FreightPickupResponse/PickupRequestConfirmationNumber			
PickupRequestConfirmationNu mber	Required: Yes Type: String Max Allowed: 1 Length: 35	Shipment pickup number.	

# Chapter 5: Cancel Pickup Ground Freight API Elements


## FreightCancelPickupRequest Top Level Containers



## FreightCancelPickupRequest XPath Table

Name	Constraint	Description		
/FreightCancelPickupRequest				
FreightCancelPickupReque st	Required: Yes Type: Container Max Allowed: 1 Length: N/A	FreightCancelPickupRequest container.		
/FreightCancelPickupReq	uest/Request			
Request	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Request container.		
/FreightCancelPickupReq	uest/Request/Transa	actionReference		
TransactionReference	Required: No Type: Container Max Allowed: 1 Length: N/A	TransactionReference identifies transactions between client and server.		
/FreightCancelPickupReq	uest/Request/Transa	actionReference/CustomerContext		
CustomerContext	Required: No Type: String Max Allowed: 1 Length: 152	The client uses CustomerContext to synchronize request/response pairs. The client establishes CustomerContext, which can contain any information you want, as long as it is valid XML; it is echoed back by the server.		
/FreightCancelPickupReq	uest/Request/Transa	actionReference/TransactionIdentifier		
TransactionIdentifier	Required: No Type: String Max Allowed: 1 Length: 0	The Unique TransactionIdentifier for a given transaction.		
/FreightCancelPickupRequest/PickupRequestConfirmationNumber				
PickupRequestConfirmatio nNumber	Required: Yes Type: Container Max Allowed: 1 Length: 35	Confirmation number of the pickup ground freight shipment to cancel.		

## FreightCancelPickupResponse Top Level Containers



## FreightCancelPickupResponse XPath Table

Name	Constraint	Description		
/FreightCancelPickupResponse				
FreightCancelPickupResp onse	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Freight Cancel response container.		
/FreightCancelPickupRes	sponse/Response			
Response	Required: Yes Type: Containder Max Allowed: 1 Length: N/A	Response container.		
/FreightCancelPickupRes	sponse/Response/Resp	onseStatus		
ResponseStatus	Required: Yes Type: String Max Allowed: 1 Length: N/A	Response Status container.		
/FreightCancelPickupRes	sponse/Response/Resp	onseStatus/Code		
Code	Required: Yes Type: String Max Allowed: 1 Length: 1	Identifies the success or failure of the transaction.1 = Successful		
/FreightCancelPickupRe	sponse/Response/Resp	onseStatus/Description		
Description	Required: Yes Type: String Max Allowed: 1 Length: 1	Warning messages returned by the system.		
/FreightCancelPickupRes	sponse/Response/Alert			
Alert	Required: Yes Type: Container Max Allowed: 1 Length: N/A	Alert container. There can be zero to many alert containers with code and description		
/FreightCancelPickupRes	sponse/Response/Alert/	Code		
Code	Required: Yes Type: String Max Allowed: 1 Length: 1	Warning code returned by the system.		
/FreightCancelPickupResponse/Response/Alert/Description				
Description	Required: Yes Type: String Max Allowed: 1 Length: 135	Warning messages returned by the system.		

Name	Constraint	Description	
/FreightCancelPickupR	Response/Response/Ti	ransactionReference	
TransactionReference	Required: No Type: Container Max Allowed: 1 Length: N/A	Transaction Reference container.	
/FreightCancelPickupR	Response/Response/Ti	ransactionReference/CustomerContext	
CustomerContext	Required: No Type: String Max Allowed: 1 Length: 1512	The CustomerContext Information that will be echoed during response.	
/FreightCancelPickupR	Response/Response/Ti	ransactionReference/TransactionIdentifier	
TransactionIdentifier	Required: No Type: String Max Allowed: 1 Length: 35	The unique TransactionIdentifier information for that transaction. This will be present only if requested in the request.	
/FreightCancelPickupR	Response/FreightCanc	elStatus	
FreightCancelStatus	Required: Yes Type: String Max Allowed: 1 Length: N/A	Container which stores the response status	
/FreightCancelPickupR	Response/FreightCanc	elStatus/Code	
Code	Required: Yes Type: String Max Allowed: 1 Length: 110	Identifies the success or failure of the transaction. 1 = Successful	
/FreightCancelPickupR	Response/FreightCanc	elStatus/Description	
Description	Required: Yes Type: String Max Allowed: 1 Length: 135	Describes the Response Status Code above.	

## Chapter 6: Pickup Ground Freight API Examples

### FreightPickupRequest Example

```
<envr:Envelope xmlns:auth="http://www.ups.com/schema/xpci/1.0/auth"</p>
xmlns:wsse="http://schemas.xmlsoap.org/ws/2002/04/secext"
xmlns:envr="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:upsa="http://www.ups.com/XMLSchema/XOLTWS/upssa/v1.0"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xmlns:common="http://www.ups.com/XMLSchema/XOLTWS/Common/v1.0"
xmlns:wsf="http://www.ups.com/schema/wsf">
   <envr:Header>
       <wsse:Security>
          <wsse:UsernameToken>
              <wsse:Username>Username</wsse:Username>
              <wsse:Password>Password</wsse:Password>
          </wsse:UsernameToken>
          <upsa:UPSServiceAccessToken>
              <upsa:AccessLicenseNumber>AccessLicenseNumber</upsa:AccessLicenseNumber>
          </upsa:UPSServiceAccessToken>
       </wsse:Security>
   </envr:Header>
   <envr:Body>
       <FreightPickupRequest
       xmlns="http://www.ups.com/XMLSchema/XOLTWS/FreightPickup/v1.0"
       xmlns:common="http://www.ups.com/XMLSchema/XOLTWS/Common/v1.0"
       xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
       xsi:schemaLocation="http://www.ups.com/XMLSchema/XOLTWS/FreightPickup/v1.0
       D:\Projects\XOLT WebServices\schemas\FreightPickup.xsd">
           <common:Request>
              <common:TransactionReference>
                  <common:CustomerContext/>
              </common:TransactionReference>
          </common:Request>
           <AdditionalComments>AdditionalComments</AdditionalComments>
          <DestinationPostalCode>DestinationPostalCode/DestinationPostalCode>
          <DestinationCountryCode>DestinationCountryCode</DestinationCountryCode>
          <Requester>
              <AttentionName>AttentionName</AttentionName>
              <EMailAddress>EMailAddress</EMailAddress>
              <Name>Name</Name>
              <Phone>
                  <Number>Number</Number>
              </Phone>
          </Requester>
           <ShipFrom>
              <AttentionName>AttentionName</AttentionName>
              <Name>Name</Name>
              <Address>
                  <AddressLine>AddressLine</AddressLine>
                  <City>City</City>
```

```
<StateProvinceCode>StateProvinceCode</StateProvinceCode>
                  <PostalCode>PostalCode</PostalCode>
                  <CountryCode>CountryCode</CountryCode>
              </Address>
              <Phone>
                 <Number>Number</Number>
              </Phone>
          </ShipFrom>
          <ShipmentDetail>
              <HazMatIndicator>
              </HazMatIndicator>
              <PackagingType>
                  <Code>Code</Code>
                  <Description>Description</Description>
              </PackagingType>
              <NumberOfPieces>NumberOfPieces</NumberOfPieces>
              <DescriptionOfCommodity>Description</DescriptionOfCommodity>
              <Weight>
                  <UnitOfMeasurement>
                     <Code>LBS</Code>
                     <Description>Pounds</Description>
                  </UnitOfMeasurement>
                 <Value>Value</Value>
              </Weight>
          </ShipmentDetail>
          <PickupDate>PickupDate</PickupDate>
          <EarliestTimeReady>EarliestTimeReady</EarliestTimeReady>
          <LatestTimeReady>LatestTimeReady</LatestTimeReady>
       </FreightPickupRequest>
   </envr:Body>
</envr:Envelope>
```

## FreightPickupResponse Example

```
<soapenv:Envelope xmlns:soapenv="http://schemas.xmlsoap.org/soap/envelope/">
   <soapenv:Header/>
   <soapenv:Body>
       <freightPickup:FreightPickupResponse</pre>
       xmlns:freightPickup="http://www.ups.com/XMLSchema/XOLTWS/FreightPickup/v1.0">
          <common:Response</p>
          xmlns:common="http://www.ups.com/XMLSchema/XOLTWS/Common/v1.0">
              <common:ResponseStatus>
                 <common:Code>Code</common:Code>
                  <common:Description>Description</common:Description>
              </common:ResponseStatus>
              <common:TransactionReference>
                  <common:CustomerContext/>
              </common:TransactionReference>
          </common:Response>
          <freightPickup:PickupRequestConfirmationNumber>PickupRequestConfirmationNumber
          freightPickup:PickupRequestConfirmationNumber>
```

</freightPickup:FreightPickupResponse>
</soapenv:Body>
</soapenv:Envelope>

### FreightCancelPickupRequest Example

```
<envr:Envelope xmlns:auth="http://www.ups.com/schema/xpci/1.0/auth"</pre>
xmlns:wsse="http://schemas.xmlsoap.org/ws/2002/04/secext"
xmlns:envr="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:upsa="http://www.ups.com/XMLSchema/XOLTWS/upssa/v1.0"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xmlns:common="http://www.ups.com/XMLSchema/XOLTWS/Common/v1.0"
xmlns:wsf="http://www.ups.com/schema/wsf">
   <envr:Header>
       <wsse:Security>
          <wsse:UsernameToken>
              <wsse:Username>Username</wsse:Username>
              <wsse:Password>Password</wsse:Password>
          </wsse:UsernameToken>
           <upsa:UPSServiceAccessToken>
              <upsa:AccessLicenseNumber>AccessLicenseNumber</upsa:AccessLicenseNumber>
          </upsa:UPSServiceAccessToken>
       </wsse:Security>
          <wsf:LumberJack wsf:pwd="IJkjN06" wsf:level="8"/>
       <wsf:pNg911jan06/>
   </envr:Header>
   <envr:Bodv>
       <FreightCancelPickupRequest
       xmlns="http://www.ups.com/XMLSchema/XOLTWS/FreightPickup/v1.0"
       xmlns:common="http://www.ups.com/XMLSchema/XOLTWS/Common/v1.0"
       xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
       xsi:schemaLocation="http://www.ups.com/XMLSchema/XOLTWS/FreightPickup/v1.0
       D:\Projects\XOLT WebServices\schemas\FreightPickup.xsd">
           <common:Request>
              <common:RequestOption/>
              <common:TransactionReference>
                  <common:CustomerContext/>
              </common:TransactionReference>
          </common:Request>
          <PickupRequestConfirmationNumber>PickupRequestConfirmationNumber</PickupReques
          tConfirmationNumber>
       </FreightCancelPickupRequest>
   </envr:Body>
</envr:Envelope>
```

## FreightCancelPickupResponse Example

```
<common:Response</pre>
          xmlns:common="http://www.ups.com/XMLSchema/XOLTWS/Common/v1.0">
              <common:ResponseStatus>
                  <common:Code>Code</common:Code>
                  <common:Description>Description/common:Description>
              </common:ResponseStatus>
              <common:TransactionReference>
                  <common:CustomerContext/>
              </common:TransactionReference>
          </common:Response>
          <freightPickup:FreightCancelStatus>
              <freightPickup:Code>Code</freightPickup:Code>
              <freightPickup:Description>Description</freightPickup:Description>
          </freightPickup:FreightCancelStatus>
       </freightPickup:FreightCancelPickupResponse>
   </soapenv:Body>
</soapenv:Envelope>
```

# Chapter 7: Pickup Ground Freight LTL API FAQs

NOTE: Common FAQS are available in the Introduction to the UPS Developer Kit guide located in the Dev Kit.

Question	Answer
What are the supported LTL Freight countries or	LTL Freight country or territory origins include US, CA & MX. The US territory means the contiguous 48 states of the US and Washington DC.
territories?	While we service Hawaii, Alaska, Guam, Puerto Rico and the US Virgin Islands, those rates can only be obtained by calling UPS Freight Customer Service at (800) 333-7400.

# **Appendices**

### **Error Codes (WS)**

When the UPS system is unable to respond to a request, be it from a malformed request, an illegal or invalid value, or other issues, the API generates an error response. For examples and additional information on error responses, refer to Chapter 3: Error Responses, in the Introduction to the UPS Developer Kit guide.

- · Successful responses may or may not include warnings.
  - o Without warnings Indicates the request has been processed as anticipated.
  - With warnings Indicates the request has been processed with potentially unanticipated results. The warning contains information in the response that should be passed to the end user.
- The severity of an error may be transient or hard.
  - o Transient error Indicates an error that is temporary in nature. Such errors may be caused by response timeouts due to high server loads or scheduled maintenance in progress. The request may be issued successfully at a later time.
  - o Hard error Indicates the request has a problem that the system is not able to resolve. These errors are critical and prevent requests from processing.



Do not resubmit requests with Hard Errors until the problems causing the error have been resolved.

#### **Common Error Codes**

The following error codes can apply to all Webservice and other APIs.

Code	Severity	Description
10001	Hard	The XML document is not well formed.
10002	Hard	The XML document is well formed but the document is not valid.
10003	Hard	The XML document is either empty or null.
10006	Hard	Although the document is well formed and valid, the element content contains values which do not conform to the rules and constraints contained in this specification.
10013	Hard	The message is too large to be processed by the Application.
20001	Transient	General process failure.
20002	Hard	The specified service name, {0}, and version number, {1}, combination is invalid.
20003	Hard	Please check the server environment for the proper J2EE ws apis.
20006	Hard	Invalid request action.
20007	Hard	Missing Required field, {0}.
20008	Hard	The field, {0}, contains invalid data, {1}.
20012	Hard	The Client Information exceeds its Maximum Limit of {0}.
250000	Hard	No XML declaration in the XML document.
250001	Hard	Invalid Access License for the tool. Please re-license.
250002	Hard	Invalid UserId/Password.
250003	Hard	Invalid Access License number.
250004	Hard	Incorrect UserId or Password.
250005	Hard	No Access and Authentication Credentials provided.
250006	Hard	The maximum number of user access attempts was exceeded.
250007	Hard	The UserId is currently locked out, please try again in 30 minutes.

Code	Severity	Description
250009	Hard	License Number not found in the UPS database.
250019	Hard	Invalid Field value.
250050	Transient	License system not available.

## Pickup Ground Freight Error Codes

### 9360577 - 9510185

Code	Severity	Description
9360577	Hard	POM not available for this origin.
9510028	Hard	It is too late to trigger a GWN pickup for today.
9510029	Hard	GWN Pickup is not available on this account.
9510090	Transient	Pickup service is unavailable due to unknown error
9510091	Transient	Pickup service is unavailable
9510100	Transient	Pickup Service Days webservice is unavailable
9510101	Transient	Pickup Creation webservice is unavailable
9510102	Transient	Pickup Trigger GWN webservice is unavailable
9510103	Transient	Pickup Rate webservice is unavailable
9510104	Transient	Pickup Cancel webservice is unavailable
9510105	Transient	Pickup Pending Status webservice is unavailable
9510106	Transient	Pickup Get Service Center webservice is unavailable
9510110	Hard	Closing time is less than the minimum window after present time
9510111	Hard	Closing time is less than the minimum window after ready time
9510112	Hard	Closing time and ready time are not on the same day
9510113	Hard	Received data containing a ready time later than the latest allowable ready time for the location
9510114	Hard	Closing time must be later than or equal to the earliest allowable close time
9510115	Hard	No Pickup days available for this location
9510116	Hard	Non-serviceable area. Location does not have pickup service available
9510117	Hard	The service(s) can not be picked up based on your ready time due to invalid data
9510118	Hard	The service(s) is not available for pickup on the selected day.
9510119	Hard	Invalid service designation
9510120	Hard	Order contains invalid pickup item quantities
9510121	Hard	Sorry, we are unable to service your pickup request on the day you have selected
9510122	Hard	Only future date pickup is available for pickup request with only Germany to Germany UPS Standard shipments

Code	Severity	Description
9510123	Hard	The billing account information provided was invalid.
9510124	Hard	The tracking numbers must be return or forward movement. Please remove those that are not return or forward movement, and re-submit order.
9510125	Hard	Tracking number does not start with 1Z
9510126	Hard	No more than 30 Tracking Numbers can be accepted
9510127	Hard	Tracking number does not accept pickup charge, please select other payment method.
9510128	Hard	Tracking number failed check digit validation
9510129	Hard	Return service labels do not accept pickup charge anymore, please select other payment method
9510130	Hard	Invalid data has been received, please check your request again
9510131	Hard	Order has already been canceled
9510132	Hard	Cannot cancel an order that has already been completed
9510133	Hard	Cannot cancel an order that has an invalid state
9510134	Hard	Unknown order number (PRN). Order number not found in data source
9510135	Hard	The provided pickup date is not the Green When Needed eligible date
9510136	Hard	It is too early to trigger a GWN pickup for the Next eligible day
9510139	Hard	GWN pickup is not available for the provided country code
9510140	Hard	It is too late to cancel the pickup request
9510141	Hard	No Pickup days available for this location
9510142	Hard	The address information passed in were not enough to guarantee a unique location for non-postal country.
9510143	Hard	Tracking number length error.
9510144	Hard	Tracking number contains invalid service indicator
9510145	Hard	Data integrity and or dependency is violated among some fields
9510146	Hard	Order Number must be 11 characters long
9510148	Hard	Populate the returnTrackingNumber element or the trackingData element, not both.
9510150	Hard	The postal code is invalid for state and country name
9510151	Hard	The state is not a valid state abbreviation for the country
9510152	Hard	Please verify that country code is correct and in upper case
9510153	Hard	The pickup window start time must be before the end time
9510154	Hard	The account number provided does not belong to the user
9510155	Hard	The account number provided is not able to pay for the pickup
9510156	Hard	The Origin postal code is invalid for the selected location
9510160	Hard	Pickup ready time can not be later than close time
9510161	Hard	Partial Data Returned. GWN pending not available

Code	Severity	Description
9510162	Hard	Partial Data Returned. On call pending not available
9510163	Hard	Order cannot be canceled with this PRN
9510164	Hard	Pickup Address not found for the Account Number. Please set up Pickup Address before you trigger Smart Pickup
9510165	Hard	This account is not set up for Smart Pickup service
9510166	Hard	Missing or Invalid ChargeCard
9510167	Hard	Missing or invalid ChargeCard Type
9510168	Hard	Missing or invalid ChargeCard expiration date
9510169	Hard	Missing or invalid ChargeCard security code
9510170	Hard	Missing or invalid ChargeCard number
9510171	Hard	Credit card has expired
9510172	Hard	Missing ChargeCard Address
9510178	Hard	Credit card declined, contact your financial institution
9510179	Hard	This credit card has been locked due to multiple unsuccessful attempts. Please use another credit card to continue or try again after 12 hours.
9510180	Hard	Invalid CardHolderName
9510181	Hard	Invalid ChargeCard AddressLine
9510182	Hard	Invalid ChargeCard City
9510183	Hard	Invalid ChargeCard StateProvince
9510184	Hard	Invalid ChargeCard PostalCode
9510185	Hard	Missing or Invalid ChargeCard country code

### 9500100 - 9500770

Error Code	Severity	Description
9500100	Hard	Invalid Request Document for Pickup Services
9500500	Hard	Missing or invalid PickupType
9500501	Hard	Missing or invalid DaysCountType
9500502	Hard	Missing or invalid NumberOfDays
9500503	Hard	Missing or invalid PickupAddress
9500504	Hard	Missing or invalid City
9500505	Hard	Missing or invalid StateProvince
9500506	Hard	Missing or invalid PostalCode
9500507	Hard	Missing or invalid CountryCode
9500508	Hard	Missing or invalid PickupPiece

Error Code	Severity	Description
9500509	Hard	Missing or invalid ServiceCode
9500510	Hard	Missing or invalid Quantity
9500511	Hard	Missing or invalid DestinationCountryCode
9500512	Hard	Missing or invalid ContainerCode
9500520	Hard	Missing or Invalid RatePickupIndicator
9500522	Hard	Missing Account when payment method is shipper account
9500523	Hard	Missing or invalid AccountNumber
9500524	Hard	Missing or invalid AccountCountryCode
9500525	Hard	Missing or invalid PickupDateInfo
9500526	Hard	Missing or invalid CloseTime
9500527	Hard	Missing or invalid ReadyTime
9500528	Hard	Missing or invalid PickupDate
9500529	Hard	Missing or invalid CompanyName
9500530	Hard	Missing or invalid ContactName
9500531	Hard	Missing or invalid AddressLine
9500532	Hard	Invalid Room
9500533	Hard	Invalid Floor
9500534	Hard	Invalid Urbanization
9500535	Hard	Invalid PickupPoint
9500536	Hard	Missing Phone
9500537	Hard	Missing or invalid Phone number
9500538	Hard	Invalid Phone extension
9500539	Hard	Invalid StreetNumber
9500540	Hard	Invalid StreetPrefix
9500541	Hard	Invalid StreetName
9500542	Hard	Invalid StreetType
9500543	Hard	Invalid StreetSuffix
9500545	Hard	Invalid UnparsedStreetAddress
9500546	Hard	Invalid StreetAddressArtifactSource
9500547	Hard	Invalid StreetAddressMatchCode
9500548	Hard	Missing or Invalid AlternateAddressIndicator
9500549	Hard	Missing or invalid number of PickupPiece
9500550	Hard	Missing or invalid Weight
9500551	Hard	Missing or invalid UnitOfMeasurement

Error Code	Severity	Description
9500552	Hard	Missing or invalid OverweightIndicator
9500553	Hard	Invalid TrackingNumber
9500554	Hard	Missing or invalid PaymentMethod
9500555	Hard	Invalid SpecialInstruction
9500556	Hard	Invalid ReferenceNumber
9500557	Hard	Invalid ConfirmationEmailAddress
9500558	Hard	Invalid UndeliverableEmailAddress
9500559	Hard	Invalid ProfileId
9500560	Hard	Invalid ProfileCountryCode
9500561	Hard	Missing or Invalid ResidentialIndicator
9500590	Hard	Missing or invalid ServiceDateOption
9500600	Hard	Invalid AddressLine
9500603	Hard	Missing PickupDateInfo When ServiceDateOption is 03
9500650	Hard	Missing or Invalid CancelBy
9500651	Hard	Missing or invalid AccountNumber when CancelBy is 01
9500652	Hard	Missing or invalid ServiceDate when CancelBy is 01
9500653	Hard	Missing or invalid GMTOffset when CancelBy is 01
9500654	Hard	Missing or invalid PRN when CancelBy is 02
9500655	Hard	Missing or invalid TrackingData /TrackingNumber
9500656	Hard	Missing or Invalid FreightOptions
9500657	Hard	No more than 1 PickupPiece is allowed for WW Express Freight shipments
9500658	Hard	Missing or Invalid Origin Service CountryCode
9500659	Hard	Missing or Invalid Origin ServiceCode
9500660	Hard	Missing or Invalid ShipmentDetail
9500661	Hard	Lift Gate for Pick Up accessorial is not allowed with Drop Off At UPS Facility accessorial.
9500662	Hard	Missing or Invalid DestinationAddress - City
9500663	Hard	Missing or Invalid DestinationAddress - StateProvince
9500664	Hard	Missing or Invalid DestinationAddress - PostalCode
9500665	Hard	Missing or Invalid DestinationAddress - CountryCode
9500666	Hard	Missing or Invalid Dimensions - UnitofMeasurement
9500667	Hard	Missing or Invalid Dimensions - Length
9500668	Hard	Missing or Invalid Dimensions - Width
9500669	Hard	Missing or Invalid Dimensions - Height
9500670	Hard	Missing or Invalid OriginAddress - City

Error Code	Severity	Description
9500671	Hard	Missing or Invalid OriginAddress - StateProvince
9500672	Hard	Missing or Invalid OriginAddress - PostalCode
9500673	Hard	Missing or Invalid OriginAddress - CountryCode
9500674	Hard	A pickup cannot have a KGS/IN or LBS/CM as its unit of measurements
9500678	Hard	Invalid ContainerCode
9500679	Hard	Invalid ServiceCode
9500680	Hard	Invalid Service Center Search Request
9500684	Hard	No Drop-Off UPS Facilities available for this location
9500685	Hard	No Hold for Pickup UPS Facility available for this location
9500686	Hard	Drop-off time must be with in Facility's hours of operations
9500687	Hard	Smart Pickup cannot be mixed with WW Express Freight shipment
9500689	Warning	Please contact customer service center for capacity authorization.
9500690	Hard	Shipment total weight has exceeded the maximum shipment weight limit of 99,999.9 kgs or 99,999.9 pounds.
9500693	Hard	The maximum per pallet weight for the selected service from the selected origin is %maxWeightOrig% pounds.
9500694	Hard	The maximum per pallet weight for the selected service from the selected origin is %maxWeightOrig% kg.
9500695	Hard	The maximum per pallet weight for the selected service to the selected destination is %maxWeightDest% pounds.
9500696	Hard	The maximum per pallet weight for the selected service to the selected destination is %maxWeightDest% kg.
9500697	Hard	The maximum dimensions for a pallet are ({0}) cm (length) by ({1}) cm (width) by ({2}) cm (height) for the selected origin.
9500698	Hard	The maximum dimensions for a pallet are ({0}) in (length) by ({1}) in (width) by ({2}) in (height) for the selected origin.
9500699	Hard	The maximum dimensions for a pallet are ({0}) cm (length) by ({1}) cm (width) by ({2}) cm (height) for the selected destination.
9500700	Hard	The maximum dimensions for a pallet are ({0}) in (length) by ({1}) in (width) by ({2}) in (height) for the selected destination.
9500701	Hard	Invalid pallet dimensions, the length must be longer than the width.
9500702	Hard	Missing or Invalid Unit Of Measure of Distance
9500703	Hard	Missing or Invalid Locale
9500704	Hard	Missing or Invalid Street Address
9500708	Hard	Invalid Search Radius
9500709	Hard	Invalid Maximum Location
9500710	Hard	Missing Origin Search Criteria Container
9500770	Warning	The pickup is chargeable and the charges will be billed to the shipper account.

### **Country or Territory Codes**

#### **Pickup Ground Freight API Supported Countries or Territories**

UPS country or territory code abbreviations generally follow the recommendations of the International Standards Organization (ISO), which publishes a list of country or territory abbreviations in ISO Standard 3166.



**NOTE**: Not all UPS services are available in every country or territory. Refer to the UPS Rate and Service Guide at UPS.com for more information on UPS services.

#### **LTL Freight Country or Territory Origins**

LTL Freight country origins include US, CA & MX. The US territory means the contiguous 48 states of the US and Washington DC. While we service Hawaii, Alaska, Guam, Puerto Rico and the US Virgin Islands, those rates can only be obtained by calling UPS Freight Customer Service at (800) 333-7400.

Country or Territory Name	Country or Territory Code
Canada	CA
Mexico	MX
Puerto Rico	PR
US	US

### **LTL Event Types**

Code	Description
EN	DRIVER_EN_ROUTE
PS	PICKUP_SECURED
PX	PICKUP_EXCEPTION
RR	PICKUP_REQUEST_CONFIRM

## **Packaging Type Codes**

Ground Freight Packaging Types for Rating, Shipping, and Packaging

Code	Description
BAG	Bag
BAL	Bale
BAR	Barrel
BDL	Bundle
BIN	Bin
вох	Вох
BSK	Basket
BUN	Bunch
CAB	Cabinet
CAN	Can

39

Code	Description
CAR	Carrier
CAS	Case
CBY	Carboy
CON	Container
CRT	Crate
CSK	Cask
CTN	Carton
CYL	Cylinder
DRM	Drum
LOO	Loose
ОТН	Other
PAL	Pail
PCS	Pieces
PKG	Package
PLN	Pipe Line
PLT	Pallet
RCK	Rack
REL	Reel
ROL	Roll
SKD	Skid
SPL	Spool
TBE	Tube
TNK	Tank
UNT	Unit
VPK	Van Pack
WRP	Wrapped

## **POM Number Type Values**

#### **Freight Class:**

- BOL number
- Load number
- Other
- P&M
- Pickup number
- Pickup Reference number
- PO number
- PRO number
- Project
- Quote number
- RA number
- Release number
- SID number
- Task
- VPRC

### **Service Codes**

Code	Charge
308	UPS Freight LTL
309	UPS Freight LTL - Guaranteed