CS162
Operating Systems and Systems Programming
Lecture 15

Demand Paging (Finished)

March 16th, 2016

Prof. Anthony D. Joseph
http://cs162.eecs.Berkeley.edu

Management & Access to the Memory Hierarchy



Some following questions

- During a page fault, where does the OS get a free frame?
  - Keeps a free list
  - Unix runs a "reaper" if memory gets too full
  - As a last resort, evict a dirty page first
- How can we organize these mechanisms?
  - Work on the replacement policy
- How many page frames/process?
  - Like thread scheduling, need to "schedule" memory resources:
    - » utilization? fairness? priority?
  - allocation of disk paging bandwidth

Demand Paging Cost Model

- Since Demand Paging like caching, can compute average access time! ("Effective Access Time")
  - EAT = Hit Rate x Hit Time + Miss Rate x Miss Time
  - EAT = Hit Time + Miss Rate x Miss Penalty
- Example:
  - Memory access time = 200 nanoseconds
  - Average page-fault service time = 8 milliseconds
  - Suppose p = Probability of miss, 1-p = Probably of hit
  - Then, we can compute EAT as follows:

$$\begin{aligned} EAT &= 200\text{ns} + p \times 8\text{ ms} \\ &= 200\text{ns} + p \times 8{,}000{,}000\text{ns} \end{aligned}$$

- If one access out of 1,000 causes a page fault, then EAT = 8.2 μs:
  - This is a slowdown by a factor of 40!
- What if want slowdown by less than 10%?
  - $200\text{ns} \times 1.1 < EAT \Rightarrow p < 2.5 \times 10^{-6}$
  - This is about 1 page fault in 400000!

What Factors Lead to Misses?

- Compulsory Misses:
  - Pages that have never been paged into memory before
  - How might we remove these misses?
    - » Prefetching: loading them into memory before needed
    - » Need to predict future somehow! More later.
- Capacity Misses:
  - Not enough memory. Must somehow increase size.
  - Can we do this?
    - » One option: Increase amount of DRAM (not quick fix!)
    - » Another option: If multiple processes in memory: adjust percentage of memory allocated to each one!
- Conflict Misses:
  - Technically, conflict misses don't exist in virtual memory, since it is a "fully-associative" cache
- Policy Misses:
  - Caused when pages were in memory, but kicked out prematurely because of the replacement policy
  - How to fix? Better replacement policy

Page Replacement Policies

- Why do we care about Replacement Policy?
  - Replacement is an issue with any cache
  - Particularly important with pages
    - » The cost of being wrong is high: must go to disk
    - » Must keep important pages in memory, not toss them out
- FIFO (First In, First Out)
  - Throw out oldest page. Be fair – let every page live in memory for same amount of time.
  - Bad – throws out heavily used pages instead of infrequently used
- MIN (Minimum):
  - Replace page that won't be used for the longest time
  - Great, but can't really know future…
  - Makes good comparison case, however
- RANDOM:
  - Pick random page for every replacement
  - Typical solution for TLB's. Simple hardware
  - Pretty unpredictable – makes it hard to make real-time guarantees

Replacement Policies (Con't)

- LRU (Least Recently Used):
  - Replace page that hasn't been used for the longest time
  - Programs have locality, so if something not used for a while, unlikely to be used in the near future.
  - Seems like LRU should be a good approximation to MIN.
- How to implement LRU? Use a list!



  - On each use, remove page from list and place at head
  - LRU page is at tail
- Problems with this scheme for paging?
  - Need to know immediately when each page used so that can change position in list…
  - Many instructions for each hardware access
- In practice, people approximate LRU (more later)

Example: FIFO

- Suppose we have 3 page frames, 4 virtual pages, and following reference stream:
  - A B C A B D A D B C B
- Consider FIFO Page replacement:

Ref: Page:	A	B	C	A	B	D	A	D	B	C	B
1	A					D				C	
2		B					A				
3			C						B		

- FIFO: 7 faults
- When referencing D, replacing A is bad choice, since need A again right away

Example: MIN

- Suppose we have the same reference stream:
  - A B C A B D A D B C B
- Consider MIN Page replacement:

Ref: Page:	A	B	C	A	B	D	A	D	B	C	B
1	A									C	
2		B									
3			C			D					

- MIN: 5 faults
  - Where will D be brought in? Look for page not referenced farthest in future.
- What will LRU do?
  - Same decisions as MIN here, but won't always be true!

When will LRU perform badly?

- Consider the following: A B C D A B C D A B C D
- LRU Performs as follows (same as FIFO here):

Ref: Page:	A	B	C	D	A	B	C	D	A	B	C	D
1	A			D			C			B		
2		B			A			D			C	
3			C			B			A			D

  - Every reference is a page fault!
- MIN Does much better:

Ref: Page:	A	B	C	D	A	B	C	D	A	B	C	D
1	A									B		
2		B					C					
3			C	D								

Graph of Page Faults Versus The Number of Frames



- One desirable property: When you add memory the miss rate drops
  - Does this always happen?
  - Seems like it should, right?
- No: Bélády's anomaly
  - Certain replacement algorithms (FIFO) don't have this obvious property!

Adding Memory Doesn't Always Help Fault Rate

- Does adding memory reduce number of page faults?
  - Yes for LRU and MIN
  - Not necessarily for FIFO! (Called Bélády's anomaly)

Ref: Page:	A	B	C	D	A	B	E	A	B	C	D	E
1	A			D			E					
2		B			A					C		
3			C			B					D	

Ref: Page:	A	B	C	D	A	B	E	A	B	C	D	E
1	A						E				D	
2		B						A				E
3			C						B			
4				D						C		

- After adding memory:
  - With FIFO, contents can be completely different
  - In contrast, with LRU or MIN, contents of memory with X pages are a subset of contents with X+1 Page

Administrivia

- Peer review is *NOT* optional
  - Every person must fill out the project 1 peer review
  - Due today Wed 3/16
    - » We will consider taking off points for missing reviews
  - The peer review is an important part of our evaluation of partner dynamics – *please take is very seriously*
- Survey on Piazza: Please tell us how the course is going!
  - What is going well, what is not going well
  - What could we change?
- Project 2 has been released
  - Get started early as design doc is due Monday 3/28

BREAK

Implementing LRU

- Perfect:
  - Timestamp page on each reference
  - Keep list of pages ordered by time of reference
  - Too expensive to implement in reality for many reasons
- Clock Algorithm: Arrange physical pages in circle with single clock hand
  - Approximate LRU (approx to approx to MIN)
  - Replace an old page, not the oldest page
- Details:
  - Hardware "use" bit per physical page:
    - » Hardware sets use bit on each reference
    - » If use bit isn't set, means not referenced in a long time
    - » Nachos hardware sets use bit in the TLB; you have to copy this back to page table when TLB entry gets replaced
  - On page fault:
    - » Advance clock hand (not real time)
    - » Check use bit: 1→used recently; clear and leave alone
      0→selected candidate for replacement
  - Will always find a page or loop forever?
    - » Even if all use bits set, will eventually loop around⇒FIFO

Clock Algorithm: Not Recently Used



Single Clock Hand:
Advances only on page fault!
Check for pages not used recently
Mark pages as not used recently

- What if hand moving slowly?
  - Good sign or bad sign?
    - » Not many page faults and/or find page quickly
- What if hand is moving quickly?
  - Lots of page faults and/or lots of reference bits set
- One way to view clock algorithm:
  - Crude partitioning of pages into two groups: young and old
  - Why not partition into more than 2 groups?

Nth Chance version of Clock Algorithm

- Nth chance algorithm: Give page N chances
  - OS keeps counter per page: # sweeps
  - On page fault, OS checks use bit:
    - » 1⇒clear use and also clear counter (used in last sweep)
    - » 0⇒increment counter; if count=N, replace page
  - Means that clock hand has to sweep by N times without page being used before page is replaced
- How do we pick N?
  - Why pick large N? Better approx to LRU
    - » If N ~ 1K, really good approximation
  - Why pick small N? More efficient
    - » Otherwise might have to look a long way to find free page
- What about dirty pages?
  - Takes extra overhead to replace a dirty page, so give dirty pages an extra chance before replacing?
  - Common approach:
    - » Clean pages, use N=1
    - » Dirty pages, use N=2 (and write back to disk when N=1)

Clock Algorithms: Details

- Which bits of a PTE entry are useful to us?
  - Use: Set when page is referenced; cleared by clock algorithm
  - Modified: set when page is modified, cleared when page written to disk
  - Valid: ok for program to reference this page
  - Read-only: ok for program to read page, but not modify
    - » For example for catching modifications to code pages!
- Do we really need hardware-supported "modified" bit?
  - No. Can emulate it (BSD Unix) using read-only bit
    - » Initially, mark all pages as read-only, even data pages
    - » On write, trap to OS. OS sets software "modified" bit, and marks page as read-write.
    - » Whenever page comes back in from disk, mark read-only

Clock Algorithms Details (continued)

- Do we really need a hardware-supported "use" bit?
  - No. Can emulate it similar to above:
    - » Mark all pages as invalid, even if in memory
    - » On read to invalid page, trap to OS
    - » OS sets use bit, and marks page read-only
  - Get modified bit in same way as previous:
    - » On write, trap to OS (either invalid or read-only)
    - » Set use and modified bits, mark page read-write
  - When clock hand passes by, reset use and modified bits and mark page as invalid again
- Remember, however, that clock is just an approximation of LRU
  - Can we do a better approximation, given that we have to take page faults on some reads and writes to collect use information?
  - Need to identify an old page, not oldest page!
  - Answer: second chance list

Second-Chance List Algorithm (VAX/VMS)



- Split memory in two: Active list (RW), SC list (Invalid)
- Access pages in Active list at full speed
- Otherwise, Page Fault
  - Always move overflow page from end of Active list to front of Second-chance list (SC) and mark invalid
  - Desired Page On SC List: move to front of Active list, mark RW
  - Not on SC list: page in to front of Active list, mark RW; page out LRU victim at end of SC list

Second-Chance List Algorithm (con't)

- How many pages for second chance list?
  - If 0 ⇒ FIFO
  - If all ⇒ LRU, but page fault on every page reference
- Pick intermediate value. Result is:
  - Pro: Few disk accesses (page only goes to disk if unused for a long time)
  - Con: Increased overhead trapping to OS (software / hardware tradeoff)
- With page translation, we can adapt to any kind of access the program makes
  - Later, we will show how to use page translation / protection to share memory between threads on widely separated machines
- Question: why didn't VAX include "use" bit?
  - Strecker (architect) asked OS people, they said they didn't need it, so didn't implement it
  - He later got blamed, but VAX did OK anyway

Free List



- Keep set of free pages ready for use in demand paging
  - Freelist filled in background by Clock algorithm or other technique ("Pageout demon")
  - Dirty pages start copying back to disk when enter list
- Like VAX second-chance list
  - If page needed before reused, just return to active set
- Advantage: Faster for page fault
  - Can always use page (or pages) immediately on fault

Demand Paging (more details)

- Does software-loaded TLB need use bit?
  Two Options:
  - Hardware sets use bit in TLB; when TLB entry is replaced, software copies use bit back to page table
  - Software manages TLB entries as FIFO list; everything not in TLB is Second-Chance list, managed as strict LRU
- Core Map
  - Page tables map virtual page → physical page
  - Do we need a reverse mapping (i.e. physical page → virtual page)?
    - » Yes. Clock algorithm runs through page frames. If sharing, then multiple virtual-pages per physical page
    - » Can't push page out to disk without invalidating all PTEs

Allocation of Page Frames (Memory Pages)

- How do we allocate memory among different processes?
  - Does every process get the same fraction of memory? Different fractions?
  - Should we completely swap some processes out of memory?
- Each process needs *minimum* number of pages
  - Want to make sure that all processes that are loaded into memory can make forward progress
  - Example: IBM 370 – 6 pages to handle SS MOVE instruction:
    - » instruction is 6 bytes, might span 2 pages
    - » 2 pages to handle *from*
    - » 2 pages to handle *to*
- Possible Replacement Scopes:
  - Global replacement – process selects replacement frame from set of all frames; one process can take a frame from another
  - Local replacement – each process selects from only its own set of allocated frames

Fixed/Priority Allocation

- Equal allocation (Fixed Scheme):
  - Every process gets same amount of memory
  - Example: 100 frames, 5 processes⇒process gets 20 frames
- Proportional allocation (Fixed Scheme)
  - Allocate according to the size of process
  - Computation proceeds as follows:
    s_i = size of process p_i and $S = \Sigma s_i$
    m = total number of frames

    a_i = allocation for p_i = $\dfrac{s_i}{S} \times m$
- Priority Allocation:
  - Proportional scheme using priorities rather than size
    - » Same type of computation as previous scheme
  - Possible behavior: If process p_i generates a page fault, select for replacement a frame from a process with lower priority number
- Perhaps we should use an adaptive scheme instead???
  - What if some application just needs more memory?

Page-Fault Frequency Allocation

- Can we reduce Capacity misses by dynamically changing the number of pages/application?



- Establish "acceptable" page-fault rate
  - If actual rate too low, process loses frame
  - If actual rate too high, process gains frame
- Question: What if we just don't have enough memory?

Thrashing



- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
  - low CPU utilization
  - operating system spends most of its time swapping to disk
- Thrashing ≡ a process is busy swapping pages in and out
- Questions:
  - How do we detect Thrashing?
  - What is best response to Thrashing?

Locality In A Memory-Reference Pattern

- Program Memory Access Patterns have temporal and spatial locality
  - Group of Pages accessed along a given time slice called the "Working Set"
  - Working Set defines minimum number of pages needed for process to behave well
- Not enough memory for Working Set⇒Thrashing
  - Better to swap out process?



Working-Set Model



- $\Delta \equiv$ working-set window $\equiv$ fixed number of page references
  - Example: 10,000 instructions
- WS_i (working set of Process P_i) = total set of pages referenced in the most recent Δ (varies in time)
  - if Δ too small will not encompass entire locality
  - if Δ too large will encompass several localities
  - if $\Delta = \infty \Rightarrow$ will encompass entire program
- $D = \Sigma|WS_i| \equiv$ total demand frames
- if $D > m \Rightarrow$ Thrashing
  - Policy: if $D > m$, then suspend/swap out processes
  - This can improve overall system behavior by a lot!

What about Compulsory Misses?

- Recall that compulsory misses are misses that occur the first time that a page is seen
  - Pages that are touched for the first time
  - Pages that are touched after process is swapped out/swapped back in
- Clustering:
  - On a page-fault, bring in multiple pages "around" the faulting page
  - Since efficiency of disk reads increases with sequential reads, makes sense to read several sequential pages
- Working Set Tracking:
  - Use algorithm to try to track working set of application
  - When swapping process back in, swap in working set

Reverse Page Mapping (Sometimes called "Coremap")

- Physical page frames often shared by many different address spaces/page tables
  - All children forked from given process
  - Shared memory pages between processes
- Whatever reverse mapping mechanism that is in place must be very fast
  - Must hunt down all page tables pointing at given page frame when freeing a page
  - Must hunt down all PTEs when seeing if pages "active"
- Implementation options:
  - For every page descriptor, keep linked list of page table entries that point to it
    - » Management nightmare – expensive
  - Linux 2.6: Object-based reverse mapping
    - » Link together memory region descriptors instead (much coarser granularity)

Linux Memory Details?

- Memory management in Linux considerably more complex that the previous indications
- Memory Zones: physical memory categories
  - ZONE_DMA: < 16MB memory, DMAable on ISA bus
  - ZONE_NORMAL: 16MB ⇒ 896MB (mapped at 0xC0000000)
  - ZONE_HIGHMEM: Everything else (> 896MB)
- Each zone has 1 freelist, 2 LRU lists (Active/Inactive)
- Many different types of allocation
  - SLAB allocators, per-page allocators, mapped/unmapped
- Many different types of allocated memory:
  - Anonymous memory (not backed by a file, heap/stack)
  - Mapped memory (backed by a file)
- Allocation priorities
  - Is blocking allowed/etc

Recall: Linux Virtual memory map



32-Bit Virtual Address Space

64-Bit Virtual Address Space

Virtual Map (Details)

- Kernel memory not generally visible to user
  - Exception: special VDSO facility that maps kernel code into user space to aid in system calls (and to provide certain actual system calls such as gettimeofday().
- Every physical page described by a "page" structure
  - Collected together in lower physical memory
  - Can be accessed in kernel virtual space
  - Linked together in various "LRU" lists
- For 32-bit virtual memory architectures:
  - When physical memory < 896MB
    - » All physical memory mapped at 0xC0000000
  - When physical memory >= 896MB
    - » Not all physical memory mapped in kernel space all the time
    - » Can be temporarily mapped with addresses > 0xCC000000
- For 64-bit virtual memory architectures:
  - All physical memory mapped above 0xFFFF800000000000

Internal Interfaces: Allocating Memory

- One mechanism for requesting pages: everything else on top of this mechanism:
  - Allocate contiguous group of pages of size 2^{order} bytes given the specified mask:

```
struct page * alloc_pages(gfp_t gfp_mask,
                          unsigned int order)
```

  - Allocate one page:

```
struct page * alloc_page(gfp_t gfp_mask)
```

  - Convert page to logical address (assuming mapped):

```
void * page_address(struct page *page)
```

- Also routines for freeing pages
- Zone allocator uses "buddy" allocator that tries to keep memory unfragmented
- Allocation routines pick from proper zone, given flags

Page Frame Reclaiming Algorithm (PFRA)

- Several entrypoints:
  - Low on Memory Reclaiming: The kernel detects a "low on memory" condition
  - Hibernation reclaiming: The kernel must free memory because it is entering in the suspend-to-disk state
  - Periodic reclaiming: A kernel thread is activated periodically to perform memory reclaiming, if necessary
- Low on Memory reclaiming:
  - Start flushing out dirty pages to disk
  - Start looping over all memory nodes in the system
    - » try_to_free_pages()
    - » shrink_slab()
    - » pdflush kernel thread writing out dirty pages
- Periodic reclaiming:
  - Kswapd kernel threads: checks if number of free page frames in some zone has fallen below pages_high watermark
  - Each zone keeps two LRU lists: Active and Inactive
    - » Each page has a last-chance algorithm with 2 count
    - » Active page lists moved to inactive list when they have been idle for two cycles through the list
    - » Pages reclaimed from Inactive list

SLAB Allocator

- Replacement for free-lists that are hand-coded by users
  - Consolidation of all of this code under kernel control
  - Efficient when objects allocated and freed frequently



- Objects segregated into "caches"
  - Each cache stores different type of object
  - Data inside cache divided into "slabs", which are continuous groups of pages (often only 1 page)
  - Key idea: avoid memory fragmentation

SLAB Allocator Details

- Based on algorithm first introduced for SunOS
  - Observation: amount of time required to initialize a regular object in the kernel exceeds the amount of time required to allocate and deallocate it
  - Resolves around object caching
    - » Allocate once, keep reusing objects
- Avoids memory fragmentation:
  - Caching of similarly sized objects, avoid fragmentation
  - Similar to custom freelist per object
- Reuse of allocation
  - When new object first allocated, constructor runs
  - On subsequent free/reallocation, constructor does not need to be reexecuted

SLAB Allocator: Cache Use

- Example:

```
task_struct_cachep =
     kmem_cache_create("task_struct",
                       sizeof(struct task_struct),
                       ARCH_MIN_TASKALIGN,
                       SLAB_PANIC | SLAB_NOTRACK,
                       NULL);
```

- Use of example:

```
struct task_struct *tsk;

tsk = kmem_cache_alloc(task_struct_cachep, GFP_KERNEL);
if (!tsk)
     return NULL;

kmem_free(task_struct_cachep,tsk);
```


SLAB Allocator Details (Con't)

- Caches can be later destroyed with:

```
int kmem_cache_destroy(struct kmem_cache *cachep);
```

  - Assuming that all objects freed
  - No one ever tries to use cache again
- All caches kept in global list
  - Including global caches set up with objects of powers of 2 from 2^5 to 2^{17}
  - General kernel allocation (kmalloc/kfree) uses least-fit for requested cache size
- Reclamation of memory
  - Caches keep sorted list of empty, partial, and full slabs
    - » Easy to manage – slab metadata contains reference count
    - » Objects within slabs linked together
  - Ask individual caches for full slabs for reclamation

Summary

- Replacement policies
  - FIFO: Place pages on queue, replace page at end
  - MIN: Replace page that will be used farthest in future
  - LRU: Replace page used farthest in past
- Clock Algorithm: Approximation to LRU
  - Arrange all pages in circular list
  - Sweep through them, marking as not "in use"
  - If page not "in use" for one pass, than can replace
- N^{th}-chance clock algorithm: Another approx LRU
  - Give pages multiple passes of clock hand before replacing
- Second-Chance List algorithm: Yet another approx LRU
  - Divide pages into two groups, one of which is truly LRU and managed on page faults.
- Working Set:
  - Set of pages touched by a process recently
- Thrashing: a process is busy swapping pages in and out
  - Process will thrash if working set doesn't fit in memory
  - Need to swap out a process