Modern C++ Programming

11. ADVANCED TOPICS

Federico Busato

University of Verona, Dept. of Computer Science 2018, v1.0



Agenda

Move Semantic

- Ivalues and rvalues
- Class move semantic
- std::move
- Universal reference
- Reference collapsing rules
- Type deduction
- Copy elision and RVO
- Perfect forwarding
- Compiler implicitly declared

C++ Idioms

- Rules of Three (and Zero)
- Rules of Five
- Singleton
- PIMLP
- CRTP
- Template virtual function

Smart Pointers

- std::unique_ptr
- std::shared_ptr
- std::weak_ptr

Concurrency

- Thread methods
- Parameters passing
- Mutex
- Atomic
- Task-based parallelism

C++ Guidelines

Move Semantic

Move semantics is about transferring ownership of resources from one object to another

It is different from **copy semantic** which give you a duplicate of the original resource

In C++ every expression is either an **rvalue** or an **Ivalue**

- a Ivalue represents an object that occupies some identifiable location in memory
- a rvalue is an expression that does not represent an object occupying some identifiable location in memory

```
int x = 5;  // x is a lvalues
int y = 10; // y is a lvalues
int z = (x * y); // y is an lvalue, (x * y) is an rvalue
```

C++11 introduces a new kind of reference called **rvalue** reference X&&

- An rvalue reference only binds to an rvalue, that is a temporary
- A Ivalue reference binds to an Ivalue, or to an rvalue if the Ivalue reference is const

```
struct A {};
void f(A& a) {}
void g(const A& a) {}
void h(A&& a) {}
int main() {
   A a:
    f(a); // ok, f() can modify "a"
   g(a); // ok, f() cannot modify "a"
// h(a); // compile error!! f() does not accept rvalues
// f(A()); // compile error!! f() does not accept rualues
   g(A()); // ok, f() cannot modify the object A()
   h(A()); // ok, f() can modify the object A()
```

The problem:

```
#include <algorithm>
#include <iostream>
struct AW { // array wrapper
  int _size;
 int* _array;
  AW(int size) : _size(size) {
      array = new int[size];
  AW(const AW& obj) : _size(obj._size){
      std::cout << "copy";</pre>
      _array = new int[_size];
      std::copy(obj._array,
                obj. array + size,
                _array);
  \sim AW() {
      delete[] array;
```

```
#include <vector>
int main() {
    std::vector<AW> vector;
    vector.push_back( AW(10) );
    // use vector
}
```

AW(10) cannot be passed by reference, otherwise _array is deallocated and it is no more valid in vector

Pass-by-value forces using the copy constructor, but it performs $\underline{redundant}$ operations (constructor + copy) since $\underline{AW}(10)$ is not more needed in \underline{main}

Class prototype with support for move semantic:

```
class X {
public:
   X();
                 // default constructor
   X(const X& obj); // copy constructor
   X(X&& obj); // move constructor
   X& operator=(const X& obj); // copy assign operator
   X& operator=(X&& obj); // move assign operator
   \sim X():
             // destructor
private:
   Y _data;
};
```

```
X(X\&\& obj);
```

Move constructor semantic:

- (1) Shallow copy of obj data members (in contrast to deep copy)
- (2) Release any obj resources and reset all data members (pointer to nullptr, size to 0, etc.)

```
X& operator=(X&& obj);
```

Move assignment semantic:

- (1) Release any resources of this
- (2) Shallow copy of obj data members (in contrast to deep copy)
- (3) Release any obj resources and reset all data members (pointer to nullptr, size to 0, etc.)
 - 4) Return *this

```
AW(AW&& obj) {
   _size = obj._size; // (1) shallow copy
   _array = obj._array; // note the difference with the copy constructor
   obj._size = 0; // (2) release obj (it is not more valid)
   obj._array = nullptr; // obj has been moved to *this
}
AW& operator=(AW&& obj) {
   delete[] _array; // (1) release this
   _size = obj._size; // (2) shallow copy
   _array = obj._array;
   delete[] obj._array; // (3) release obj
   obj. size = 0;
   return *this; // (4) return *this
```

C++11 provides the method std::move (<utility>) to indicate that an object may be "moved from"

It allows to efficient transfer resources from an object to another one

Considering the class array wrapper AW with support for move semantic:

```
#include <vector>
int main() {
    std::vector<AW> vector;
    vector.push_back( AW(10) ); // call move constructor
    // use vector

AW aw(10);
    vector.push_back( aw ); // call copy constructor
    vector.push_back( std::move(aw) ); // call move constructor
}
```

Universal Reference

The && syntax has two different meanings depending on the context it is used

- rvalue reference
- Either rvalue reference or lvalue reference (universal reference, cit. Scott Meyers)

```
struct A {}:
void f(A&& a) {} // rvalue only
template<typename T>
void g(T&& t) {} // universal reference
int main() {
   A a:
   f(A()); // ok
// f(a); // compile error (only rvalue) }
   g(A()); // ok
   g(a); // ok
```

```
void h() {
   A a1:
  A\&\& a2 = A(); // ok
// A&& a3 = a1; // compile error
                  // (only rvalue)
    auto&& a4 = A(); // ok
    auto\&\& a5 = a1: // ok
   A\&\& a6 = std::move(a1): // ok
```

10/54

Reference Collapsing Rules

Before C++11 (C++98, C++03), it was not allowed to take a reference to a reference (A&& causes a compile error)

C++11, by contrast, introduces the following **reference collapsing rules**:

Туре	Reference		Result
A&	&	\rightarrow	A&
A&	&&	\rightarrow	A&
A&&	&	\rightarrow	A&
A&&	&&	\rightarrow	A&&

Type Deduction (Template)

const A[3]

Туре	Т	T&	const T&	T&&
A a	A	A&	const A&	A& &&
A&	A	A&	const A&	A& &&
const A&	A	const A&	const A&	const A& &&
A&&	A	const A&	const A&	A& &&
A *	A*	A*&	cosnt A*&	A*& &&
const A*	const A*	const A*&	cosnt A*&	const A*& &&
A[3]	A *	(A&)[3]	const (A&)[3]	(A&)[3] &&

const A* const (A&)[3] const (A&)[3] const (A&)[3] &&

Type Deduction (auto)

Туре	auto	auto&	const auto&	auto&&
A a	A	A&	const A&	A&
A&	A	A&	const A&	A&
const A&	A	const A&	const A&	const A&
A&&	A	A&	const A&	A&
A *	A*	A*&	const A*&	A*&
const A*	const A*	const A*&	const A*&	const A*&
A[3]	A*	(A&)[3]	const (A&)[3]	(A&)[3]
const A[]	const A*	const (A&)[3]	const (A&)[3]	const (A&)[3]

Type Deduction (std::initializer_list)

```
#include <utility>
template<typename T>
void f(T a) {}
template<typename T>
void g(std::initializer_list<int>) {}
// auto h1() { return { 1, 2, 3 }; } // compile error
auto h2() { // ok
   return std::initializer_list<int>({ 1, 2, 3 });
}
int main() {
   auto x = \{ 1, 2, 3 \}; // x: std::initializer list<int>
// f({1,2,3}); // compile error
   g({1,2,3}); // ok
```

Type Deduction (decltype)

decltype can be combined with auto to prevent type decay

```
struct A {};
A a; A\& a1 = a;
  return a1;
decltype(auto) g() { // decltype(auto) : A& !!
   A a; A\& a1 = a;
   return a1;
decltype(auto) g() { // decltype(auto) : A& !!
   A a:
   return (a); // without (expr ) decltype(auto) : A
int main() {
   A a:
   const A\& a1 = a;
   auto x = a1; // x is of type "A"
   decltype(auto) y = a1; // y is of type "const A&"
```

Copy elision is a compiler optimization technique that eliminates unnecessary copying/moving of objects (it is defined in the C++ standard)

A compiler avoids omitting copy/move operations in these cases:

- RVO (Return Value Optimization) means the compiler is allowed to avoid creating temporary objects for return values
- NRVO (Named Return Value Optimization) means the compiler is allowed to return an object (with automatic storage duration) without invokes copy/move constructors

Copy Elision and RVO

AW f1() {

```
return AW(10); // RVO
                                           return AW(10);
                                           std::move(aw); // RVO
AW f2() {
                                       AW aw_global(10);
   AW aw(10);
                                       AW&& f7() {
   return aw; // NRVO
                                           return aw_global;
                                       } // copy constructor
AW f5() {
   AW aw(10);
                                       struct B {
   return std::move(aw);
                                         AW aw(10);
  // move constructor
                                       } b;
AW f3(bool b) {
                                       AW f8() {
   return b ? AW(10) : AW(5); // RVO
                                       return b.aw; // copy constructor
                                       }
AW f4(bool b) {
                                       int main() {
   AW aw1(10), aw1(5);
                                           AW aw = f1(); // ok RVO
   return b ? aw1(10) : aw1(5);
                                           aw = f1();
                                                                         17/54
} // copy constructor
                                       } // move operator= (no RVO)
```

AW&& f6() {

Perfect Forwarding

std::forward (<utility>) forwards the argument to another
function with the value category it had (lvalue/rvalue and
const/volatile modifiers) when passed to the calling function
(perfect forwarding)

```
#include <iostream>
                                         template<typename T>
template<typename T>
                                         void f1(T&& obj) {
void g(T& t) {
                                             g( obj );
    std::cout << "lvalue";
} // q(T\&) is never called if q(A(10))
                                         template<typename T>
                                         void f2(T&& obj) {
template<typename T>
void g(T&& t) {
                                             g( std::forward<T>(obj) );
    std::cout << "rvalue";
                                         int main(int argc) {
                                             g ( A(10) ); // print "rvalue"
// template<typename T>
// void g(T t) {
                                             f1( A(10) ); // print "lvalue"!!
// when call f1() T cannot
                                             f2( A(10) ); // print "rvalue" 18/54
// deduce T& or T&&
```

Compiler Implicitly Declares

	Special Members						
compiler implicitly declares							
		default constructor	destructor	copy constructor	copy assignment	move constructor	move assignment
user declares	Nothing	defaulted	defaulted	defaulted	defaulted	defaulted	defaulted
	Any constructor	not declared	defaulted	defaulted	defaulted	defaulted	defaulted
	default constructor	user declared	defaulted	defaulted	defaulted	defaulted	defaulted
	destructor	defaulted	user declared	defaulted	defaulted	not declared	not declared
	copy constructor	not declared	defaulted	user declared	defaulted	not declared	not declared
	copy assignment	defaulted	defaulted	defaulted	user declared	not declared	not declared
	move constructor	not declared	defaulted	deleted	deleted	user declared	not declared
	move assignment	defaulted	defaulted	deleted	deleted	not declared	user declared

Full story: www.slideshare.net/ripplelabs/howard-hinnant-accu2014 $^{\,19/54}$

C++ Idioms

Rule of Three

The **Rule of Three** is a rule of thumb for C++(03)

If your class needs $\underline{\text{any}}$ of

- a copy constructor X(const X&)
- an assignment operator X& operator=(const X&)
- or a destructor ~X()

defined explicitly, then it is likely to need <u>all</u> three of them

Some resources <u>cannot</u> or <u>should not</u> be copied. In this case, they should be declared as deleted

```
X(const X&) = delete
X& operator=(const X&) = delete
```

Note: many classes (such as **std** classes) manage resources themselves and should not implement copy/move constructor and assignment operator (**Rule of Zero**)

Rule of Five

The **Rule of Five** is a rule of thumb for C++11

If your class needs any of

- a copy constructor X(const X&)
- a move constructor X(X&&)
- an assignment operator X& operator=(const X&)
- an assignment operator X& operator=(X&&)
- or a destructor ~X()

defined explicitly, then it is likely to need all five of them

Singleton

Singleton is a software design pattern that restricts the instantiation of a class to one and only one object

A common application is for logging

```
class Singleton {
public:
    static Singleton& get_instance() { // note "static"
        static Singleton instance { ..init.. } ;
        return instance; // destroyed at the end of the program
    }
                           // initiliazed at first use
    Singleton(const& Singleton) = delete;
    void operator=(const& Singleton) = delete;
private:
   T data:
    Singleton( ..args.. ) { // used in the initialization
        . . .
```

PIMPL (Opaque Pointer)

Pointer to IMPLementation (PIMPL) idiom allow removing compilation dependencies on internal class implementations and improve compile times

```
{\tt header.hpp}
```

```
class A {      // the class A is responsible to allocate
public: // and deallocate Impl* ptr
    void f() {
        ptr->f();
private:
    class Impl; // forward declaration
    Impl* ptr; // opaque pointer
}:
source.cpp (Impl actual implementation)
class A::Impl {
public:
    void f() {
        ..do something..
};
```

The Curiously Recurring Template Pattern (CRTP) is an idiom in which a class X derives from a class template instantiation using X itself as template argument

A common application is static polymorphism

```
template <class T>
struct Base {
    void my_method() {
        static_cast<T*>(this)->implementation();
    }
};

class Derived : public Base<Derived> {
// void my_method() is inherited
private:
    void my_method_impl() { ... }
};
```

```
#include <iostream>
template <class T>
struct Writer {
    void write(const char* str) {
        static_cast<const T*>(this)->write_impl(str);
    }
};
class CerrWriter : public Writer<CerrWriter> {
private:
    void write_impl(const char* str) { std::cerr << str; }</pre>
};
class CoutWriter : public Writer<CoutWriter> {
private:
    void write_impl(const char* str) { std::cout << str; }</pre>
};
int main() {
   CoutWritter x;
   CerrWritter y;
   x.write("abc");
   y.write("abc");
```

Virtual functions cannot have template arguments, but they can be emulated by using the following pattern

```
class Base {
public:
    template<typename T>
    void method(T t);  // here we want to emulate a virtual method
}
```

```
class Base {
public:
    template<typename T>
    void method(T t) {
        v_method(t);    // call the actual implementation
    }
private:
    virtual void v_method(int t) = 0; // v_method is valid only
    virtual void v_method(double t) = 0; // for "int" and "double"
};
```

Actual implementations for derived class A and B

```
class AImpl : public Base {
protected:
    template<typename T>
    void t_method(T t) { // template "method()" implementation for A
        std::cout << "A " << t << std::endl;
    }
};
class BImpl : public Base {
protected:
    template<typename T>
    void t_method(T t) { // template "method()" implementation for B
        std::cout << "B " << t << std::endl;
    }
};
```

```
template<class <pre>Impl>
                                          int main(int argc, char* argv[]) {
class DerivedWrapper : public Impl {
                                              A a;
private:
                                              B b:
    void v method(int t) {
                                              Base* base = nullptr;
        Impl::t_method(t);
    }
                                              base = &a;
    void v_method(double t) {
                                              base->method(1); // print "A 1"
        Impl::t method(t);
                                              base->method(2.0); // print "A 2.0"
    } // call the base method
};
                                              base = \&b;
                                              base->method(1); // print "B 1"
using A = DerivedWrapper<AImpl>;
                                              base->method(2.0); // print "B 2.0"
using B = DerivedWrapper<BImpl>;
```

method() calls v_method() (pure virtual method of Base)
v_method() calls t_method() (actual implementation)

Smart pointers

Smart Pointers

Smart pointer is a pointer-like type with some additional functionality, e.g. *automatic memory deallocation* (when the pointer is no longer in use, the memory it points to is deallocated), reference counting, etc.

C++11 provides three smart pointer types:

std::unique_ptr

std::shared_ptr

std::weak_ptr

Smart pointers prevent most situations of memory leaks by making the memory deallocation automatic

Full Story: embeddedartistry.com

Smart Pointers Benefits

- If a smart pointer goes out-of-scope, the appropriate method to release resources is called automatically. The memory is not left dangling
- Smart pointers will automatically be set to nullptr if not initialized or when memory has been released
- std::shared_ptr provides automatic reference count
- If a special delete function needs to be called, it will be specified in the pointer type and declaration, and will automatically be called on delete

std::unique_ptr is used to manage any dynamically allocated
object that is not shared by multiple objects

```
#include <iostream>
#include <memory>
struct A {
    A() { std::cout << "Constructor\n"; } // called when A()
    \sim A() { std::cout << "Destructor\n"; } // called when u ptr1,
};
                                           // u ptr2 are out-of-scope
int main() {
    auto raw_ptr = new A();
    std::unique_ptr<A> u_ptr1(new A());
    std::unique_ptr<A> u_ptr2(raw_ptr);
// std::unique ptr<A> u ptr3(raw ptr); // no error, but wrong!!
                                        // (same pointer)
// u ptr1 = &raw ptr; // compile error (unique pointer)
// u_ptr1 = u_ptr2; // compile error (unique pointer)
   u_ptr1 = std::move(u_ptr2); // delete u ptr1;
                                // u_ptr1 = u_ptr2;
                                // u_ptr2 = nullptr
```

std::unique_ptr methods

- get() returns the underlying pointer
- operator* operator-> dereferences pointer to the
 managed object
- operator[] provides indexed access to the stored array (if it supports random access iterator)
- release() returns a pointer to the managed object and releases the ownership
- reset(ptr) replaces the managed object with ptr

Utility method: std::make_unique<T>() creates a unique
pointer of a class T that manages a new object

```
#include <iostream>
#include <memory>
struct A {
   int value;
};
int main() {
   std::unique_ptr<A> u_ptr1(new A());
   u_ptr1->value; // dereferencing
   (*u_ptr1).value; // dereferencing
   auto u_ptr2 = std::make_unique<A>(); // create a new unique pointer
   u_ptr1.reset(new A()); // reset
   auto raw_ptr = u_ptr1.release(); // release
   delete[] raw_ptr;
   std::unique_ptr<A[]> u_ptr3(new A[10]);
   auto& obj = u_ptr3[3];  // access
```

Implements a custom deleter

```
#include <iostream>
#include <memory>
struct A {
    int value;
};
int main() {
    auto DeleteLambda = [](A* x) {
        std::cout << "delete" << std::endl;
        delete x;
    };
    std::unique_ptr<A, decltype(DeleteLambda)>
        x(new A(), DeleteLambda);
} // print "delete"
```

std::shared_ptr is the pointer type to be used for memory that
can be owned by multiple resources at one time

std::shared_ptr maintains a reference count of pointer objects. Data
managed by std::shared_ptr is only freed when there are no remaining
objects pointing to the data

```
#include <iostream>
#include <memory>
struct A {
    int value;
};
int main() {
    std::shared_ptr<A> sh_ptr1(new A());
    std::shared_ptr<A> sh_ptr2(sh_ptr1);
    std::shared_ptr<A> sh_ptr3(new A());
    sh_ptr3 = nullptr; // allowed, the underlying pointer is deallocated
                       // sh_ptr3 : zero references
    sh_ptr2 = sh_ptr1; // allowed // sh_ptr1, sh_ptr2: two references
    sh_ptr2 = std::move(sh_ptr1); // allowed // sh_ptr1: zero references
35/54
                                             // sh ptr2: one references
```

std::shared_ptr methods

- get() returns the underlying pointer
- operator* operator-> dereferences pointer to the managed object
- use_count() returns the number of objects referring to the same managed object
- reset(ptr) replaces the managed object with ptr

Utility method: std::make_shared() creates a shared pointer
that manages a new object

```
#include <iostream>
#include <memory>
struct A {
   int value:
};
int main() {
   std::shared ptr<A> sh ptr1(new A());
   auto sh_ptr2 = std::make_shared<A>(); // std::make shared
   std::cout << sh_ptr1.use_count(); // print 1
   sh ptr1 = sh ptr2;
                                    // copy
// std::shared ptr<A> sh ptr2(sh ptr1); // copy (constructor)
   std::cout << sh_ptr1.use_count(); // print 2</pre>
   std::cout << sh_ptr2.use_count(); // print 2
   auto raw_ptr = sh_ptr1.get(); // get
   sh_ptr1.reset(new A());
                          // reset
    (*sh_ptr1).value = 3; // dereferencing
   sh_ptr1->value = 2;
                                    // dereferencing
```

A std::weak_ptr is simply a std::shared_ptr that is allowed to dangle (pointer not deallocated)

```
#include <iostream>
#include <memory>
struct A {
   int value;
};
int main() {
    auto ptr = new A();
    std::weak_ptr<A> w_ptr(ptr);
    std::shraed_ptr<A> sh_ptr(new A());
    sh ptr = nullptr;
// delete sh ptr.qet(); // double free or corruption
   w_ptr = nullptr;
   delete w_ptr; // ok valid
```

It must be converted to std::shared_ptr in order to access the referenced object

std::weak_ptr methods

- use_count() returns the number of objects referring to the same managed object
- reset(ptr) replaces the managed object with ptr
- expired() checks whether the referenced object was already deleted (true, false)
- lock() creates a std::shared_ptr that manages the referenced object

```
#include <iostream>
#include <memory>
struct A {
    int value:
};
int main() {
    auto sh_ptr1 = std::make_shared<A>();
    std::cout << sh_ptr1.use_count(); // print 1</pre>
    std::weak_ptr<A> w_ptr = sh_ptr1;
    std::cout << w_ptr.use_count(); // print 1</pre>
    auto sh ptr2 = w ptr.lock();
    std::cout << kk.use_count(); // print 2 (sh ptr1 + sh ptr2)
    sh_ptr1 = nullptr;
     std::cout << w ptr.expired(); // print false</pre>
    sh ptr2 = nullptr;
    std::cout << w_ptr.expired(); // print true</pre>
```

Concurrency

Overview

C++11 introduces the **Concurrency** library to simplify managing OS threads

```
#include <iostream>
#include <thread>

void f() {
    std::cout << "first thread" << std::endl;
}

int main() {
    std::thread th(f);
    th.join();  // stop the main thread until "th" complete
}</pre>
```

How to compile:

```
$g++ -std=c++11 main.cpp -pthread
```

Example

```
#include <iostream>
#include <thread>
#include <vector>
void f(int id) {
    std::cout << "thread " << id << std::endl;</pre>
int main() {
    std::vector<std::thread> thread vect; // thread vector
    for (int i = 0: i < 10: i++)
        thread vect.push back( std::thread(&f, i) );
    for (auto& th : thread_vect)
        th.join();
    thread_vect.clear();
    for (int i = 0; i < 10; i++) { // thread + lambda expression
        thread_vect.push_back(
            std::thread( [](){ std::cout << "thread\n"; });
```

Library methods:

- std::this_thread::get_id() returns the thread id
- std::thread::sleep_for(sleep_duration)
 Blocks the execution of the current thread for at least the specified sleep_duration
- std::thread::hardware_concurrency() returns the number of concurrent threads supported by the implementation

Thread object methods:

- get_id() returns the thread id
- join() waits for a thread to finish its execution
- detach() permits the thread to execute independently from the thread handle

```
#include <chrono> // the following program should (not deterministic)
#include <iostream> // produces the output:
#include <thread> // child thread exit
                    // main thread exit
int main() {
   using namespace std::chrono literals;
   std::cout << std::this_thread::get_id();</pre>
   std::cout << std::thread::hardware_concurrency(); // e.q. print 6
   auto lambda = \Pi() {
       std::this_thread::sleep_for(1s); // t2
       std::cout << "child thread exit\n":
   };
   std::thread child(lambda):
   child.detach(); // without detach(), child must join() the
                    // main thread (run-time error otherwise)
   std::this thread::sleep for(2s); // t1
   std::cout << "main thread exit\n";</pre>
// if t1 < t2 the should program prints:
   main thread exit
```

Parameters Passing

Parameters passing by-value or by-pointer to a thread function works in the same way of a standard function. Pass-by-reference requires a special wrapper (std::ref, std::cref) to avoid wrong behaviors

```
#include <iostream>
#include <thread>
void f(int& a, const int& b) {
    a = 7:
    const cast<int&>(b) = 8:
int main() {
   int a = 1, b = 2;
    std::thread th1(f. a. b):
                                                  // wrona!!!
    std::cout << a << ", " << b << std::endl; // print 1, 2!!
    std::thread th2(f, std::ref(a), std::cref(b)); // correct
    std::cout << a << ", " << b << std::endl; // print 7, 8!!
   th1.join(); th2.join();
```

The following code produces (in general) a value < 1000:

```
#include <chrono>
#include <iostream>
#include <thread>
#include <vector>
void f(int& value) {
   for (int i = 0; i < 10; i++) {
        value++:
        std::this_thread::sleep_for(std::chrono::milliseconds(10));
int main() {
    int value = 0:
    std::vector<std::thread> th vect;
   for (int i = 0: i < 100: i++)
        th vect.push back( std::thread(f, std::ref(value)) );
   for (auto& it : th_vect)
        it.join();
    std::cout << value;
```

47/54

C++11 provide the mutex class as synchronization primitive to protect shared data from being simultaneously accessed by multiple threads

mutex methods:

- lock() locks the mutex, blocks if the mutex is not available
- try_lock() tries to lock the mutex, returns if the mutex is not available
- unlock() unlocks the mutex

More advanced mutex can be found here: en.cppreference.com/w/cpp/thread C++ includes three mutex wrappers to provide safe copyable/movable objects:

- lock_guard (C++11) implements a strictly scope-based mutex ownership wrapper
- unique_lock (C++11) implements movable mutex ownership wrapper
- shared_lock (C++14) implements movable shared mutex ownership wrapper

```
#include <chrono>
#include <iostream>
#include <thread>
#include <vector>
void f(int& value, std::mutex& m) {
   for (int i = 0; i < 10; i++) {
        m.lock():
        value++: // other threads must wait
        m.unlock():
       std::this_thread::sleep_for(std::chrono::milliseconds(10));
int main() {
    std::mutex m;
   int value = 0;
    std::vector<std::thread> th_vect;
   for (int i = 0; i < 100; i++)
        th_vect.push_back( std::thread(f, std::ref(value), std::ref(m)) );
   for (auto& it : th vect)
       it.join();
    std::cout << value:
                                                                         48/54
```

Atomic

 $\mathtt{std::atomic}$ (C++11) template class defines an atomic type that are implemented with lock-free operations (much faster than locks)

```
#include <atomic>
... // include also: chrono, iostream, thread, vector
void f(std::atomic<int>& value) {
   for (int i = 0: i < 10: i++) {
       value++:
       std::this thread::sleep for(std::chrono::milliseconds(10));
   }
int main() {
   std::atomic<int> value(0):
   std::vector<std::thread> th_vect;
   for (int i = 0; i < 100; i++)
       th_vect.push_back( std::thread(f, std::ref(value)) );
   for (auto& it : th vect)
       it.join();
   std::cout << value; // print 1000
```

The future library provides facilities to obtain values that are returned and to catch exceptions that are thrown by *asynchronous* tasks

Asynchronous call: std::future async(function, args...)
runs a function asynchronously (potentially in a new thread)
and returns a std::future object that will hold the result

std::future methods:

- T get() returns the result
- wait() waits for the result to become available

async() can be called with two launch policies for a task executed:

- std::launch::async a new thread is launched to execute the task asynchronously
- std::launch::deferred the task is executed on the calling thread the first time its result is requested (lazy evaluation)

```
#include <iostream>
#include <vector>
#include <algorithm>
#include <numeric>
#include <future>
template <typename RandomIt>
int parallel_sum(RandomIt beg, RandomIt end) {
   auto len = end - beg:
   if (len < 1000) // base case
       return std::accumulate(beg, end, 0);
   RandomIt mid = beg + len / 2;
   auto handle = std::async(std::launch::async, // right side
                             parallel_sum<RandomIt>, mid, end);
   int sum = parallel sum(beg, mid);
                                                 // left side
   return sum + handle.get();
                                                 // left + right
int main() {
   std::vector<int> v(10000, 1); // init all to 1
   std::cout << "The sum is " << parallel_sum(v.begin(), v.end());</pre>
```

C++ Guidelines


C++ Core Guidelines

Authors: Bjarne Stroustrup, Herb Sutter



The guidelines are focused on relatively high-level issues, such as interfaces, resource management, memory management, and concurrency. Such rules affect application architecture and library design. Following the rules will lead to code that is statically type safe, has no resource leaks, and catches many more programming logic errors than is common in code today

High Integrity C++ Coding Standard (HIC++)



This document defines a set of rules for the production of high quality C++ code. The guiding principles of this standard are maintenance, portability, readability and robustness

CERT C++ Secure Coding

Author: Aaron Ballman



This standard provides rules for secure coding in the C++ programming language. The goal of these rules is to develop safe, reliable, and secure systems, for example by eliminating undefined behaviors that can lead to undefined program behaviors and exploitable vulnerabilities