

Network Layer Data Plane - Theory Notes

1. Introduction to Network Layer

Overview

The network layer is responsible for moving packets from a sending host to a receiving host. It operates on every Internet device including hosts and routers, making it a critical component of network communication.

Key Responsibilities

- **Encapsulation:** At the sender, the network layer encapsulates transport layer segments into datagrams and passes them to the link layer
- **Delivery:** At the receiver, it delivers segments to the transport layer protocol
- **Routing:** Routers examine header fields in all IP datagrams and move them from input ports to output ports along the end-to-end path

2. Network Layer Functions

Two Key Functions

Forwarding

Forwarding is the process of moving packets from a router's input link to the correct output link. It is a local function that happens within a single router. We can think of it like passing through a single interchange during a trip. Forwarding is very fast, typically operating in the nanosecond range, because it is handled by hardware.

Routing

Routing, on the other hand, is the process of deciding the path that packets will take from the source to the destination. Unlike forwarding, routing is a network-wide function that involves planning the entire journey across multiple routers. It relies on routing algorithms to determine the best paths and operates in the millisecond range since it is handled by software.

Relationship Between Functions

The forwarding function depends on the routing function, as routing algorithms create the forwarding tables that guide packet forwarding decisions at each router.

3. Data Plane vs Control Plane

Data Plane

The Data Plane (also called the forwarding plane) is responsible for moving packets from a router's input interface to the correct output interface. It operates locally within each router and works very

fast, usually in the nanosecond range, because it is implemented in hardware. Essentially, it handles the actual traffic and packet delivery.

Control Plane

The Control Plane, on the other hand, is responsible for deciding how packets should be routed across the network. It builds and updates routing tables using routing algorithms and network-wide information. This process is slower than the data plane, operating in the millisecond range, because it is handled by software. The control plane determines the rules, while the data plane executes them.

Two Control Plane Approaches:

1. Per-Router Control Plane (Traditional):

- Each router makes its own routing decisions.
- Routers run routing algorithms independently.
- Routers exchange information with each other.
- Distributed approach – decision-making is spread across all routers.

2. Software-Defined Networking (SDN) Control Plane:

- A central controller decides routes for all packets.
- Controller sends forwarding tables to routers.
- Centralized approach – one controller manages the network.
- Makes the network easier to program and control.

4. Network Service Models

Service Model Definition

A service model defines what services are provided for transporting datagrams from sender to receiver.

Types of Services

Individual Datagram Services

- **Guaranteed delivery:** Ensures packets reach destination
- **Guaranteed delivery with bounded delay:** Ensures packets arrive within specified time limit (e.g., less than 40 msec)

Flow of Datagrams Services

- **In-order datagram delivery:** Ensures packets arrive in sequence
- **Guaranteed minimum bandwidth:** Provides minimum throughput guarantee
- **Restrictions on inter-packet spacing:** Controls timing between packets

Internet's "Best-Effort" Service Model

The Internet uses a **best-effort service model**, which means it **tries to deliver packets but provides no guarantees**. The main characteristics are:

- **Delivery:** No guarantee that a datagram will reach its destination.
- **Timing:** No guarantee on when a datagram will arrive.
- **Order:** Datagrams may arrive out of order.
- **Bandwidth:** No guarantee on how much bandwidth is available for a flow.

Advantages of Best-Effort Service

- **Simplicity:** Its simple design allowed the Internet to be widely deployed and adopted.
- **Sufficient provisioning:** With enough bandwidth, real-time applications like voice and video perform "good enough" most of the time.
- **Distributed services:** Replicated application-layer services (like data centers and content delivery networks) provide content closer to users, improving performance.
- **Congestion control:** Helps manage "elastic" services that can adjust to network conditions.

5. Router Architecture

High-Level Architecture Overview

A router consists of several key components that work together to forward packets efficiently.

Main Components

- **Routing processor:** Handles control plane functions (routing, management)
- **High-speed switching fabric:** Connects input and output ports
- **Router input ports:** Receive incoming packets
- **Router output ports:** Send outgoing packets

Input Port Functions

Three Main Stages

1. **Physical Layer (Line Termination)**
 - Handles bit-level reception
 - Converts physical signals to digital data
2. **Link Layer Protocol Processing**
 - Processes link layer protocols (e.g., Ethernet)
 - Handles link-specific frame processing

3. Lookup, Forwarding, and Queuing

- Performs header field analysis
- Uses forwarding table for output port determination
- Implements "match plus action" paradigm

Decentralized Switching

In decentralized switching, the input ports of a switch handle the forwarding of packets themselves. The process works as follows:

- The input port looks at the header fields of each incoming packet.
- It uses a forwarding table stored in its memory to decide the correct output port.
- The main goal is to process packets at line speed, meaning as fast as they arrive.
- If packets arrive faster than they can be forwarded into the switch fabric, input port queuing occurs, temporarily storing packets until they can be processed.

Types of Forwarding

- **Destination-based forwarding:** Forward based only on destination IP address (traditional approach)
- **Generalized forwarding:** Forward based on any set of header field values

Longest Prefix Matching

Definition: Longest Prefix Matching is a method used by routers to decide which output port to forward a packet to. The router compares the destination IP address of the packet with entries in its routing table and chooses the entry that **matches the longest number of initial bits** (the longest prefix).

How it works:

- The router examines all routing table entries that match the packet's destination address.
- It selects the entry with the **most specific match** (longest prefix).
- The packet is then forwarded according to that routing table entry.

Implementation

- Often performed using Ternary Content Addressable Memories (TCAMs)
- **Content addressable:** present address to TCAM and retrieve result in one clock cycle
- Independent of table size
- Example: Cisco Catalyst can handle approximately 1M routing table entries in TCAM

Switching Fabrics

Purpose

Transfer packets from input links to appropriate output links at high speed.

Performance Metrics

- **Switching rate:** Rate at which packets can be transferred from inputs to outputs
- Often measured as multiple of input/output line rate
- For N inputs: switching rate of N times line rate is desirable

Three Major Types

1. Switching via Memory (First Generation)

- Traditional method where the **CPU controls switching** directly.
- Packets are copied into the **system's memory** before being forwarded.
- Speed is limited by **memory bandwidth**.
- Each packet requires **two bus crossings** (input → memory → output).

2. Switching via Bus

- Packets are transferred from **input port memory to output port memory** using a **shared bus**.
- **Bus contention** can limit the switching speed to the bus's bandwidth.
- Example: Cisco 5600 uses a 32 Gbps bus, suitable for access routers.

3. Switching via Interconnection Network

Switching via Interconnection Network means using a **network of smaller switches** (like a crossbar or Clos network) to connect input ports to output ports inside a switch or router. Instead of sending packets through memory or a shared bus, the pass through this network of interconnected paths.

Queuing in Routers

Input Port Queuing

Input port queuing happens when the **switch fabric is slower** than the combined speed of all input ports.

- **Head-of-the-Line (HOL) Blocking:** A packet at the front of the queue can block other packets behind it from moving forward.
- Can cause queueing delay and loss due to input buffer overflow
- **Output port contention:** Only one packet can be transferred at a time

Output Port Queuing

Output port queuing occurs when packets arrive from the switch fabric **faster than the link can transmit**.

- **Buffer requirements:** Buffers are needed when the arrival rate exceeds the transmission rate.
- **Drop policy:** Determines which packets are dropped if the buffer is full.
- **Scheduling discipline:** Decides the order in which queued packets are transmitted.
- Can lead to **packet loss** due to congestion or lack of buffer space.

Buffer Management

Buffer Management refers to how a network device (like a router or switch) handles temporary storage of packets when they cannot be immediately forwarded due to congestion or speed mismatches.

How Much Buffering?

Buffering in a switch or router is needed to **temporarily store packets** when they arrive faster than they can be transmitted. The required buffer size depends on the link capacity, network delays, and the number of flows.

Key Terms:

- **RTT (Round-Trip Time):** The time it takes for a packet to travel from the sender to the receiver **and back again**, usually measured in milliseconds (ms).
- **C (Link Capacity):** The maximum data rate of the link.
- **N (Number of Flows):** The number of simultaneous data streams (like TCP connections) sharing the link.

Buffering Rules and Recommendations:

1. RFC 3439 Rule of Thumb:

- Buffer size $\approx \text{RTT} \times C$
- *Example:* For a 10 Gbps link with 250 ms RTT:

$$\text{Buffer} = 10 \text{ Gbps} \times 0.25 \text{ s} = 2.5 \text{ Gbits}$$

2. Modern Recommendation (for multiple flows):

- If there are **N flows**, buffer size can be reduced to:

$$\text{Buffer} = \frac{\text{RTT} \times C}{\sqrt{N}}$$

- This accounts for statistical multiplexing, as many flows smooth out bursts.

Buffer Management Policies

Drop policies:

1. Tail Drop (TD)

Definition:

Tail Drop is the simplest queue management method. When the router's buffer is full, any incoming packets are simply dropped (from the "tail" of the queue).

Characteristics:

- **Simplicity:** Very easy to implement.
- **Behavior under congestion:** All packets are treated equally; the last packets arriving are dropped first.
- **Drawbacks:**
 - Can lead to **global synchronization**: multiple TCP flows reduce their window simultaneously, causing underutilization.
 - **No differentiation** between important and less important packets.

Preferred when:

- Network is simple, low-cost devices.
- Traffic is mostly homogeneous (all flows are of equal priority).
- Simplicity is more important than performance optimization.

2. Priority-Based Buffer Management (PBM)

Definition:

PBM manages the buffer by assigning **priorities to packets**. High-priority packets are less likely to be dropped, while low-priority packets can be dropped first when the buffer is congested.

Characteristics:

- **Intelligent packet handling:** Prioritizes important traffic (e.g., VoIP, video).
- **Fairness control:** Can combine with other policies like Weighted Fair Queuing.
- **Complexity:** Requires more processing and proper classification.

Preferred when:

- Network carries **heterogeneous traffic** with varying importance.
- QoS (Quality of Service) guarantees are needed (e.g., real-time video, voice).
- Congestion needs to be controlled more **gracefully** without impacting critical flows.

Marking: Mark packets to signal congestion (ECN, RED)

1. RED (Random Early Detection)

- **Purpose:** Avoid buffer overflow and reduce TCP global synchronization by **early detection** of congestion.
- **How it works:**
 - Router monitors average queue length.
 - **If avg queue length < min threshold:** No packets dropped/marked.
 - **If avg queue length > max threshold:** All incoming packets are dropped.
 - **If avg queue length between min & max:** Some packets are **dropped randomly**.
- **Marking packets:**
 - Original RED drops packets.
 - **With ECN-capable RED:** Instead of dropping, the router **marks the ECN field** in the packet header.

2. ECN (Explicit Congestion Notification)

- **Purpose:** Signal congestion **without dropping packets**.
- **How it works:**
 - ECN-enabled routers check for congestion (using RED or other methods).
 - **Packets marked:** Packets with **ECN-capable bits set** (from TCP header: **ECT(0)/ECT(1)**).
 - Marking indicates **"congestion experienced"** to the receiver.
 - Receiver informs sender (via TCP CE code) to **reduce sending rate**.

Packet Scheduling

First Come, First Served (FCFS/FIFO)

- Packets transmitted in order of arrival to output port
- Simplest scheduling approach
- No differentiation between packet types

Priority Scheduling

- Incoming packets are grouped into different priority classes.
- Any information in the packet header can be used to decide its class.
- The router or switch always sends packets from the highest-priority queue that has packets waiting.

- Within each priority class, packets are sent in first-come, first-served (FCFS) order.

Round Robin (RR) Scheduling

- Incoming packets are also grouped by class.
- The router or switch cycles through all class queues one by one.
- It sends one full packet from each class in turn, if packets are available.
- This way, all classes get a fair chance to be transmitted.

Weighted Fair Queuing (WFQ)

- Generalized Round Robin approach
- Each class has weight w_i
- Provides minimum bandwidth guarantee per traffic class
- Each class gets weighted amount of service: $w_i / \sum w_j$

6. IP Protocol

Internet Protocol

The **Internet Protocol (IP)** is a **network layer protocol** that defines how data is **packaged, addressed, transmitted, and routed** across networks so it can travel from the **source host** to the **destination host**

Key Components

- **IP protocol:** Handles datagram format, addressing, and packet handling conventions
- **ICMP protocol:** Provides error reporting and router signaling
- **Forwarding table:** Used by routers for packet forwarding decisions
- **Path-selection algorithms:** Implemented in routing protocols (OSPF, BGP) or SDN controllers

IP Fragmentation and Reassembly

Different networks have different Maximum Transmission Units (MTU) (the largest packet size they can carry). If an IP datagram is larger than the MTU of a link, it must be fragmented into smaller pieces. Each fragment is transmitted separately and later reassembled at the destination host.

Example For a 4000-byte datagram with MTU = 1500 bytes:

- Original: ID=x, offset=0, flag=0, length=4000
- Fragment 1: ID=x, offset=0, flag=1, length=1500 (1480 bytes data)
- Fragment 2: ID=x, offset=185, flag=1, length=1500 (1480 bytes data)
- Fragment 3: ID=x, offset=370, flag=0, length=1040 (1020 bytes data)

7. IP Addressing

An IP address is a unique identifier for a device on a network, used for addressing and routing data packets.

IP Address Fundamentals

Basic Concepts

- **IP address:** 32-bit identifier associated with each host or router interface
- **Interface:** Connection between host/router and physical link
- **Router interfaces:** Routers typically have multiple interfaces
- **Host interfaces:** Hosts typically have one or two interfaces (wired Ethernet, wireless 802.11)

Dotted-Decimal Notation

IP addresses are represented in dotted-decimal format:

- Example: 223.1.1.1 = 11011111 00000001 00000001 00000001
- Each octet represents 8 bits (0-255 decimal range)

Subnets

Subnet Definition

A subnet consists of device interfaces that can physically reach each other without passing through an intervening router.

What is Subnetting?

- Subnetting means **splitting a large network into smaller networks**, called **subnets**.
- Each subnet acts like its **own little network** where devices can communicate more easily.
- Example: In a company, HR, Sales, and IT can each have their **own subnet**.

Why do we subnet?

1. **Save IP addresses** – avoids wasting unused addresses.
2. **Better performance** – traffic stays inside each subnet, avoiding congestion.
3. **Improved security** – one department cannot easily access another department's devices.

Subnetting = divide network → save IPs → improve speed & security.

A **subnet mask** is a 32-bit number used in IP addressing to separate the network portion of an IP address from the host portion

IP Address Structure

An IPv4 address has 4 parts (octets), like 192.168.1.1.

Two main sections:

1. Network part – identifies the network
2. Host part – identifies the device in that network

Classes:

- Class A: 8 bits network, 24 bits host
- Class B: 16 bits network, 16 bits host
- Class C: 24 bits network, 8 bits host

Subnet Mask Notation

- **CIDR notation:** a.b.c.d/x, where x is number of bits in subnet portion
- Example: 223.1.1.0/24 means first 24 bits identify subnet
- **Subnet mask:** /24 means 24 bits are for the network, 8 bits for hosts.

CIDR (Classless Inter Domain Routing)

CIDR is a way of allocating IP addresses and routing without using the old fixed classes

Key Features

- **Arbitrary length:** Subnet portion can be any length
- **Address format:** a.b.c.d/x format
- **Flexibility:** Allows efficient address space utilization

Example

- Address: 200.23.16.0/23
- Binary: 11001000 00010111 00010000 00000000
- Subnet part: First 23 bits
- Host part: Last 9 bits

How Subnetting Works

1. Take some bits from the host part to create subnets.
2. Each subnet has:
 - **Subnet ID** – identifies the subnet
 - **Broadcast ID** – used to send messages to all hosts in that subnet
 - **Usable hosts** – actual devices in the subnet

1. **Subnet ID** = First IP in the block (IP AND Subnet Mask)
2. **Broadcast ID** = Last IP in the block = (Next subnet – 1)
3. **Usable Hosts** = All IPs between Subnet ID and Broadcast
→ Count = $2^h - 2$ where h = host bits

Example – Class C network 193.1.2.0/25:

- **Subnet-1:** 193.1.2.0 – 193.1.2.127
 - Subnet ID = 193.1.2.0
 - Broadcast ID = 193.1.2.127
 - Usable hosts = 126
- **Subnet-2:** 193.1.2.128 – 193.1.2.255
 - Subnet ID = 193.1.2.128
 - Broadcast ID = 193.1.2.255
 - Usable hosts = 126

Rule: More subnets → fewer usable hosts in each subnet

Hierarchical Addressing

- **Definition:** IP addresses are arranged in a hierarchy to make routing simpler and more efficient.
- **Levels:** Usually three levels:
 1. **Network/Organization level** – identifies the overall network.
 2. **Subnet level** – divides the network into smaller subnetworks.
 3. **Host level** – identifies individual devices within a subnet.
- **Advantage:** Routers mainly use the network part to forward packets, **reducing the size of routing tables**.
- **Example:** In IP 192.168.1.10/24:
 - 192.168 → network
 - .1 → subnet
 - .10 → host

More Specific Routes

- When an organization **changes ISPs**, the new ISP advertises a **more specific route**.
- **Longest prefix matching** ensures packets are delivered to the correct network.

- **Example:** If a company moves from one ISP to another, the more specific route from the new ISP takes precedence, ensuring proper routing.

Getting IP Addresses

Two Questions

1. How does a host get IP address within its network?
2. How does a network get IP addresses for itself?

Host Address Assignment Methods

1.Static configuration: Hard-coded by system administrator

A host can obtain an IP address through **static configuration**, where the system administrator manually assigns the address in a configuration file. This method ensures the host always has the same IP address, which is useful for servers or devices that must be easily reachable. However, static assignment is inflexible and can become difficult to manage in large networks.

2.DHCP: Dynamic Host Configuration Protocol for automatic assignment

The more common approach is **dynamic assignment using DHCP (Dynamic Host Configuration Protocol)**. With DHCP, a host automatically requests an IP address from a DHCP server when it connects to the network. The server responds with an available IP along with other important configuration details such as subnet mask, default gateway, DNS server, and lease time.

How a Network Gets Its Subnet Part

- The network gets a **big block of IP addresses** from an Internet authority (like IANA or a regional registry).
- The network administrator **splits this block into smaller parts** called subnets.
- Each subnet has a **unique ID**, which becomes the subnet part of the IP address.
- The **subnet mask** tells the system which part of the IP is for the network/subnet and which part is for hosts.
- This helps organize many smaller networks within the bigger network **without address conflicts**.

8. DHCP (Dynamic Host Configuration Protocol)

DHCP Overview

Purpose

DHCP allows hosts to dynamically obtain IP addresses from a network server when joining a network.

Key Benefits

- **Plug-and-play:** Automatic network configuration
- **Address reuse:** Addresses only held while connected
- **Mobility support:** Supports mobile users joining/leaving networks
- **Lease renewal:** Can renew address lease while in use

DHCP Operation

Four-Step Process

1. **DHCP Discover:** Host broadcasts discovery message (optional)
2. **DHCP Offer:** DHCP server responds with offer message (optional)
3. **DHCP Request:** Host requests specific IP address
4. **DHCP ACK:** DHCP server confirms address assignment

Message Details(How DHCP (Dynamic Host Configuration Protocol) assigns an IP address to a host)

1. DHCP Discover (Broadcast)

- When a host (e.g., your laptop) connects to a network, it doesn't have an IP address yet.
- It sends a **DHCP Discover message** as a **broadcast** (to all devices in the LAN) saying:

"Is there any DHCP server? I need an IP address."

2. DHCP Offer (Server Reply)

- A DHCP server on the network receives the Discover message.
- The server responds with a **DHCP Offer message** (also broadcast).
- This offer includes:

"I'm a DHCP server! Here's an IP address you can use, along with subnet mask, gateway, DNS, etc"


3. DHCP Request (Client Chooses)

- The host may receive offers from multiple DHCP servers.
- It picks **one offer** and replies with a **DHCP Request message** (broadcast), saying:

"OK. I want to use this IP address from this server"

4. DHCP Acknowledgment (Final Assignment)

- The selected DHCP server sends a broadcast ACK:
- "Great! You've got this IP address."
- The client configures itself with the assigned IP and can now communicate on the network.



DHCP provides more than just IP addresses:

1. Default Gateway

- The IP address of the **first-hop router** (also called the default router).
- The client uses this gateway to send packets **outside its local network**.

2. DNS Server

- DHCP can provide the **IP address of a DNS server**.
- This allows the client to resolve domain names (like `www.google.com`) into IP addresses.

3. Subnet Mask

- Informs the client which part of the address is the **network portion** and which is the **host portion**.

4. Lease Time

- The **time duration** for which the IP address is valid.

NAT (Network Address Translation)

Definition

Network Address Translation (NAT) is a technique that allows multiple devices within a private network to access external networks (like the Internet) using a **single public IP address**. NAT was introduced to slow down IPv4 address exhaustion.

How NAT Works

- Devices inside a private network use private IP addresses (e.g., 192.168.x.x, 10.x.x.x, 172.16.x.x – 172.31.x.x).
- When a device sends a packet to the Internet, the NAT-enabled router replaces the **source private IP address** with the **public IP address** assigned by the ISP.
- The router also modifies the source port number and records the mapping in a **translation table**.
- When a response arrives, the router consults the table to deliver the packet to the correct internal device.

Example:

- 10.0.0.1:1025 → Internet becomes 138.76.29.7:5001 → Internet
- 10.0.0.2:1025 → Internet becomes 138.76.29.7:5002 → Internet

Advantages of NAT

1. Saves IPv4 addresses by allowing many hosts to share one public IP.
2. Provides some security by hiding internal IP addresses.
3. Makes internal addressing flexible, since changes don't affect external communication.
4. ISPs and organizations can change providers without renumbering internal networks.

Disadvantages of NAT

1. Breaks the **end-to-end principle**, since internal addresses are hidden.
2. It was intended as a temporary solution until IPv6 adoption, but is still widely used.

IPv6 (Internet Protocol version 6)

Motivation

IPv4 uses 32-bit addresses, which allows for about 4.3 billion unique addresses. With the explosive growth of the Internet, IPv4 addresses have become scarce. IPv6 solves this by introducing **128-bit addresses**, which provide 3.4×10^{38} possible addresses.

Features of IPv6

1. **Larger address space** – Supports virtually unlimited devices.
2. **Simplified header** – IPv6 has a fixed 40-byte header, making packet processing faster.
3. **No checksum field** – Eliminates checksum calculation, improving router performance.
4. **No router fragmentation** – Only source devices can fragment packets. Routers drop oversized packets and send an ICMPv6 "Packet Too Big" message.
5. **Extension headers** – Options are placed in extension headers instead of the base header.

6. **Flow label** – Provides special handling for real-time traffic such as video or voice.
7. **Auto-configuration** – Devices can configure themselves using Stateless Address Autoconfiguration (SLAAC).

Transition from IPv4 to IPv6

The Internet cannot migrate from IPv4 to IPv6 instantly. Both run in parallel for many years. Transition mechanisms include:

- **Dual stack** – Devices run both IPv4 and IPv6.
- **Tunneling** – IPv6 packets are encapsulated inside IPv4 packets to travel across IPv4 networks.
- **Translation** – Protocol translation allows IPv6 devices to communicate with IPv4 devices.

IPv6 deployment has been slower than expected. Today, many ISPs and organizations use IPv4 with NAT, though IPv6 usage is steadily increasing.

Generalized Forwarding and Software-Defined Networking (SDN)

Traditional Forwarding

In traditional IP networks, routers forward packets based only on the **destination IP address** in the packet header. This is simple but limited.

Generalized Forwarding

Generalized forwarding uses the principle of **match + action**. Instead of just looking at the destination IP, routers and switches can examine multiple header fields and apply flexible actions.

- **Match fields:** Source IP, destination IP, source port, destination port, MAC address, VLAN ID, protocol type, etc.
- **Actions:** Forward to a specific output port, drop the packet, modify header fields, mirror traffic, or send to a controller.

OpenFlow and SDN

OpenFlow is a protocol that enables Software-Defined Networking (SDN). In SDN, the **control plane** (decision-making) is separated from the **data plane** (forwarding).

- The **controller** installs flow table entries in the network devices.
- The **devices** only forward packets according to the installed rules.

Importance

Generalized forwarding and SDN provide:

1. **Flexibility** – The same hardware can act as a router, firewall, or load balancer depending on rules.
2. **Programmability** – Network operators can dynamically adjust traffic using software.
3. **Centralized control** – Policies can be applied across the whole network from a controller.

4. **Scalability** – Easier management of large data centers and enterprise networks.

12. Middleboxes

Definition:

A middlebox is any **intermediary device on the network path** that does more than a normal IP router. It performs extra functions between a source and destination.

Departure from Pure IP Model:

- The original Internet design had **all intelligence at the endpoints**.
- Middleboxes **break this principle** by adding intelligence inside the network.

Types and Functions of Middleboxes

1. **Network Address Translation (NAT)**: Translates private IP addresses to public ones.
2. **Firewalls**: Controls access and blocks unwanted traffic.
3. **Intrusion Detection Systems (IDS)**: Monitors for security threats.
4. **Load Balancers**: Distributes traffic across multiple servers.
5. **Caches**: Stores content to improve performance.
6. **Application-specific devices**: E.g., deep packet inspection, content filtering.

Where They Are Deployed:

- **Home networks**: NAT routers, firewalls.
- **Enterprise networks**: Firewalls, IDS, load balancers.
- **Service providers & data centers**: Caches, firewalls, load balancers.
- **Mobile networks**: NAT, firewalls, performance enhancers.

-----Example-----

1.

a) What is an IP address? Why do we need IPv6 over IPv4?

b) Suppose a block of addresses is granted to a small organization and one of the addresses is 205.16.37.39/28.

i) What is the first address in the block?

ii) What is the first usable address in the block?

- iii) What is the last usable address in the block?
- iv) What is the broadcast address in the block?
- v) Find the number of addresses in the block.

a) IP Address and the Need for IPv6

An IP address is a unique identifier for devices on a network, enabling communication via the Internet Protocol. It serves two main purposes:

1. **Device Identification:** Uniquely identifies a device (host) on a network.
2. **Location Addressing:** Helps route data to the correct device across networks.

Why IPv6 over IPv4:

IPv4 uses 32-bit addresses (about 4.3 billion), which are insufficient due to the growth of internet-connected devices. IPv6, with 128-bit addresses, provides a vastly larger address space (around 340 undecillion), supports better security, and eliminates the need for NAT, making it essential for future scalability.

- **IPv4 limitation:** Uses 32-bit addresses → ~4.3 billion addresses, insufficient for global devices.
- **IPv6 advantage:** Uses 128-bit addresses → practically unlimited addresses ($\sim 3.4 \times 10^{38}$).
- Other benefits of IPv6:
 - Simplified header for faster routing.
 - Built-in security features (IPSec).
 - Better support for mobile and IoT devices.

Summary: IPv6 is needed to overcome IPv4 address exhaustion and improve security, efficiency, and scalability.

Question (b): Given: 205.16.37.39/28

Step 1: Understand the subnet

- /28 means **28 bits are fixed for network** and **32 – 28 = 4 bits for host**.
- Number of addresses = $2^4 = 16$.
- Each block (subnet) will have 16 addresses in the last octet.
- The subnets in the **last octet** are:

0–15, 16–31, 32–47, 48–63, ...

- The given IP 205.16.37.39 falls inside the **32–47 range**.

- So the block is: **205.16.37.32 – 205.16.37.47**

Answers

i) First address in the block (Subnet ID):

- The **first address** of the block is the **network ID**.
- Here: **205.16.37.32**

ii) First usable address:

- Usable addresses start after the subnet ID.
- So: **205.16.37.32 + 1 = 205.16.37.33**

iii) Last usable address:

- Usable addresses end just before the broadcast address.
- Broadcast is at the last address of the block → **205.16.37.47**
- So last usable = **205.16.37.46**

iv) Broadcast address:

- Broadcast = last address in the subnet block.
- Here: **205.16.37.47**

v) Number of addresses in the block:

- Total = $2^{\text{host bits}} = 2^4 = 16$ addresses.
- Out of these:
 - 1 = Network ID
 - 1 = Broadcast
 - Remaining **14 are usable host addresses**

2.

a) Explain Classful and Classless IP addresses with their pros and cons.

b) Break up 192.168.1.64/28 to support as many subnets as possible with 8 hosts per subnet. Also, show the network address, subnet mask, first usable address, last usable address, broadcast address, and how many addresses are supported in each block.

a)

Classful IP Addressing

Classful addressing assigns IP addresses based on the first few bits, which determine its class and the fixed network and host portion sizes. For example, a Class A network has a fixed 8-bit network part and a 24-bit host part.

- **Pros:**
 - **Simplicity:** It was easy to implement and understand as the network and host boundaries were predefined. You didn't need a separate subnet mask.
- **Cons:**
 - **Lack of flexibility:** You couldn't create custom-sized subnets, which was a major limitation.

Classless IP Addressing (CIDR)

Classless addressing, or CIDR, uses a **variable-length subnet mask (VLSM)**, allowing network administrators to divide the IP address space more efficiently. The network and host portions are defined by a prefix length, denoted by a slash (e.g., 192.168.1.0/24).

- **Pros:**
 - **Improved scalability:** It supports flexible subnetting and supernetting, which helps reduce the size of routing tables and improves routing efficiency on the internet.
- **Cons:**
 - **Complexity:** It's more complex than classful addressing and requires a deeper understanding of subnetting and binary math.

b) Break up 192.168.1.64/28 to support as many subnets as possible with 8 hosts per subnet + show details

Given Network:

- **Network Address:** 192.168.1.64
- **Subnet Mask:** /28 (255.255.255.240)
- **Total Addresses:** 16
- **Usable Host Addresses:** 14

Requirement: Break up the network to support **as many subnets as possible** with **at least 8 hosts per subnet**.

Analysis:

- To support at least 8 hosts per subnet, each subnet must have **at least 10 addresses** (8 usable hosts + network + broadcast).
- The smallest power-of-2 block that can hold 10 addresses is **16** (i.e., a /28 subnet).
- The given network is already a /28 (16 addresses), so **it cannot be subdivided** into smaller subnets that each meet the 8-host requirement.

- Therefore, the entire /28 block must be used as **one subnet**.

Subnet Details:

Field	Value
Network Address	192.168.1.64
Subnet Mask	255.255.255.240 (/28)
First Usable Address	192.168.1.65
Last Usable Address	192.168.1.78
Broadcast Address	192.168.1.79
Total Addresses in Block	16
Usable Host Addresses	14

Conclusion:

- Only **1 subnet** can be created from 192.168.1.64/28 that supports at least 8 hosts.
- This subnet provides **14 usable host addresses**, which exceeds the requirement.