

State Farm B2B - Author Guide

Date: July 31, 2026

Table of Contents

State Farm B2B - Author Guide 3

 Quick Reference 3

 Getting Started 3

 Content Organization 4

 Block Library 4

 Available Blocks 5

 Page Templates 6

 Configuration Sheets 6

 Publishing Workflow 6

 Common Tasks 7

 Sections and Section Metadata 7

 Page Metadata 7

 Images and Media 8

 Troubleshooting 8

 Resources 8

 Support Contacts 9

State Farm B2B - Author Guide

This guide is for content authors and content managers working on the State Farm B2B portal, an Adobe Experience Manager Edge Delivery Services project backed by Document Authoring (DA).

Quick Reference

Resource	URL
Document Authoring	https://da.live/#/adobedrago/statefarm-b2b-eds/
Preview	https://main-statefarm-b2b-eds-adobedrago.aem.page/
Live	https://main-statefarm-b2b-eds-adobedrago.aem.live/
Block Library	https://da.live/#/adobedrago/statefarm-b2b-eds/.da/library
Bulk Operations	https://da.live/apps/bulk

Site

Site	Content Source (DA)	Preview	Live
statefarm-b2b-eds	<code>content.da.live/adobedrago/statefarm-b2b-eds</code>	https://main-statefarm-b2b-eds-adobedrago.aem.page/	https://main-statefarm-b2b-eds-adobedrago.aem.live/

This is a single-site (standard) setup — one GitHub code repository (`adobedrago/statefarm-b2b-eds`) paired with one DA content source.

Getting Started

Access Requirements

- ☐ DA access (request from a project admin — current admins: gallardo@adobe.com, mdean@adobe.com)
- ☐ Preview/publish permissions

Your First Page

- Go to Document Authoring: <https://da.live/#/adobedrago/statefarm-b2b-eds/>
- Navigate to the correct folder (content mirrors the site's URL structure, e.g. `/claim-services/`, `/electronic-payments`)
- Create a new document
- Add content using default rich text (headings, paragraphs, lists, links, images) and insert blocks from the Library sidebar where needed
- Add a Metadata block at the bottom of the page
- Preview the page, review it, then Publish

Content Organization

Site Structure

Pages are authored as folders/documents in DA and map directly to the site's URL paths. Existing top-level content areas include:

Path	Purpose
/acct-mgmt	Account management content
/claim-services	Claims service information
/electronic-payments	Electronic payments information
/home-auto-lenders	Home/auto lenders content
/medical-ebilling	Medical e-billing information
/select-service	Service selection content
/suppliers	Supplier information
/contact-us	Contact page
/other-ins-carrier	Other insurance carrier information
/terms-of-use	Terms of use

Global navigation and footer are authored as separate documents and pulled onto every page automatically:

- **Navigation:** /nav (or /content/nav) — edit this document to change the header megamenu, search, and login link
- **Footer:** /footer (or /content/footer) — edit this document to change the footer banner, link lists, and copyright

Both the header and footer blocks also support a page-level metadata override (nav / footer properties in the Metadata block) if a specific page needs to point at a different nav or footer document.

Languages

This project is currently English-only. No language folders (/en, /fr, etc.) are present in the codebase.

Block Library

The **Block Library** is the sidebar in Document Authoring where you browse and insert blocks and templates into your document.

What	Details
Open in DA	Use the Library icon in the DA editor sidebar, or go directly to: https://da.live/#/adobedrago/statefarm-b2b-eds/.da/library
What's in it	All blocks listed in "Available Blocks" below appear in the library
How to use	Click a block in the library to insert it at the cursor position in your document

When creating or editing a page, use the Library sidebar to add blocks instead of typing block names manually.

Available Blocks

Block	Purpose	Variants	Usage
Hero	Full-bleed banner with a background image and large heading, used at the top of a page	—	Use once, near the top of a page, to introduce the page topic with a strong visual
Columns	General-purpose two-column layout (image + text)	quarter — image takes 25% width instead of an even 50/50 split	Use for standard image/text pairings; use quarter when the image should read as a small supporting visual next to a larger block of text
Columns Auth	Portal landing header combining an image, heading, intro copy, a “Log In” call-to-action, and a “No login required” quick-links row	Automatically adopts a 2-column or 3-column layout depending on how many columns are authored; the 3-column form is used when the image is a small fixed-size icon rather than a wide photo	Use for authentication/login-oriented landing sections (e.g. the portal home page)
Columns Promo	Centered, boxed promotional panel with a heading, sub-heading, and a product/service selector dropdown	—	Use for a single, contained call-to-action panel offering a dropdown of related products or services
Cards	Responsive grid of image + text cards (1 column on mobile, 2 per row on larger screens)	Supports an optional small “login required” lock icon overlaid on a card’s title	Use for general content card grids, including cards that need to flag login-gated content
Cards Service	Grid of fixed-width (350px) service/category cards, each with a pictogram icon, heading, description, and an optional dropdown of quick-navigation links	—	Use for portal navigation grids (e.g. “Claim Services,” “Electronic Payments”) where each card represents a service category with related quick links
Icon Text	Rows pairing an icon with a heading and supporting text/links	small — uses a fixed 56px icon instead of the default responsive pictogram size (64px mobile / 120px desktop)	Use for feature lists or contact-method lists with an icon per row; use small for a simpler, consistently-sized icon (e.g. a generic contact icon)
Breadcrumbs	Horizontal trail of links showing the page’s position in the site hierarchy, with the current page shown as plain (non-linked) text	—	Place at the top of a page, authored as a simple linked list, to show users their navigation path
Fragment	Pulls in the content of another authored page/fragment	—	Use to reuse a block of content (e.g. a shared disclaimer or promo)

Block	Purpose	Variants	Usage
	ment document and renders it inline		across multiple pages without duplicating it. A plain link to a / fragments/... path is auto-detected and doesn't require the block explicitly
Widget	Loads a self-contained HTML/CSS/JS widget from the / widgets/ folder and mounts it in the page	—	Use only for pre-built interactive widgets provided by developers; authored as a link to the widget's .html file under /widgets/
Header (site-wide)	Site navigation bar: logo, utility links (Search/Help/Contact/FAQ), megamenu sections, search, and login link	—	Not inserted per-page — edit the /nav document to change its content
Footer (site-wide)	Site footer: red slogan banner, link lists, privacy notices, and copyright	—	Not inserted per-page — edit the /footer document to change its content

Page Templates

No dedicated page templates (template: metadata values with distinct layouts) are currently defined for this project. Pages are built from sections and the blocks listed above.

Configuration Sheets

Sheet	Location	Purpose	When to Update
Placeholders	/placeholders	Reusable text strings, translations	Changing labels or button text used sitewide
Redirects	/redirects	Forward old URLs to new URLs	After deleting or moving pages
Bulk Metadata	/metadata	Apply metadata to multiple pages	Setting metadata defaults by folder/URL pattern

None of these sheets currently exist in the project; create them in DA only if/when the need arises (e.g. before deleting or renaming a page, always add a redirect first).

Publishing Workflow

Environment	Domain	Purpose
Preview	.aem.page	Test changes before going live
Live	.aem.live	Production site

Workflow: Edit in DA → Preview → Publish → Live immediately

Bulk: <https://da.live/apps/bulk>

Common Tasks

Task	Steps
Create a Page	Navigate to folder → New → Document → Add content → Add Metadata → Preview → Publish
Edit a Page	Open in DA → Make changes → Preview → Publish
Delete a Page	Add a redirect first → Delete document → Publish redirects
Update Navigation	Edit / nav document → Preview → Publish
Update Footer	Edit / footer document → Preview → Publish
Reuse Content Across Pages	Author the shared content as a fragment document, then link to it (e.g. under / fragments / . . .) from any page

Sections and Section Metadata

Sections group content together. Create sections with horizontal rules (---).

Add styles with a Section Metadata block at the end of a section:

Section Metadata	
style	[style-name]

Available Section Styles:

Style	Effect
light	Light background treatment for the section
highlight	Highlighted/emphasized background treatment for the section
khaki	Khaki/tan background panel, with adjusted list spacing inside it
khaki spacious	Same khaki panel with additional internal spacing (apply both khaki and spacious)
accent-heading	Colors the first heading in the section with the brand red accent color

Page Metadata

Property	Required	Purpose	Example
title	Yes	Page title for SEO and browser tab	“Claim Services”

Property	Required	Purpose	Example
description	Yes	SEO description	“Learn about filing and managing claims...”
image	No	Social sharing image	/images/og.jpg
nav	No	Override which document is used for the site header	/content/nav
footer	No	Override which document is used for the site footer	/content/footer

Images and Media

Method	How
Drag & drop	Drag images directly into the DA editor
AEM Assets	Use the Assets sidebar in DA

Best Practices: Use descriptive filenames, always add alt text, images are automatically optimized by the platform.

Troubleshooting

Issue	Solution
Page not updating after publish	Wait 1-2 minutes for cache, then hard refresh (Cmd+Shift+R)
Block not displaying correctly	Check the block's content structure matches what's expected, verify variant name spelling (e.g. quarter, small)
Images not showing	Verify the image uploaded successfully in DA, check the path is correct
Nav or footer not updating	Confirm you edited /nav or /footer (or the page's metadata override), then preview and publish that document

Resources

Resource	URL
DA Documentation	https://docs.da.live/
Authoring Guide	https://www.aem.live/docs/authoring
Placeholders Docs	https://www.aem.live/docs/placeholders
Redirects Docs	https://www.aem.live/docs/redirects

Support Contacts

For access requests or admin support, contact a project administrator: gallardo@adobe.com or mdean@adobe.com.