

Integer Factorization as an Ising problem

Advith Desu

IIT Madras

May 6, 2026

Factorization Problem

- ▶ Given a natural number N , find P, Q such that

$$N = PQ$$

- ▶ Hard inverse problem underlying RSA security.
- ▶ Map factorization $\rightarrow$ QUBO problem.
- ▶ Solve using annealing-based algorithms.

Binary Representation and Assumptions

Assumptions:

- ▶ N is odd.
- ▶ Factors have equal bit-length

$$n = \left\lceil \frac{1}{2} \log_2 N \right\rceil.$$

Binary form:

$$P = \sum_{k=0}^{n-1} 2^k p_k, \quad Q = \sum_{k=0}^{n-1} 2^k q_k, \quad p_k, q_k \in \{0, 1\}.$$

Fixed bits:

$$p_0 = q_0 = 1, \quad p_{n-1} = q_{n-1} = 1.$$

Column-wise Multiplication

- ▶ Construct binary long multiplication table.
- ▶ Introduce carry variables $s_{i,j}$.
- ▶ Each column gives a constraint:

$$C_i = N_i - \sum_j q_j p_{i-j} - \sum s_{j,i} + \sum 2^j s_{i,j}.$$

- ▶ Correct factors satisfy $C_i = 0$.

Worked Example: $N = 391 = 17 \times 23$

Setup:

- ▶ $391 = 110000111_2$
- ▶ Fixed bits: $p_0 = q_0 = 1$ (odd), $p_4 = q_4 = 1$ (MSB)
- ▶ Free bits: p_1, p_2, p_3 and q_1, q_2, q_3 — 6 unknowns

Long multiplication table (cross-product $p_a q_b$ sits in column $a + b$):

	2^8	2^7	2^6	2^5	2^4	2^3	2^2	2^1	2^0
P					1	p_3	p_2	p_1	1
Q					1	q_3	q_2	q_1	1
				q_1 $p_3 q_2$ $p_2 q_3$ $p_1 q_3$ 1	$p_3 q_1$ $p_2 q_2$ $p_1 q_3$ 1	p_3 $p_2 q_1$ $p_1 q_2$ q_3	p_2 $p_1 q_1$ q_2	p_1 q_1	1
	1	q_3 p_3	q_2 $p_3 q_3$ p_2	$p_2 q_3$ p_1	1				
Carry-outs		$s_{6,7}, s_{6,8}$	$s_{5,6}, s_{5,7}$	$s_{4,5}, s_{4,6}$	$s_{3,4}, s_{3,5}$	$s_{2,3}, s_{2,4}$	$s_{1,2}$		
$N = 391$	1	1	0	0	0	0	1	1	1

Carry $s_{i,j}$ = bit of column i 's carry destined for column j (coefficient 2^{j-i}).

Optimization objective:

$$\min_{\{p_i, q_i, s_{ij}\}} \sum_i (C_i)^2.$$

- ▶ Binary variables: factor bits + carry bits.
- ▶ Ground state corresponds to valid factorization.
- ▶ Alternative direct method:

$$\left(N - \sum p_i 2^i \sum q_j 2^j\right)^2$$

but gives fewer preprocessing opportunities.

Rule 1: Saturated Sum

For binary $x_i \in \{0, 1\}$:

$$\sum_{i=1}^n x_i = n \implies x_i = 1 \forall i.$$

Why: the only way n binary variables sum to n is for every one of them to be 1.

A symmetric form with negative coefficients:

$$\sum_{i=1}^n -x_i = -n \implies x_i = 1 \forall i.$$

Rule 2: Zero Sum

For binary $x_i \in \{0, 1\}$:

$$\sum_{i=1}^n x_i = 0 \implies x_i = 0 \forall i.$$

Why: a sum of non-negative binaries equals 0 only when every term is 0.

The same conclusion holds with negative coefficients:

$$\sum_{i=1}^n -x_i = 0 \implies x_i = 0 \forall i.$$

Rule 3: Doubling Rule

For binary variables $x_1, x_2, x_3 \in \{0, 1\}$:

$$x_1 + x_2 = 2x_3 \implies x_1 = x_2 = x_3.$$

Why: $\text{LHS} \in \{0, 1, 2\}$ and $\text{RHS} \in \{0, 2\}$. Equality forces LHS even, so $x_1 + x_2 \in \{0, 2\}$ — both equal, and equal to x_3 .

Use in factorization: appears whenever a column clause has only two factor-bit terms balanced against a single carry, e.g.

$$p_k + q_k = 2s \Rightarrow p_k = q_k = s.$$

Rule 4: Coefficient Bound Rule

General linear constraint on $x_i \in \{0, 1\}$:

$$\sum_i c_i x_i + C = 0, \quad S_+ = \sum_{c_i > 0} c_i, \quad S_- = \sum_{c_j < 0} |c_j|.$$

If a single coefficient is larger than the max possible opposing sum, the variable is *forced*:

Positive coefficients ($c_i > 0$):

$$c_i > S_- - C \Rightarrow x_i = 0, \quad c_i > S_+ + C \Rightarrow x_i = 1.$$

Negative coefficients ($c_j < 0$, $|c_j|$ magnitude):

$$|c_j| > S_+ + C \Rightarrow x_j = 0, \quad |c_j| > S_- - C \Rightarrow x_j = 1.$$

Example: $x_1 + x_2 = 2x_3 + 1$. Coefficient of x_3 is 2, max LHS is 2, so x_3 cannot be 1 $\Rightarrow x_3 = 0$.

Rule 5: Complement Rule

For binary $x_1, x_2 \in \{0, 1\}$:

$$x_1 + x_2 = 1 \implies x_2 = 1 - x_1, \quad x_1 x_2 = 0.$$

Why: the only solutions are $(0, 1)$ and $(1, 0)$ — exactly one variable is 1, so their product is always 0.

Use in factorization: eliminates one variable outright (substitute $x_2 \rightarrow 1 - x_1$) and kills any quadratic term $x_1 x_2$ that appears in a column clause.

Rule 6: Complementary Pair Rule

For a constraint $\sum_i c_i x_i + C = 0$ with S_+, S_- as before:

Two positive coefficients $c_i, c_j > 0$:

$$c_i + c_j > S_- - C \quad \text{and} \quad c_i + c_j > S_+ + C$$

$$\implies x_j = 1 - x_i.$$

Two negative coefficients $c_i, c_j < 0$ (let $\bar{c} = |c|$):

$$\bar{c}_i + \bar{c}_j > S_+ + C \quad \text{and} \quad \bar{c}_i + \bar{c}_j > S_- - C$$

$$\implies x_j = 1 - x_i.$$

Why: the first inequality forbids both variables from being 1 simultaneously; the second forbids both from being 0. The only remaining option is one of each.

Parity Rule

Both sides of a clause must have the same parity:

$$x_1 + x_2 + \text{even} = \text{even} \Rightarrow x_1 = x_2,$$

$$x_1 + x_2 + \text{even} = \text{odd} \Rightarrow x_1 + x_2 = 1.$$

Example:

$$x_1 + x_2 + 2x_3 = 2y_1 + 4y_2 \Rightarrow x_1 = x_2,$$

$$x_1 + x_2 + 2x_3 = 2y_1 + 4y_2 + 1 \Rightarrow x_1 + x_2 = 1.$$

Why it matters: column clauses balance a small sum of factor bits against carries with even coefficients ($2s_{i,i+1}, 4s_{i,i+2}, \dots$). The parity of the factor-bit sum is therefore locked by N_i .

Power Rule

For any binary variable $x \in \{0, 1\}$:

$$x^m = x, \quad m = 2, 3, \dots$$

Why: $0^m = 0$ and $1^m = 1$ for all positive integers m .

Use in factorization: after squaring the energy function $E = \sum_i C_i^2$, every p_k^2 , q_k^2 , s^2 collapses back to its linear form p_k , q_k , s . This is what makes the squared objective expressible as a (degree-2) QUBO once cubics/quartics are quadrized.

Worked Example: $N = 391 = 17 \times 23$

Setup:

- ▶ $391 = 110000111_2$
- ▶ Fixed bits: $p_0 = q_0 = 1$ (odd), $p_4 = q_4 = 1$ (MSB)
- ▶ Free bits: p_1, p_2, p_3 and q_1, q_2, q_3 — 6 unknowns

Long multiplication table (cross-product $p_a q_b$ sits in column $a + b$):

	2^8	2^7	2^6	2^5	2^4	2^3	2^2	2^1	2^0
P					1	p_3	p_2	p_1	1
Q					1	q_3	q_2	q_1	1
				q_1 $p_3 q_2$ $p_2 q_3$ $p_1 q_3$ 1	$p_3 q_1$ $p_2 q_2$ $p_1 q_3$ 1	p_3 $p_2 q_1$ $p_1 q_2$ q_3	p_2 $p_1 q_1$ q_2	p_1 q_1	1
	1	q_3 p_3	q_2 $p_3 q_3$ p_2	q_1 $p_3 q_2$ $p_2 q_3$ p_1	$p_3 q_1$ $p_2 q_2$ $p_1 q_3$ 1	p_3 $p_2 q_1$ $p_1 q_2$ q_3	p_2 $p_1 q_1$ q_2	p_1 q_1	1
Carry-outs		$s_{6,7}, s_{6,8}$	$s_{5,6}, s_{5,7}$	$s_{4,5}, s_{4,6}$	$s_{3,4}, s_{3,5}$	$s_{2,3}, s_{2,4}$	$s_{1,2}$		
$N = 391$	1	1	0	0	0	0	1	1	1

Carry $s_{i,j}$ = bit of column i 's carry destined for column j (coefficient 2^{j-i}).

Column Clauses: $C_i = 0$

Each column i : (column sum) + (carries in) = $N_i + 2s_{i,i+1} + 4s_{i,i+2}$.

$$C_0 : 1 - 1 = 0 \quad \checkmark$$

$$C_1 : p_1 + q_1 - 1 - 2s_{1,2} = 0$$

$$C_2 : p_2 + q_2 + p_1q_1 + s_{1,2} - 1 - 2s_{2,3} - 4s_{2,4} = 0$$

$$C_3 : p_3 + q_3 + p_1q_2 + p_2q_1 + s_{2,3} - 2s_{3,4} - 4s_{3,5} = 0$$

$$C_4 : 2 + p_1q_3 + p_3q_1 + p_2q_2 + s_{2,4} + s_{3,4} - 2s_{4,5} - 4s_{4,6} = 0$$

$$C_5 : p_1 + q_1 + p_2q_3 + p_3q_2 + s_{3,5} + s_{4,5} - 2s_{5,6} - 4s_{5,7} = 0$$

$$C_6 : p_2 + q_2 + p_3q_3 + s_{4,6} + s_{5,6} - 2s_{6,7} - 4s_{6,8} = 0$$

$$C_7 : p_3 + q_3 + s_{5,7} + s_{6,7} - 1 - 2s_{7,8} = 0$$

$$C_8 : 1 + s_{6,8} + s_{7,8} - 1 = 0$$

Applying Reduction Rules

C_8 (**Rule 2, sum = 0**): $s_{6,8} + s_{7,8} = 0 \Rightarrow \boxed{s_{6,8} = s_{7,8} = 0}$.

C_2 (**Rule 4, large coefficient**): LHS terms $p_2 + q_2 + p_1 q_1 + s_{1,2} \leq 4$, but coefficient of $s_{2,4}$ is 4. If $s_{2,4}=1$, need LHS ≥ 5 . $\boxed{s_{2,4} = 0}$.

C_1 (**Rule 5**): $p_1 + q_1 = 1 + 2s_{1,2}$. Max sum = $2 < 3$, so $s_{1,2} = 0$:

$$\boxed{s_{1,2} = 0, \quad q_1 = 1 - p_1} \Rightarrow p_1 q_1 = p_1(1 - p_1) = 0$$

C_2 (**after substitutions**): $p_2 + q_2 = 1 + 2s_{2,3}$. Same logic as C_1 :

$$\boxed{s_{2,3} = 0, \quad q_2 = 1 - p_2}$$

C_7 (**Rule 2, sum = 1 exactly-one**):

$$p_3 + q_3 + s_{5,7} + s_{6,7} = 1 \quad (s_{7,8} = 0 \text{ already})$$

Exactly one of these four binaries equals 1.

Remaining Structure After Pre-processing

After the rules above, we have eliminated 5 variables ($s_{1,2}, s_{2,3}, s_{2,4}, s_{6,8}, s_{7,8}$) and reduced q_1, q_2 to functions of p_1, p_2 .

Free QUBO variables (13):

$\{p_1, p_2, p_3, q_3\} \cup \{s_{3,4}, s_{3,5}, s_{4,5}, s_{4,6}, s_{5,6}, s_{5,7}, s_{6,7}\}$ (plus 2 auxiliaries from quadrization)

Remaining clauses (after substituting $q_1=1-p_1, q_2=1-p_2$):

$$\begin{aligned} C_3 : p_3 + q_3 + p_1(1-p_2) + p_2(1-p_1) - 2s_{3,4} - 4s_{3,5} &= 0 \\ &= p_3 + q_3 + p_1 + p_2 - 2p_1p_2 - 2s_{3,4} - 4s_{3,5} = 0 \end{aligned}$$

$$\begin{aligned} C_4 : 2 + p_1q_3 + p_3(1-p_1) + p_2(1-p_2) + s_{3,4} - 2s_{4,5} - 4s_{4,6} &= 0 \\ &= 2 + p_1q_3 + p_3 - p_1p_3 + s_{3,4} - 2s_{4,5} - 4s_{4,6} = 0 \end{aligned}$$

$$C_5 : 1 + p_2q_3 + p_3(1-p_2) + s_{3,5} + s_{4,5} - 2s_{5,6} - 4s_{5,7} = 0$$

$$C_6 : 1 + p_3q_3 + s_{4,6} + s_{5,6} - 2s_{6,7} = 0$$

$$C_7 : p_3 + q_3 + s_{5,7} + s_{6,7} = 1$$

Cubic terms appear after squaring (e.g. $p_1p_2 \cdot s_{3,4}$ in C_3^2 , $p_1p_3 \cdot s_{4,5}$ in C_4^2) $\Rightarrow$ quadrization required.

Quadrization and QUBO Construction

Energy function: $E = \sum_{i=3}^7 C_i^2$. Squaring introduces cubics like $a \cdot p_i p_j s_{k,\ell}$.

Rosenberg substitution: replace each AB pair appearing in a cubic by an auxiliary w , with penalty

$$P(A, B, w) = M(AB - 2Aw - 2Bw + 3w), \quad M \gg \max |\text{coeff}|.$$

$P = 0$ iff $w = AB$. After substitution every cubic $AB \cdot s$ becomes $w \cdot s$ (quadratic).

Auxiliaries needed: $w_1 = p_1 p_2$, $w_2 = p_1 p_3$.

Full QUBO:

$$H = \sum_{i=3}^7 C_i^2 \Big|_{w_1 \rightarrow p_1 p_2, w_2 \rightarrow p_1 p_3} + M[P(p_1, p_2, w_1) + P(p_1, p_3, w_2)]$$

Active QUBO variables (13 total):

Original (4)	p_1, p_2, p_3, q_3
Carry (7)	$s_{3,4}, s_{3,5}, s_{4,5}, s_{4,6}, s_{5,6}, s_{5,7}, s_{6,7}$
Auxiliary (2)	$w_1 = p_1 p_2, w_2 = p_1 p_3$

QUBO Matrix Structure

QUBO form: $H = \sum_i h_i x_i + \sum_{i < j} Q_{ij} x_i x_j + \text{const.}$

Example: contribution of C_1^2 before C_1 was eliminated (illustrative pattern):

$$C_1^2 = (p_1 + q_1 - 1 - 2s_{1,2})^2 \xrightarrow{x^2=x} -p_1 - q_1 + 8s_{1,2} + 2p_1 q_1 - 4p_1 s_{1,2} - 4q_1 s_{1,2} + 1.$$

Sketch of nonzero entries of Q for $N = 391$ (qualitative):

	p_1	p_2	p_3	q_3	$s_{3,4}$	$s_{3,5}$	$s_{4,5}$	$s_{4,6}$	$s_{5,6}$	$s_{5,7}$	$s_{6,7}$	w_1	w_2
p_1	•	•	•	•								•	•
p_2		•	•	•	•	•						•	
p_3			•	•	•		•	•					•
q_3				•			•	•	•	•	•		
$s_{3,4}$					•	•	•	•					
$s_{3,5}$						•	•		•	•			
$s_{4,5}$							•	•	•	•			
$s_{4,6}$								•	•		•		
$s_{5,6}$									•	•	•		
$s_{5,7}$										•	•		
$s_{6,7}$											•		
w_1												•	
w_2													•

Ground state at $(p_1, p_2, p_3, q_3) = (0, 0, 0, 0)$ recovers $P=17$, $Q=23$ with $E=0$.

J matrix Visualization I




Figure: Sparsity of J matrix for 162 BQM (Integer 39203).

Sparse Coupling Matrix Representation (CSR)

Problem: The Ising coupling matrix J_{ij} is very large but mostly zero. Storing it as a dense $N \times N$ matrix wastes memory and bandwidth.

Key idea: Store *only the nonzero couplings* using **Compressed Sparse Row (CSR)** format. CSR represents a sparse matrix using three arrays:

`row_ptr[i]` start index of row i

`col_idx[k]` column index of nonzero entry

`values[k]` value of J_{ij}

Only nonzero entries are stored.

Memory cost: $\mathcal{O}(N + \text{nnz})$ instead of $\mathcal{O}(N^2)$

GPU Kernel




Figure: GPU Threads and Thread blocks.

GPU Thread Calculation in DA1

Each thread i calculates the local field $L_i = \sum_j J_{ij}s_j + h_i$ and the energy difference is then calculated as $-2 \times s_i \times L_i$ depending on which i^{th} spin flipped.




Figure: Energy calculation in DA1.

Graph-Coloring Simulated Annealing

In one Metropolis sweep we want to flip many spins in parallel, but two spins coupled by a non-zero J_{ij} share an edge and cannot be flipped simultaneously without invalidating each other's ΔE .

We use graph coloring on the interaction graph (nodes = spins, edges = nonzero J_{ij}) partitions spins into colors such that *no two same-color spins are coupled*. All spins in one color can then be flipped in parallel without affecting each other's energy calculations.

Two performance bins based on row degree $d_i = |\{j : J_{ij} \neq 0\}|$:

- ▶ **Dense** ($d_i \geq 128$): full block of 1024 threads, shared-memory reduction.
- ▶ **Sparse** ($d_i < 128$): one warp (32 threads) per spin, 32 spins packed per block, warp-shuffle reduction.

One-time Setup (Host)

Algorithm Pre-processing on host before annealing

Require: CSR of symmetric J , linear field h , num_spins N

- 1: Verify J symmetry and a zero diagonal
 - 2: Bin each spin: **dense** if $d_i \geq 128$, else **sparse**
 - 3: $\text{color}[] \leftarrow$ Welsh–Powell greedy coloring (largest-degree-first, first-fit)
 - 4: Build sparse-only CSR with hub-tagged col_idx (high bit $\Rightarrow$ index into hub cache)
 - 5: Bucket spins by color: $\text{color_dense_offsets}$, $\text{color_sparse_offsets}$
 - 6: Upload all CSR + color tables + hub arrays to GPU
 - 7: Initialize a random spin configuration and compute initial energy
 - 8: Calculate the start-temperature: $T_0 = \langle \Delta E^+ \rangle / \ln(1/\chi)$
-

Annealing Loop (GPU)

Algorithm Color-parallel simulated annealing

Require: β -schedule $\{\beta_t\}$ (geometric), sweeps per β , N_{colors}

```
1: for  $\beta$  in  $\beta$ -schedule do
2:   for sweep = 1 ...  $m$  do
3:     Generate fresh uniform randoms for all  $N$  spins
4:     for  $c = 0 \dots N_{\text{colors}} - 1$  do                                ▷ colors run sequentially
5:       collectFlipCandidates(dense) on color  $c$ 
6:       collectFlipCandidates(sparse) on color  $c$ 
7:       each spin  $i$  in color  $c$  in parallel:
8:          $L_i \leftarrow \sum_j J_{ij}s_j + h_i$ ,  $\Delta E_i \leftarrow -2s_i L_i$ 
9:         if  $\text{rand}_i < \min(1, e^{-\beta \Delta E_i})$ : append  $(i, \Delta E_i)$  to candidates
10:      applyAllFlipsInColor: flip every accepted spin, atomicAdd  $\Delta E_i$ 
        to total energy
11:      if any hub spin in color  $c$ : refresh hub-values cache
12:    end for
13:  end for
14:  if total energy < best energy then snapshot best spins
15:  end if
16: end for
17: return best-energy spin configuration
```

Number of Densely connected spins with scale






Figure: BQM variables vs number of densely connected spins.


Annealing Time per Iteration vs Number of Spins




Construction time for CSR J



Execution Time Comparison




Solution Quality Measured by Gap between Real and Estimated P



1. Average (%) difference with square root N as the estimate = **10.33%**
2. Average (%) difference with P_{pred} from Simulated Annealing = **4.23%**
3. Average (%) difference with mean of P_{pred} and N/Q_{pred} = **2.98%**

Time Taken to Find Exact primes by Brute Force



$$\text{Time Taken (s)} = \frac{3.32 \times 10^{-9}}{\text{Threads}} \times \text{Gap (\%)} \times 2^n$$