





DIADEM User Manual

Version 5.0 (SATURN)

February 2011 (Reissued September 2012)

Department for Transport





DIADEM User Manual

Version 5.0 (SATURN)

February 2011 (Reissued September 2012)

Department for Transport

From Thursday 13th September 2012, the responsibility for the maintenance, support, and sale of DIADEM on behalf of the Department for Transport has transferred from Mott MacDonald to Atkins Limited. For all enquires, please contact Atkins via email on DIADEM@atkinsglobal.com in the first instance or by telephone on +44 (0)1372 756272



Issue and revision record

Revision A	Date March 2010	Originator A Gordon	Checker S Sirivadidurage	Approver C White	Description First issue (version 4.1 manual)
В	May 2010	A Gordon	S Sirivadidurage	C White	Second issue
С	August 2010	A Gordon	S Sirivadidurage	C White	Third issue
D	October 2010	A Gordon	S Sirivadidurage	C White	Fourth issue
E	January 2011	A Gordon	C White	C White	Fifth issue (version 5.0 manual)
F	February 2011	A Gordon	S Sirivadidurage	C White	Sixth issue

This document is issued for the party which commissioned it and for specific purposes connected with the above-captioned project only. It should not be relied upon by any other party or used for any other purpose.

We accept no responsibility for the consequences of this document being relied upon by any other party, or being used for any other purpose, or containing any error or omission which is due to an error or omission in data supplied to us by other parties

This document contains confidential information and proprietary intellectual property. It should not be shown to other parties without consent from us and from the party which commissioned it.



Content

Chapter	litle	Page
1.	Introduction	1
2.	Installation	2
3.	Overview of DIADEM	3
3.1	Purpose of DIADEM	3
3.2	Types of demand model	
3.3	Help and support	4
4.	Background information	6
4.1	Logit models	6
4.2	HADES	
4.3	Generalised costs and cost damping	24
4.4	OD and PA	28
4.5	Public transport in DIADEM	
4.6	Segmentation in DIADEM	32
5.	Preparation for a DIADEM run	34
5.1	Overview	34
5.2	Incremental model	35
5.3	Absolute model	36
6.	Entering DIADEM data	41
6.1	Overview	41
6.2	The DIADEM Control file	
6.3	General information	42
6.4	Page 1: forecast network files(s) and segmentation	43
6.5	Page 2: Model Parameters	46
6.6	Page 3: Highway Trip/Cost Data	53
6.7	Page 4: PT Trip/Cost data	59
6.8	Page 5: PA Model Data	61
6.9	Page 6: Absolute Model Data	
6.10	Page 7: DIADEM Parameters	
6.11	Page 8: HADES Data	
6.12	Page 9: SATURN Settings	
6.13	Running DIADEM	74
7.	DIADEM output	75
7.1	Output files	75
7.2	Dealing with error and warning messages	78
8.	Hints and tips	81
8.1	Realism testing with DIADEM	81
8.2	Reducing run times	
8.3	Improving convergence	

DIADEM User Manual Version 5.0



8.4	Freezing particular movements	85
9.	References	86
Appen	dices	87
Appendix	x A. Description of algorithms	88
A.1.	Definitions and notation	88
A.2.	Algorithm 1/MSA/FSL	
Appendix	x B. Demand model functions	90
B.1.	Logit model	90
B.2.	The hierarchical model	92
B.3.	A general note on the demand models	
B.4.	Example implementation of incremental logit model	93
Appendix	x C. Initial tour proportions from NTS data	97
Appendix	x D. History of DIADEM changes	99
D.1.	Changes between 4.1 and 5.0	99
D.2.	Changes between 3.1 and 4.1	99
D.3.	Changes between 3.0 and 3.1	99
D 4	Changes between 2.1 and 3.0	90



1. Introduction

This document provides guidance on how to run version 5.0 of DIADEM (Dynamic Integrated Assignment and DEmand Modelling). It should be read in conjunction with the Department for Transport's latest WebTAG guidance on variable demand modelling which provides information on appropriate demand modelling structures and associated parameters (http://www.dft.gov.uk/webtag).

DIADEM fulfils two main roles:

- It provides a relatively simple way to link highway assignment models to a variable demand model. Currently links to CONTRAM and SATURN assignment models are supported, though links to other packages may be possible.
- It provides a means of achieving convergence between assignment (supply) and demand models.

DIADEM is intended to extend existing highway assignment models to variable demand modelling as easily as possible. It may not be appropriate for every possible demand modelling situation. In some cases more complex demand modelling software will be required; for example DIADEM does not include an explicit representation of walking and cycling modes.

There are separate versions of the manual for SATURN and CONTRAM users. The manual version is shown in the header of each page of the manual.

The DIADEM website (http://www.dft.gov.uk/diadem) provides information on DIADEM and access to the latest versions of the software and manuals.



2. Installation

You must have administrator rights on your pc to install DIADEM. If you receive the software on CD the installation process should start automatically on inserting the CD into the drive. If this does not happen, or you have received the software through a different medium you will need to run the program called setup.exe. To complete the installation you will need to accept the terms of the licence agreement. The following files will be installed to the DIADEM program files directory:

- DIADEM software
- DIADEM help file
- Licence agreement (licence.txt)
- CONTRAM and SATURN versions of the manual

DIADEM works with SATURN version 10.8.21 and later and CONTRAM8.

The system requirements are:

- Windows XP or Vista
- Minimum 1024x768 screen resolution

We are not aware of any problems using DIADEM with Windows 7, though this has not yet been fully tested.

The amount of memory (RAM) and disk space required depend on the size of the network being used with DIADEM and the level of segmentation.

Typically, the most significant performance improvements are obtained by ensuring that enough RAM is available for DIADEM not to need to use virtual memory. 256MB is the recommended minimum but 1GB or more may be required for large models. If there is insufficient RAM DIADEM will use virtual memory instead but this will significantly increase run times.

7MB of disk space is required for the DIADEM software itself. In addition sufficient space must be available to store DIADEM outputs, as follows:

- For CONTRAM DIADEM creates one trip matrix per iteration.
- For SATURN DIADEM creates one matrix per iteration for each of trips, time, distance and generalised cost for each time period and user class.

The actual amount of disk space required may vary from a few megabytes to several hundred megabytes depending on the size of the model network and matrix files.

If SATURN is being used as the assignment model DIADEM can reduce run times by carrying out assignments in parallel, provided suitable hardware is available (minimum dual core processor).

Software updates are made available via the website http://www.dft.gov.uk/diadem. Downloading the software requires a user name and password which are provided to licence holders when they purchase the software.



Overview of DIADEM

3.1 Purpose of DIADEM

DIADEM aims to provide a user-friendly method for setting up a multi-stage transport demand model and then finding equilibrium between demand and supply, using an external assignment package as the supply model. The process iterates between demand calculations and assignments, meaning that several assignments are needed in a single DIADEM run. As with all such iterative processes, equilibrium is not found exactly but convergence criteria are used to determine when the solution is close enough to equilibrium. More details of the algorithms used in this process can be found in Appendix A.

DIADEM does not include an assignment module; instead it relies on other software packages to carry out assignments. Currently DIADEM can formally be linked to CONTRAM and SATURN highway assignment models, although a DIADEM user has developed a link to VISUM and links to other packages may be possible (contact DIADEM support for advice). Any public transport (PT) assignment package can be used, provided it can produce trip and cost data in the required format.

The software structure is illustrated in Figure 1. The PT and highway assignment models are external to DIADEM. Outputs are produced in comma-separated variable (CSV) or plain text format to allow further analysis.




Figure 3.1: DIADEM software structure



3.2 Types of demand model

The main form of demand model available in DIADEM is the incremental hierarchical logit model, as recommended in WebTAG. This can be used to model trip distribution, mode choice and time period choice and can also be linked to an incremental trip frequency model.

The incremental model works by adjusting an input reference demand matrix according to changes between forecast travel costs and input reference travel costs.

An absolute version of the hierarchical logit model is also available.

A more detailed discussion of the logit model and its application in DIADEM can be found in Section 4.1.

A simple elasticity model using the Tanner function is available. Power and exponential elasticity functions are special cases of the Tanner function. It should be noted that WebTAG currently states that 'Pending further research it is recommended that simple elasticity models are not used to model the full effects of variable demand', although consultation guidance on proportionate appraisal proposes allowing their use on schemes with capital costs less than £20m (October 2009 consultation version of Unit 3.10.1). If you are using SATURN then it is usually more efficient to implement elasticity models using the options available within SATURN, rather than using DIADEM. The functional form of the elasticity model is given in Appendix B.

DIADEM 5.0 includes the HADES model of arrival time choice. This part of DIADEM currently has beta test status. It is described in more detail in Section 4.2.

For further discussion of these models and how to decide which is appropriate for your application please see WebTAG <u>Unit 3.10.3</u> (Variable Demand Modelling - Key Processes).

3.3 Help and support

DIADEM has a context-sensitive help system. Pressing F1 or clicking the Help button will bring up help information relevant to the page you are working on. The help file can also be accessed via the Help menu. The help and manual contain mostly the same information, though the former does not include the appendices that are part of the manual.

The DIADEM website (http://www.dft.gov.uk/diadem) includes an FAQ list which covers a number of issues relating to running DIADEM.

If you have any questions, problems or suggestions for improvements please contact the DIADEM help desk at Mott MacDonald: email diadem@atkinsglobal.com.

DIADEM is developed on behalf of ITEA division of the Department for Transport (E: itea@dft.gsi.gov.uk). Please note that details of support queries will be passed to the Department for their information.

DIADEM User Manual Version 5.0 (SATURN)



Guidance on all aspects of modelling, including assignment and variable demand modelling, can be found on WebTAG (http://www.dft.gov.uk/webtag). Questions on the application and interpretation of WebTAG should be directed towards DfT.



4. Background information

4.1 Logit models

4.1.1 Absolute logit

The logit model is at the heart of the main DIADEM demand model. It is one of a family of models referred to as discrete choice models. Such models predict the probability that an individual will pick a particular alternative when faced with a choice between a number of options. For instance, in the context of mode choice they can be used to predict the probability of someone choosing to travel by bus. When applied to a large number of people these probabilities can be interpreted as mode shares, e.g. the proportion of people who will choose to travel by bus. These proportions can then be multiplied by the total number of people to obtain the number of people using each mode.

Algebraically, the multinomial logit model is given by:

$$p_i = \frac{\exp(U_i)}{\sum_{j} \exp(U_j)}$$

where

 p_i is the probability of choosing alternative i

 U_i is the utility of alternative i

'Utility' is a term used in economics to describe the amount of satisfaction derived from consuming a product or service. In general the utility of travel is negative and is related to the generalised cost of travel by

$$U_i = \lambda c_i$$

where

 c_i is the generalised cost of alternative i

λ is a negative scaling parameter

The scaling parameter can be interpreted as a factor to convert from generalised cost to utility; it can also be seen as a measure of the sensitivity of travel choices to generalised cost.

Taking an example with just two alternatives, say bus and car, it can be shown that the formula reduces to:

$$\rho_{car} = \frac{\exp(U_{car})}{\exp(U_{car}) + \exp(U_{bus})} = \frac{1}{1 + \exp(\lambda(c_{bus} - c_{car}))}$$

This shows an important property of logit models: the choice probabilities depend only on the absolute differences in costs between the alternatives.



When viewed graphically logit models follow a typical S-shaped curve. This can be seen in Figure 4.1, which shows the curves for different values of λ , illustrating how it changes the sensitivity of mode shares to costs.




Figure 4.1: Typical logit curves

In transport modelling logit models have a multitude of uses. In DIADEM the absolute model can be used to model choices of mode and destination (destination choice models are also referred to as trip distribution models).

4.1.2 Mode-specific constants, size variables and K-factors

When using an absolute logit model for mode choice it is usually found that generalised cost alone is not enough to explain the observed mode choice. For example, the logit model would predict that if the generalised costs are the same then the mode share would be 50/50 between car and PT, whereas the corresponding observed mode share might be closer to 60/40. This is usually handled by adding a constant to the generalised cost for one of the modes. This represents the remaining preference for one particular mode, after differences in generalised costs have been taken into account. These constants are called mode-specific constants.

Mode-specific constants can be defined in DIADEM. These constants must be in the same units as the generalised cost function (usually generalised minutes). A positive value for the constant reflects a dislike of that mode, i.e. other things being equal, as the constant increases the mode share will decline.

Similarly, destination choice cannot usually be explained by travel costs alone. For example, suppose Zones X and Y have the same travel costs from Zone Z. If Zone X has twice as many shops as Zone Y we would expect it to attract about twice as many shoppers. This is reflected through the use of size variables 244465/ITD/ITW/4/F 7 February 2011



which are added to the basic functional form as follows:

$$\rho_{j|i} = \frac{B_j \exp(U_{ij})}{\sum_i B_j \exp(U_{ij})}$$

where

 $p_{j|i}$ is the probability of someone travelling from zone *i* choosing to travel to zone *j* is the size variable for zone *j*

Because of the way size variables are used it is only their relative size that affects the model results, the actual units used are not important.

Typical size variables will depend on the trip purpose. For instance, commuting trips will often use the number of jobs; shopping trips might use the amount of retail floorspace or the number of retail employees.

Size variables cannot be used with the doubly-constrained distribution model (i.e. where the number of trips to and from each zone is fixed). When this model is used then, in effect, DIADEM estimates its own size variables to ensure that the specified destination trip end constraints are met.

In a similar vein, K factors are sometimes used in distribution models. They depend on the zone pair and are added to the model as follows:

$$\rho_{j|i} = \frac{K_{ij} \exp(U_{ij})}{\sum_{i} K_{ij} \exp(U_{ij})}$$

They are used to give a better fit between modelled and observed data. K-factors are much-abused in distribution modelling and often lead to over-specified models.

K factors can be used in conjunction with size variables:

$$\rho_{j|i} = \frac{K_{ij}B_j \exp(U_{ij})}{\sum_i K_{ij}B_j \exp(U_{ij})}$$

Alternatively this can be written as:

$$p_{j|i} = \frac{\exp(U_{ij} + \ln(K_{ij}) + \ln(B_j))}{\sum_{i} \exp(U_{ij} + \ln(K_{ij}) + \ln(B_j))}$$


In other words the size variables and K factors can be incorporated into the utilities. This formulation is used in DIADEM in the calculation of composite utilities (see following section).

Section 6.9 explains how the various constants are entered into DIADEM by the user. 244465/ITD/ITW/4/F 7 February 2011



4.1.3 Hierarchical logit

The model becomes more complicated when more than one choice is being considered. Suppose a traveller has to choose between 2 modes and 3 destinations, a total of 6 different combinations. The multinomial logit could be used to model the choice between these 6 options, but it is more common to have mode and destination choice in a hierarchical structure (often referred to as nested logit, and sometimes tree logit).



In effect the logit model is being applied several times, once for mode choice and once for destination choice for each mode separately. These results are then combined together.

On the probability side, the probabilities at the bottom level are calculated *conditional* on the choice(s) made at the higher level. This is denoted $p_{j|im}$. The combined probability of a traveller from zone i choosing to travel to destination j by mode m is then:

$$\rho_{jm|i} = \rho_{m|i}\rho_{j|im} = \frac{\exp(\theta U_{i^*m})}{\displaystyle\sum_{m} \exp(\theta U_{i^*m})} \frac{\exp(U_{ijm})}{\displaystyle\sum_{j} \exp(U_{ijm})}$$

Note the additional scaling/tree parameter θ . This must be greater than zero and less than or equal to 1. It represents how sensitive the upper level choice is to cost, relative to the lower level. The response most sensitive to cost appears at the bottom of the hierarchy, with other responses less and less sensitive the higher up the tree they are.

On the cost side, the bottom level model uses generalised costs converted to utilities U_{ijm} in the normal way. The higher level then uses utilities U_{i^*m} which are, in some sense, the average over the choices in the nest below. These are referred to as composite utilities and are calculated as follows:

$$U_{i^*m} = \ln \sum_{j} \exp(U_{ijm})$$

4.1.4 Spatial segmentation

Spatial segmentation is a feature available in DIADEM whereby the distribution model parameters (λ or θ , depending on the position of distribution in the hierarchy) can vary by OD pair.



4.1.5 Incremental logit

Incremental models are used where the costs and demand (or probabilities) for a *reference* case are known as we want to estimate how a *change* in cost will affect demand. In DIADEM the form of incremental logit model is:

$$p_i = \frac{p_i^0 \exp(\Delta U_i)}{\sum_j p_j^0 \exp(\Delta U_j)}$$

where

 $\Delta U = U_i - U_i^0 = \lambda (c_i - c_i^0)$ where $\lambda < 0$ c_i^0 is the generalised cost from the reference case p_i^0 is the reference case probability

There are two key properties of the model apparent from this equation:

- The results depend on the absolute changes in travel costs for each option. This removes the need to consider size variables and mode-specific constants as they simply cancel out when taking the differences.
- If the reference case probability is zero then it will remain zero in the forecast case.

These models are also known as pivot point models because they pivot around the reference case.

The reference case has a number of interpretations. For instance, it may be thought of as a hypothetical situation saying that *if* the costs were c_i^0 then the demand would be p_i^0 . Alternatively it can be thought of as specifying a point on the demand curve.

In DIADEM the user has to input the data for the reference case. Commonly there are two possible sources for this data, referred to as pivoting off the base year and pivoting off the DM. These are illustrated below.



Figure 4.2: Pivoting off the base year.




Figure 4.2 depicts the base year situation with demand curve $D_{Base\ Year}$ and supply curve $S_{Base\ Year}$. From the calibrated and validated base year model we know the costs C^{base} and trips T^{base} . Typically in DIADEM we will be forecasting for a future year. The demand curve in the future will tend to shift to $D_{Forecast\ Year}$ as a result of economic and demographic effects (e.g. increased car ownership, higher population and smaller households). DIADEM's job is then to estimate the future year equilibrium position E (for simplicity we assume in this example that the supply curve does not change). To do this it requires a reference case. Typically this will be point R which is a combination of base year costs, and applying TEMPRO growth to the base year trip matrix to obtain reference trips (making sure any specific local developments are included (see WebTAG Unit 3.15.2 'Use of TEMPRO Data' for more details on how to do this)). Note that TEMPRO gives a reference case growth rate, i.e. what the growth will be *if* generalised costs remain unchanged.

When using TEMPRO to derive reference matrices for input to DIADEM the TEMPRO fuel and income factors should *not* be used. Instead the effect of changing fuel costs and incomes should be represented by changing the generalised cost coefficients. See Section 6.5.5.



Figure 4.3: Pivoting off the do minimum




Figure 4.3 illustrates an alternative pivoting approach that can be used when modelling the do something (DS) scenario, provided the do minimum (DM) has already been modelled. From the DIADEM results for the DM we have the DM equilibrium point E^{DM} . This gives us the DM costs and trips which we then use, unmodified, as the reference case for the DS. We can do this because the demand curve does not change between the DM and DS, hence the DM equilibrium is a point on the DS demand curve and can be used as the reference case.

WebTAG recommends the use of incremental models whenever possible.

4.1.6 Implementation in DIADEM

Absolute and incremental hierarchical logit models are both available in DIADEM for destination choice (distribution) and mode choice. The incremental model can also be used for modelling time period choice. The three responses can be placed in any order in the hierarchy.

Singly and doubly-constrained distributions options are available in DIADEM. In the singly-constrained models the trip ends are fixed for one end of the trip, with no constraints on the other end. The singly-constrained options available in DIADEM are:

DIADEM User Manual Version 5.0 (SATURN)



- Origin-constrained (for OD models) equivalent to a model of destination choice
- Destination-constrained (for OD models) equivalent to a model of origin choice (most likely to be used for trips travelling to home with the home end fixed)
- Production-constrained (for PA models)

The doubly-constrained model is available for OD and PA options. The total trip ends to and from each zone are fixed.

In the absolute model there is the option to define mode-specific constants for the mode choice model, and size variables and K factors for the distribution model. Size variables cannot be used for the doubly-constrained distribution model.

The λ parameter is defined for the response at the bottom of the hierarchy. The θ parameter is defined for all higher level responses.

4.2 HADES

4.2.1 Overview

HADES stands for Heterogeneous Arrival and Departure times with Equilibrium Scheduling. It is a model of micro arrival time choice, intended to deal with short time shifts of the order of about 5 to 20 minutes. As such it is distinct from the macro time period choice model in DIADEM, which deals with the choice between travelling in, for example, the AM peak and the inter-peak.

HADES was originally developed as an experimental stand-alone program (see Mott MacDonald, 2004. 2005a-2005c). The version of the HADES method known as HADES-B has now been implemented in DIADEM and is available for use on a beta test basis. This means that the software may not be as robust as a full release version. As part of the beta testing process, users are asked to provide feedback to DIADEM support (diadem@atkinsglobal.com) on their experience in using the software and to report any bugs as soon as they are encountered.

4.2.2 Equilibrium scheduling theory (EST)

HADES is based on the principles of equilibrium scheduling theory (EST), as set out by Vickrey (1969), and later developed by Small (1982, 1992a, 1992b), and Arnott et al (1994).

The main idea behind EST is that a traveller has a preferred arrival time (PAT) for their trip, with a cost (known as the scheduling cost) associated with arriving either earlier or later than this. Instead of arriving at their preferred time the traveller may choose to arrive either earlier or later provided they reduce their time spent travelling (the travel duration) by enough to offset the increased scheduling cost. (Note the use of 'travel duration' instead of the more usual 'travel time'; this is to avoid any possible confusion with arrival and departure times.)

Earlier work on HADES involved a number of developments of the original EST (Bates, 2007 and Mott MacDonald, 2005a-2005c). One of these was to extend the concept of the PAT to a PAT window. The traveller is assumed to be indifferent to arrival at any time within this window and only incurs scheduling costs if they arrive before or after this.



EST can be illustrated with reference to the following diagram, which shows the costs for someone with a PAT window between 0845 and 0900. The scheduling cost (in generalised minutes) associated with early or late arrival is shown by the solid blue line. The travel duration is shown by the dotted red line and the total travel cost is shown by the dashed green line. In this example, the PAT window coincides with the peak in travel durations. When the total cost including the scheduling cost is considered, the optimum arrival time is actually at 0835; in other words the traveller is willing to accept some scheduling cost in return for reduced travel duration.




Figure 4.4: Costs associated with preferred arrival time between 0845 and 0900

More formally, the total generalised cost is given by:

$$cost = \begin{cases} \alpha.\xi(\tau) + \gamma(\tau - PAT2) & \text{if} & \tau > PAT2 & \text{(late arrival)} \\ \alpha.\xi(\tau) & \text{if} & \tau \in \left[PAT1, PAT2\right] & \text{(on-time arrival)} \\ \alpha.\xi(\tau) + \beta(PAT1 - \tau) & \text{if} & \tau < PAT1 & \text{(early arrival)} \end{cases}$$

$$(4.1)$$

where:

T	is the arrival time
PAT1, PAT2	are the beginning and end of the PAT window
ξ(τ)	is the travel duration for arrival time τ
α	is the cost coefficient for travel duration
β	is the cost coefficient per unit time for early arrival
V	is the cost coefficient per unit time for late arrival



Note that HADES does not currently include distance or toll-related costs.

HADES is an equilibrium model and seeks to allocate trips to arrival times in such a way that no traveller can reduce their generalised cost by changing their arrival time.

Equation (4.1) can be used when the scheduling constraint is at the destination end of the trip and is often applied when considering the journey to work, or travel to a business appointment. It may not be applicable to the return leg of such trips, and thus is perhaps best suited to modelling the AM peak.

4.2.3 Implementation of HADES in DIADEM

4.2.3.1 Overview

This section explains the details of how HADES has been implemented in DIADEM.

It should be noted that HADES is currently implemented only as an absolute demand model, whereas DIADEM is most often used to implement an incremental model.

The notation used below does not explicitly refer to time periods. Within DIADEM, HADES is applied independently between time periods, i.e. the choice of arrival time within one time period will not affect the choice of the arrival or departure time of the other leg of the trip in a different time period.

4.2.3.2 Limitations

The current implementation of HADES in DIADEM has some limitations:

- Only travel durations and scheduling costs are included in the generalised cost function. Distancebased and toll costs are not included at the present time.
- Convergence between the assignment and HADES demand model is slow and in some cases it may not be possible to achieve acceptable levels of convergence.
- HADES can only be used for highway trips, not public transport.
- HADES can only be used as a stand-alone demand model, or linked to an absolute logit model of mode and destination choice. It cannot be linked to an incremental logit model.

Some or all of these limitations may be addressed in future versions of DIADEM.

4.2.3.3 Segmentation

The levels of segmentation associated with the HADES model in DIADEM are:

- Whether to use HADES is defined separately for each demand segment; even for demand segments
 that do use HADES, it may be turned off in selected time periods (for example, it may only apply to
 commuting trips in the AM peak).
- The definition of PAT windows is done by demand segment, destination sector and time period
- The definition of scheduling parameters β and γ is done by demand segment, destination sector and time period.
- The definition of demand by PAT window is done by origin-destination pair, demand segment and time period.

DIADEM User Manual Version 5.0 (SATURN)



The ability to define PAT windows and scheduling parameters by destination sector is designed to recognise that there may be variations in trip scheduling constraints even within a demand segment. For instance, commuters travelling to one area may be predominantly factory workers, who will have different constraints compared to workers travelling to a different area who may be mainly office workers.

The details of how to enter HADES data in DIADEM are covered in Section 6.11.

4.2.3.4 What does the assignment represent?

For a dynamic assignment model like CONTRAM it is well-defined that the trip matrix for, say, the time slice 0810-0820 represents all trips departing in that time slice.

For a static model like SATURN it is less clear cut and, to some extent, is up to the modeller. So a SATURN time slice for 0810-0820 could either represent trips departing in that time, or trips with a midpoint in that time (the mid-point being midway (in time) between the departure time and arrival time of the trip). Within DIADEM the user can choose either option.

4.2.3.5 Assignment-HADES iteration


Overview

Although sometimes referred to as a departure time choice model, HADES is strictly speaking a model of *arrival* time choice. On the other hand, assignment models typically work on the basis of departure times (or, occasionally, trip mid-point times). Interfacing between the HADES demand model and an assignment model therefore involves a translation of data between the two paradigms.

The overall process is shown in Figure 4.5 below.



Figure 4.5: Assignment-HADES iteration.



The details behind each step are described in more detail below.

Time skimming

After an assignment travel durations are skimmed as per a conventional DIADEM run. However, the way these skims are used is slightly different.

Within HADES it is assumed that travel duration varies continuously with arrival time, and therefore also by departure time. For each OD pair and demand segment the skim will return a single value for the travel duration for each time slice. It is then necessary to associate this duration with a fixed point in time.

If the assignment is based on departure times (or trip mid-points), then the travel duration is assumed to be that for a trip departing at (or with a mid-point at) the middle of the time slice, i.e. if the time slice represents 0810 to 0820 then the skimmed travel duration is assumed to be for a trip departing (or with a mid-point at) 0815.

Travel durations by arrival time

From the previous step, for each OD pair and demand segment we have the travel duration for a discrete set of departure times (or trip mid-points). As noted earlier, HADES is more concerned with arrival times,



so the data are translated to travel duration by arrival time as follows:

- For assignments based on departure time, arrival time is departure time plus travel duration
- For assignments based on trip mid-points, arrival time is trip mid-point time plus half the travel duration

Travel durations for arrivals at other times are interpolated from the above values¹. This can only give travel durations for a period similar to that covered by the assignments. For example if the assignment covers, in total, the period 0800-0900 then the above might only give us travel durations for arrival between 0810 and 0910 (assuming 10 minute travel durations).

For this reason, the user must also define pre-peak and post-peak travel times. When modelling the AM peak the former will be close to free-flow times, but the latter are likely to be a bit higher. Durations for arrival before or after the time interval defined by the above process are then extrapolated until they hit the user-defined pre and post-peak times. This gives us travel durations for a much wider range of arrival times than implied by the assignment. (This has implications for the length of the period covered by PAT windows, compared to that covered by the assignment. This is discussed further in Section 6.11.)

The process is illustrated in Figure 4.6. The red squares represent the travel durations for a set of departure times, as defined by the assignment. Converting these to travel durations for a set of arrival times gives us the blue diamonds; the horizontal distance between the two represents the travel duration. The blue line shows the interpolation and extrapolation of these values, including the user-defined pre-peak and post-peak durations, represented by the horizontal sections of the line.




Figure 4.6: Obtaining travel durations as a function of arrival time.

_

At this stage DIADEM will check for violations of the first-in first-out (FIFO) principle by looking for any cases where later departure implies earlier arrival. A warning message will be issued to the log file if this is found to be the case.
244465/ITD/ITW/4/F 7 February 2011



Cost of arrival in each arrival window

For a trip for a given origin, destination and demand segment, with a preferred arrival time window k, the next step is to calculate the cost of arrival in each possible arrival time window, in order to then be able to calculate the optimum arrival time, i.e. the one with the minimum cost.

The cost of arrival in a given arrival time window is calculated assuming arrival in the middle of the window. The travel duration (interpolated as described earlier) is added to any scheduling cost. The scheduling cost will be zero for any actual arrival time window h that is the same as the preferred arrival time window h.

For a trip from zone *i* to zone *j* in demand segment *c* with PAT window *k* the generalised cost of arriving in the middle of a particular arrival time window *h* (at time τ_h) is given by ²:

$$V_{ijckh} = \begin{cases} \xi_{ijc}(\tau_h) + \gamma_{Jc}(\tau_h - PAT2_k) & \text{if} & \tau_h > PAT2_k \text{ (late arrival)} \\ \xi_{ijch} & \text{if} & \tau_h \in [PAT1_k, PAT2_k] \text{ (on - time arrival)} \\ \xi_{ijc}(\tau_h) + \beta_{Jc}(PAT1_k - \tau_h) & \text{if} & \tau_h < PAT1_k \text{ (early arrival)} \end{cases}$$

$$(4.2)$$

 $\xi_{ijc}(r_h)$ is the (interpolated) travel duration for demand segment c from zone i to zone j arriving at time r_h is the sector which contains zone j

Allocate demand to arrival time windows

Once the utilities V_{ijckh} have been calculated the demand T_{ijck} is allocated on an all or nothing basis to arrive in the arrival time window $h^*(k)$ with the lowest generalised cost. This gives the 'auxiliary' demand Y:

$$Y_{ijckh} = T_{ijck} \cdot \delta_{ijck:h,h}. \tag{4.3}$$

where

 $\delta_{ijck:h,h^*} = 1$ if $h=h^*$, i.e. h is the arrival time window with the lowest cost for this ijck $\delta_{ijck:h,h^*} = 0$ otherwise

Y is subsequently combined with the current best estimate of trips, as described below.

Convergence algorithm

Suppose X_{ijckh}^N is the current best estimate of the number of trips from i to j in class c with a preferred arrival time of k that choose arrival time window h. (N is the iteration number and refers to the number of HADES-assignment model loops that have been carried out.)

This is slightly simpler than equation (4.1). In DIADEM the cost is expressed in generalised minutes. In DIADEM-HADES travel durations are also in minutes, therefore we can set α=1 and define the scheduling parameters β and γ as the scheduling costs per minute of early or late arrival relative to one minute of travel duration.
244465/ITD/ITW/4/F 7 February 2011



Following the assignment of X^N , the skimming of costs and completion of all the steps already described above we end up with the auxiliary solution. The two are then combined to obtain the next estimate. With the fixed step length (FSL) and method of successive averages (MSA) algorithms this is done as follows:

$$X_{ijckh}^{N+1} = (1-\alpha) \cdot X_{ijckh}^{N} + \alpha \cdot Y_{ijckh}$$
(4.4)

where α is the step length, as defined by either the fixed step length (FSL) or method of successive averages (MSA) algorithm.

If the Social Pressure algorithm is used the formula is:

$$X_{ijCkh}^{N+1} = \begin{cases} X_{ijCkh}^{N} - \min[1, \alpha \cdot P_{ijCkh}] \cdot X_{ijCkh}^{N-1} & \text{if } h \neq h_{ijCk}^{*} \\ X_{ijCkh}^{N} + \sum_{h \neq h_{ijCk}} \left(\min[1, \alpha \cdot P_{ijCkh}] \cdot X_{ijCkh}^{N-1} \right) & \text{if } h = h_{ijCk}^{*} \end{cases}$$

$$(4.5)$$

where

$$P_{ijCkh} = \begin{cases} \begin{pmatrix} V_{ijCkh} - V & \star \\ & ijCkh_{odCk} \end{pmatrix} & if \quad V & \star \\ & V & ijCkh_{odCk} \end{pmatrix} \\ V_{ijCkh} - V & otherwise \\ & ijCkh_{odCk} \end{cases}$$

Convergence monitoring

Because HADES uses a deterministic choice model it is possible to calculate a delta gap function analogous to that used in Wardrop equilibrium assignment models:

$$\delta = \frac{\sum_{ijchk} X_{ijckh}^{N+1} \left(V_{ijckh} - \min_{h} \left(V_{ijckh} \right) \right)}{\sum_{ijckh} X_{ijckh}^{N+1} V_{ijckh}}$$
(4.6)

This is referred to as the HADES gap in the output files. It is not directly comparable to the demand-supply gap usually reported by DIADEM. The gap will be zero at equilibrium.

The HADES gap value can be used as a stopping criterion in the iterative process.

An alternative convergence measure, the average excess cost (AEC), is discussed in Mott MacDonald (2011). It is not automatically output by DIADEM, but can be calculated from standard outputs. Please contact DIADEM support if you would like details.



Conversion of demand by arrival time window to demand by assignment time slice

Having calculated the demand X by arrival time window, it then needs to be converted into demand by assignment time slice. At this stage we are only interested in the actual arrival time window h and not the preferred arrival time window h so we can sum the arrival time matrix over h as follows:

$$X_{ijch}^{N+1} = \sum_{k} X_{ijckh}^{N+1} \tag{4.7}$$

For tidiness we now drop the *ijc* subscripts, but note that the following steps need to be carried out for each *ijc* combination.

First calculate the cumulative arrival time distribution Ω , i.e. the total demand arriving before the end of each arrival time window ($rend_H$):

$$\Omega(rend_H) = \sum_{h=1}^H X_h^{N+1} \tag{4.8}$$

In addition we can also calculate the cumulative demand at the start of the first arrival time window $\Omega(rstart_1)^3$.

Using the interpolation method set out earlier, we then estimate travel durations for arrival at the end of each arrival time window (and the beginning of the first one) to obtain $\xi(rend_H)$ and $\xi(start_1)$.

For departure time-based assignment we can then calculate the cumulative distribution of demand by departure time, Q, at the corresponding departure times:

$$Q(rend_H - \xi(rend_H)) = \Omega(rend_H)$$

$$Q(rstart_1 - \xi(rstart_1)) = \Omega(rstart_1)$$
(4.9)

Or, for assignments based on trip mid-points:

$$Q\left(\tau end_{H} - \frac{\xi(\tau end_{H})}{2}\right) = \Omega(\tau end_{H})$$

$$Q\left(\tau start_{1} - \frac{\xi(\tau start_{1})}{2}\right) = \Omega(\tau start_{1})$$
(4.10)

Using linear interpolation we then evaluate Q at the end of each assignment time slice r. Call this Q_r.

The demand to be allocated to timeslice r for assignment is then just:

 $Q_r - Q_{r-1}$ where Q_0 is Q evaluated at the beginning of the first time slice

Note that not all demand will be allocated to assignment time slices. Some may be allocated to pre and post-peak periods and will not be assigned.

This is not necessarily zero as HADES can shift demand to arrive before the start of the first arrival time window. 244465/ITD/ITW/4/F 7 February 2011 http://pims01/pims/llisapi.dll/open/1453538064



The principle is illustrated in Figure 4.7 which shows cumulative demand distributions by arrival and departure times, and how the latter is used to calculate the demand allocated to a particular time slice (0800-0815), using the difference in the cumulative demand function (departure time) between the beginning and end of the time slice. If the 0800-0815 time slice were the first assignment time slice, then any trips departing before 0800 would not be assigned.




Figure 4.7: Use of cumulative demand distributions to allocate demand to assignment time slices.

The first iteration

On the very first iteration it is assumed that all travellers choose to arrive at their preferred arrival time. The user-defined pre-peak travel durations are then used to convert this to departure times (or trip mid-points), and then to demand by time slice for assignment.

4.2.4 Integrating HADES with other demand responses

The process described above refers to HADES iterating with the assignment only, with no other demand responses involved. However DIADEM allows HADES to be integrated with other responses, specifically absolute logit models of mode choice and distribution (the other DIADEM responses of frequency and time period choice are not currently available in absolute form). The overall process is illustrated in Figure 4.8.



Main demand model (mode choice & distribution) Demand by time Demand by time period (HADES period (non-HADES segments/periods) segments/periods) Run HADES model Apply fixed profiles Demand by assignment time slice Assignment Costs by assignment time slice Costs by time period

Figure 4.8: Integrating HADES with other demand responses.

The main demand model is shown at the top. This produces trip matrices by time period. For HADES demand segments and time periods the HADES process described earlier is applied to produce demand by time slice, ready for assignment. For non-HADES demand segments and time periods, fixed profiles are applied to produce demand by time slice.



The demand is then assigned and the costs skimmed. For HADES time periods there is an iterative loop between the assignment and HADES which is run to convergence, as described in section 4.2.3. This is done independently for each time period to which HADES is applied.

Following the convergence of this loop, costs by time period need to be calculated for passing to the demand model. This is a three-stage process as follows:

- For each OD pair and demand segment, the actual arrival time *h* is checked to see if it falls within the time period. Based on the actual arrival time and the travel duration the clock time of the midpoint of the trip is calculated to see if it is within the time period. If it does, the related data is used in the following stages. If it doesn't, the data is discarded. For example, the time period might be 0700-1000. If the actual arrival time is 1010 and the travel duration is 30 minutes then the midpoint occurs at 0955 and fits in the time period. If the actual arrival time is 1010 and the travel duration is 10 minutes then the midpoint occurs at 1005 and is outside the time period.
- For each preferred arrival time k, the minimum cost over all actual arrival times h is found.
- A flow-weighted average of this minimum cost over all k is then calculated. This gives the cost by OD pair, demand segment and time period which is passed to the main demand model.

Note that, for HADES demand segments and time periods, the costs used in the main demand model do not include distance-related or toll costs. This may be changed in a future version.

4.3 Generalised costs and cost damping

4.3.1 Generalised costs

DIADEM works with generalised costs in time units, specifically generalised minutes. The cost function is:

$$60 \cdot \left(t + \frac{ppk \cdot d + toll}{VOT}\right)$$
 for highway trips

$$60 \cdot \left(t + \frac{fare}{VOT}\right)$$
 for PT trips

where

t is the time in hours

d is the distance in kilometres

toll is the toll (or parking charge) in pence

fare is the PT fare in pence

ppk is the vehicle operating cost in pence per kilometre

VOT is the value of time in pence per hour

Generalised costs are converted to utilities for use in the demand model as described in Section 4.1.



4.3.2 Cost damping

It was noted in section 4.1.1 that the choices predicted by the multinomial logit model depend only on the difference in utilities or generalised costs between alternatives. This means that for a choice between two alternatives, the model gives the same choice probabilities when the alternatives have costs of 115 and 120, as when the alternatives have costs of 15 and 20. However, some modellers argue that this overestimates the sensitivity of longer trips to differences in costs and that in the former case the split should be closer to 50/50 than in the latter case. One way to achieve this is to use cost damping.

The idea behind cost damping is to adjust the cost for longer trips so that their sensitivity to individual cost components (like fuel cost or travel time) is reduced. A typical impact of cost damping is shown in Figure 4.9. This shows that the cost used in the demand model is reduced compared to the 'undamped' cost and that a greater reduction is applied the higher the undamped cost.




Figure 4.9: Effect of cost damping on the cost used in the demand model.

Table 4.1 shows how cost damping can affect mode shares in a model of the choice between car and PT. In Scenario 1 the two modes have costs of 115 and 120 units respectively, in Scenario 2 the costs are 15 and 20. The difference in costs between the two modes is the same in both scenarios (5 units). Without cost damping the mode shares are the same in both scenarios (60/40). With cost damping the shares in Scenario 1 become more even (55/45) but there is little change in Scenario 2, i.e. cost damping makes travellers less sensitive to cost differences in the higher cost scenario.



Table 4.1: Example of the effect of cost damping on choice probabilities.

			Mode shares (choice probabilities)	
Scenario	Mode	Undamped cost	Without damping	With damping
Scenario 1	Car	115	60%	55%
	PT	120	40%	45%
Soonaria 2	Car	15	60%	59%
Scenario 2	PT	20	40%	41%

WebTAG 3.10.2 'Variable demand modelling – scope of the model' sets out 4 different cost damping mechanisms. All of these are available in DIADEM. For consistency with the notation in WebTAG the following sections use *c* to refer to money costs; in DIADEM this is either the combination of toll and vehicle operating cost for highway trips, or fare for PT trips. The basic cost function is then:

$$60 \cdot \left(t + \frac{c}{VOT}\right)$$

The following sections set out the different cost damping functions. Further information on obtaining suitable parameter values can be found in WebTAG. All the functions have been previously used in practice, but there is little empirical evidence to prefer one method over another. A thorough review of cost damping methods and their theoretical basis can be found in Daly (2010).

4.3.2.1 Damping by a function of distance

$$damped cost = \begin{cases} \left(\frac{dshort}{k}\right)^{-\alpha} \cdot 60 \cdot \left(t + \frac{c}{VOT}\right) & \text{if dshort} > d' \\ 60 \cdot \left(t + \frac{c}{VOT}\right) & \text{if dshort} \le d' \end{cases}$$

where

dshort is the shortest distance on the network for the zone pair

 α is a parameter greater than or equal to zero and less than one

k is a positive parameter

d' is a cut-off distance, below which cost damping is not applied, with k=d' if d'>0

According to WebTAG *dshort* "should be calculated by skimming distances along minimum distance paths built between all origin-destination pairs using a base year network. In forecasting, there would only be a need to recalculate these distances if the structure of the network changed significantly between base and forecast years."

4.3.2.2 Damping by a power function of cost

$$damped cost = \mu \cdot \left(60 \cdot \left(t + \frac{c}{VOT}\right)\right)^{\beta}$$

where



- β is a parameter greater than zero and less than or equal to one
- μ is a positive parameter

4.3.2.3 Varying the non-working value of time by distance

$$damped cost = 60 \cdot \left(t + \frac{c}{VOT_d}\right)$$

where

 VOT_d is the value of time which varies with distance and is calculated using:

$$VOT_d = VOT \cdot \left(\frac{\max(d, d_c)}{d_0}\right)^{n_c}$$

VOT is the average value of time;

- d₀ is a calibrated parameter value to ensure that the average value of time is consistent with that derived from either WebTAG or local data;
- n_c is the elasticity of VOT with respect to distance;
- d_c is a calibrated parameter value designed to prevent short-distance trips, particularly intrazonal trips, becoming unduly sensitive to cost changes.

4.3.2.4 Log cost plus linear cost

$$damped cost = 60 \cdot t + \epsilon \log(c + \delta) + \gamma c$$

where

- δ is a small constant (e.g. 1p); and
- ε, γ are coefficients greater than or equal to zero

When models of this type are used, the implied value of time (pence per hour) can be obtained from the formula:

$$VOT = \frac{60}{\gamma + \frac{\varepsilon}{c + \delta}}$$

These values of time need to be acceptable over all appropriate values of c.



4.3.2.5 Implementation in DIADEM

All of the cost damping mechanisms can be combined into a single function:

$$cost = \mu \left(\frac{dshort^{0}}{k}\right)^{-\alpha} \left(\frac{60 \cdot t + \epsilon \cdot \log(ppk \cdot d + toll + \delta) + ppk \cdot d + toll}{\gamma \cdot (ppk \cdot d + toll) + S_{1} \cdot 60 \cdot \frac{ppk \cdot d + toll}{VOT \cdot \left(\frac{max(dshort, d_{c})}{d_{0}}\right)^{n}}\right)^{\beta}$$
for highway

$$cost = \mu \left(\frac{dshort^{0}}{k}\right)^{-\alpha} \left(\frac{60 \cdot t + \epsilon \cdot \log(fare + \delta) + \sigma}{\gamma \cdot (fare) + S_{1} \cdot 60 \cdot \frac{fare}{VOT \cdot \left(\frac{\max(dshort, d_{c})}{d_{0}}\right)^{n}}\right)^{\beta}$$
for PT

where S_1 is a binary switch that takes the values:

$$S_1 = \begin{cases} 1 & \text{if} \quad \epsilon = \gamma = 0 \\ 0 & \text{otherwise} \end{cases}$$

In other words, when the log plus linear cost option is applied, the final term inside the brackets is not used (it would duplicate the linear cost term that has the ε coefficient).

By setting appropriate values for each parameter, particular cost damping mechanisms can be turned on or off, and different methods can be used together. This is explained further in section 6.5.5.5, which describes how cost damping data can be entered into DIADEM.

Note that the log plus linear cost method and the varying non-working value of time by distance method should not be used at the same time.

4.4 OD and PA

4.4.1 Introduction

As discussed in WebTAG <u>Unit 3.10.2</u> (Variable Demand Modelling – the Scope of the Model) trip matrices can be represented in origin-destination (OD) or production-attraction (PA) format.

Consider someone who lives in zone A and works in zone B. They commute to work in the AM peak and return home in the PM peak. This behaviour would be represented in the two matrix formats as follows:

OD matrix AM peak:

	Α	В
Α	0	1
В	0	0

OD matrix PM peak:

	Α	В
Α	0	0
В	1	0



PA matrix 24 hrs:

	Α	В
Α	0	1
В	0	0

In the PA format the value of 1 with production zone A and attraction zone B implies the outbound trip from A to B and the return trip from B to A. Some notations would require a value of 2 to give a single outbound and a single return trip. However in the convention used in DIADEM a value of 1 implies a single trip in each direction.

The key differences can be summarised as follows:

OD	PA
Usually broken down by time period	Usually represent a 24 hour total
Direction of travel is always from origin to destination	Production end is always the home end of the trip, regardless of the direction of travel

It can be seen that the OD representation loses the link between outbound and return trips. This means it is difficult to ensure consistency of travel behaviour between the two legs. For example, someone might choose to go out by car but return by bus. This is one of the main disadvantages of OD-based demand modelling.

Where matrices are in PA format it is still necessary to convert them to OD matrices by time period for assignment to the transport network. This is done using a series of factors which, for example, represent the proportion of trips that go out in the AM peak, or the proportion that return in the inter-peak.

Conversion from OD to PA is usually not possible as the link between the two legs has normally been lost, as has the information on which end of the trip is 'home'.

Variable demand modelling can be done using OD or PA format matrices. WebTAG recommends that PA is used for home-based trips. This has the advantage that it ensures consistency between mode and destination choice for outbound and return trips, and that these decisions are affected by costs on both legs. PA modelling is normally only used for home-based trips. Non home-based trips can be modelled on an OD basis.

4.4.2 Trips and tours

DIADEM actually uses a development of 24 hour PA modelling. This is necessary because traditional PA modelling does not support the modelling of time period choice in a way that is consistent with WebTAG. This is explained further in the paper by Gordon et al (2007).

For home-based trips, a single tour consists of all the trips made between leaving home and returning. For example home to work to shops to home is a single tour.



DIADEM makes the simplifying assumption that all tours are so-called 'simple' tours, i.e. they go from home to a single destination and then back home again. Diversions from this can be modelled as non home-based trips using OD-based demand modelling.

The distinction between PA modelling and simple tours is not clear cut. As far as DIADEM is concerned the key difference is that with tour modelling we explicitly consider, and link together, the time periods for outbound and return travel. The 24 hour PA matrix is broken down by outbound and return travel times. If there are, for example, four time periods (AM and PM peaks, inter-peak and off-peak) then the PA matrix is broken down into 16 (=4 x 4) combinations of outbound and return times.

To break down a 24 hour PA matrix to this level of detail requires information on what proportion of trips in the 24 hour matrix go out and return in each combination of time periods. This data is typically available from household travel diaries, but usually not from roadside interviews. A new method has been developed for DIADEM which makes use of national data combined with local data to minimise the local data requirements. This can be illustrated with reference to the following table.

Table 4.2: Tour and PA modelling data requirements.

		Return time period				
		AM	IP	PM	OP	Total
Φ	АМ					
d ti	IP					
ound	PM					
Outbound time period	OP					
	Total					

Consider a particular zone pair, mode and demand segment. For tour-based modelling we need to know the proportion of trips for each of the 16 unshaded cells in the table, e.g. 45% of commuting trips by car go out in the AM peak and return in the PM peak. However, typically we may only know the proportions in the shaded cells, e.g. 70% of commuting trips by car go out in the AM peak.

The approach used in DIADEM is to take initial estimates for the unshaded cells (also called tour proportions), for which local information may not be available and to use local data for the shaded cells to furness the unshaded cells. Initial estimates for the tour proportions cells (by purpose and mode) have been calculated from National Travel Survey (NTS) and reproduced in Appendix C for information. The user then needs to just specify local data for the shaded cells.

These tour proportions are used slightly differently in the incremental and absolute implementations of the model.

In the incremental version the tour proportions are applied to the input reference 24 hour PA matrix to obtain reference tour matrices by outbound and return time periods. The tour proportions have no further use as the information they contained is now in the reference tour matrices. The application of time period choice in the incremental model may subsequently change the number of trips in each outbound/return time period combination.



In the absolute version no reference matrix is input, just the trip ends. The tour proportions are therefore used to segment the trip ends by each outbound/return time period combination. (Note that for the doubly-constrained model the constraints are always applied summed over all time periods and modes).

4.5 Public transport in DIADEM

DIADEM has a simplified representation of public transport (PT).

Mode choice in DIADEM is a simple two way choice between car and PT. If a more detailed representation of mode choice is required this will need to be represented outside DIADEM. Examples might include modelling the choice between bus and rail, or looking at park and ride submodes. In many cases it will be possible to use the public transport assignment model for these choices and to use DIADEM for main mode choice and other demand responses – please contact DIADEM support for advice.

A second simplification is that DIADEM assumes that PT costs are not demand responsive. DIADEM will carry out a highway assignment every time it adjusts demand to see how costs are affected, but assumes PT costs remain unchanged. This has two implications:

- The level of crowding, if modelled, is assumed to remain constant and will not change as public transport passenger numbers change.
- Bus travel times are not automatically linked to changes in highway travel times.

If either of these effects is significant then it might be necessary to include an additional manual outer loop in the DIADEM process, for example:

- 1. Obtain an initial set of forecast PT costs for input to DIADEM
- Run DIADEM with these PT costs.
- Based on DIADEM outputs (PT passenger demand, highway travel times) update the forecast PT costs and, if they have changed for those previously input, rerun DIADEM
- 4. Repeat as necessary until PT costs have stabilised

WebTAG states that it is acceptable to use fixed PT costs where the mode share is less than 5%. As noted above it will also be acceptable if a) crowding is not significant and b) travel times for the PT mode(s) being considered do not depend significantly on highway travel times. In all other cases a manual outer loop similar to that described above will be required.

Note that although PT costs remain fixed within a given DIADEM run, they can change between different DIADEM runs to reflect different scenarios, whether that it due to changes in the individual cost components (e.g. reduced travel times as a result of infrastructure improvements) or changes in the cost coefficients (e.g. increased values of time as a result of incomes increasing over time).




4.6 Segmentation in DIADEM

4.6.1 Demand segments

DIADEM demand models operate with two levels of segmentation: trip purpose and person type. This is illustrated with an example in Figure 4.10. Total travel is first split into 3 purposes: commute, employer's business and other. Travel within each purpose is then further divided into trips made by two distinct person types, those with a car available for the trip and those without.

Figure 4.10: Segmentation by trip purpose and person type



As well as car availability the other common division of person types is according to income or willingness to pay bands, for example to model the response to road tolling. This can also be represented in DIADEM.

Each trip purpose is treated independently for demand modelling. For example, in a doubly-constrained distribution model distinct trip end constraints are used for each purpose and are applied separately.

The way person types are grouped into trip purposes only matters when a doubly-constrained distribution model is being used. In this case the trip end constraints are applied at the purpose level, not to individual person types within that purpose. This can be seen as different person types competing for a single set of trip ends.

Each person type can have its own demand model structure and associated parameters. The only restriction is that if one person type within a purpose has a doubly-constrained distribution model then all person types within that purpose must have one.

Person types can be marked as being 'car not available'. Mode choice is not modelled for these person types; they are assumed to be captive to public transport. The main reason for including such person types would be to ensure that they are included in the competition for trip ends in a doubly-constrained distribution model.

The purpose/person type combinations used in the demand model have to be mapped to the different user classes in the assignment model. This is described in detail in section 6.4.



In the rest of this document the term 'demand segment' is used to refer to a particular purpose/person type combination.

Demand segments can also represent a particular vehicle type. For example HGVs can have their own demand segment which may be treated as having fixed demand, i.e. no variable demand model is applied.

4.6.2 Time periods

If time period choice is modelled then time periods will be linked together through the structure of the model hierarchy.

If time period choice is not modelled then the demand model is generally applied independently to each time period (for OD modelling) or each combination of outbound and return time period (for PA modelling). The exception is when the doubly constrained distribution is used, in which case the constraints are applied summed across all time periods.



5. Preparation for a DIADEM run

5.1 Overview

Chapter 6 sets out the process of setting up a DIADEM run in detail. This chapter describes some of the data preparation required before starting the DIADEM software and gives a brief overview of the DIADEM set up process.

DIADEM will need to be run separately for each scenario (Do-Minimum (DM) and Do-Something (DS)) and forecast year.

The data preparation and DIADEM set up are slightly different for absolute and incremental models and are set out separately in the following sections. Note that it is possible to mix absolute and incremental model demand segments within the same DIADEM run.

Simplified representations of a DIADEM run are shown in Figure 5.1 to Figure 5.3 at the end of this chapter, representing an incremental model pivoting off the base year, an incremental model pivoting off the Do-Minimum, and an absolute model respectively. The shaded boxes represent information specified by the user via the interface program. The iterative loop is shown within the dotted line and is controlled by DIADEM.

A summary of trip and cost data requirements for the different types of demand model is shown in the table below

Table 5.1: Summary of trip and cost data requirements

	Incremental model		Absolute model	
	OD	PA	OD	PA
Reference trips	Required (by time period)	Required (24 hr PA)	Not re	equired
Reference costs	Required		Required when trip ends are defined rather than 'initial guess'	
Trip ends	Not required		Either trip ends or 'initial guess' matrix is required.	
Initial guess matrix	Not required			
Initial tour proportions, outbound and return time period proportions	Not required	Required	Not required	Required

An absolute model with HADES requires the following additional trip data:

- Profile of trips over preferred arrival time windows for each HADES demand segment/time period
- Profile of trips over time slices for each non-HADES demand segment/time period



5.2 Incremental model

Before running DIADEM you will need, at least, the following:

- Assigned validated base year highway networks (if pivoting off the base)
- Assigned DM highway networks (if running the DS and pivoting off the DM)
- Forecast year reference highway trip matrices
- Forecast year/scenario (e.g. 2016 Do-Minimum) network data files
- Details of the demand model structure you want to set up

If you are doing mode choice modelling, or are modelling non-car available demand segments, you will also need the following public transport (PT) data:

- Forecast year reference trip matrices
- Forecast year/scenario travel times and, optionally, fares
- Reference case travel times and, optionally, fares

The following is a brief summary of the steps required in setting up and carrying out a run of DIADEM. Further explanation of the steps involved and terminology is given elsewhere in the manual and in WebTAG.

- 1. Consult WebTAG and decide on the appropriate segmentation and demand model structure and parameters.
- Prepare forecast network data file(s) for the scenario and year you are planning to model.
- 3. Prepare the reference trip matrix/matrices:
 - a. If pivoting off the base year these will be unrestrained growth forecasts from, e.g., applying TEMPRO to the validated base year matrix.
 - b. If running the DS and pivoting off the DM these will be the forecast trip matrices output by the DIADEM DM run.
- 4. Locate previous assignments from which reference costs can be obtained:
 - a. If pivoting off the base year these will be the base year assignment.
 - b. If running the DS and pivoting off the DM these will be the costs from the assignment of the forecast DM matrix produced by DIADEM.
- 5. If using a mode split model, or modelling non-car available person types, then carry out PT assignments for the scenario and forecast year you are modelling and skim forecast costs (fare and generalised time). Repeat for the scenario from which reference costs will be obtained (base year if pivoting off



base, DM if pivoting off DM).

- Using the DIADEM interface set up the DIADEM data using the segmentation and demand model structure and parameters that you decided upon at step 1 and using the reference trip and cost matrices, and PT forecast cost matrices (if applicable) you obtained above.
- Save the DIADEM control file.
- 8. Click the Run DIADEM button.
- When the DIADEM run has completed check the output .csv file to ensure that convergence is acceptable. Use matrices with 'best' appended to the file name for all further analysis. Check the log file for warning messages.

5.3 Absolute model

Before running DIADEM you will need, at least, the following:

- Forecast year trip ends (absolute model) or an initial guess of the full trip matrix for the year you are modelling
- Forecast year/scenario (e.g. 2016 Do-Minimum) network data files
- Details of the demand model structure you want to set up

If you are doing mode choice modelling, or are modelling non-car available demand segments, you will also need the following public transport (PT) data:

- Forecast year/scenario travel times and fares
- Forecast year reference trip matrices

If you are specifying trip ends rather than an initial guess matrix then you will also need to provide some reference costs for DIADEM to carry out an initial distribution of the trip ends. These will usually come from the modelling results of some other year/scenario that has already been carried out, for example the base year model, the do-minimum model when modelling the do-something, or the scheme opening year when modelling the design year.

The following is a brief summary of the steps required in setting up and carrying out a run of DIADEM. Further explanation of the steps involved and terminology is given elsewhere in the manual and in WebTAG.

- 1. Consult WebTAG and decide on the appropriate segmentation and demand model structure and parameters.
- 2. Prepare forecast network data file(s) for the scenario and year you are planning to model.
- 3. If using a mode split model, or modelling non-car available person types, then carry out PT assignments for the scenario and forecast year you are modelling and skim forecast costs (fare and




generalised time).

- 4. Using the DIADEM interface set up the DIADEM data using the segmentation and demand model structure and parameters that you decided upon at step 1 and using the reference trip and cost matrices, and PT forecast cost matrices (if applicable) you obtained above.
- 5. Save the DIADEM control file.
- 6. Click the Run DIADEM button.
- 7. When the DIADEM run has completed check the output .csv file to ensure that convergence is acceptable. Use convergence results to pick 'best' DIADEM matrix and use this for all further analysis. Check the log file for warning messages.



Figure 5.1: Structure of a DIADEM run, incremental model pivoting off the base year. (Shaded background indicates user-specified input.)






DM DIADEM Reference Demand model Unmodified trip matrices output structure and (PT & HW) matrices parameters DM DIADEM assignments Skimming Reference Forecast cost matrices Demand model trip (PT & HW) matrices Forecast Forecast Forecast Forecast Skimming PT highway highway cost network files matrices assignment costs

Figure 5.2: Structure of a DIADEM run, incremental model pivoting off the Do-Minimum. (Shaded background indicates user-specified input.)



Figure 5.3: Structure of a DIADEM run, absolute model. (Shaded background indicates user-specified input.)





6. Entering DIADEM data

6.1 Overview

DIADEM input data is set up from a Windows interface. As discussed earlier, some external preparation of data files is required beforehand.

The data set up in the DIADEM interface can be saved to the DIADEM control file. The data does not need to be complete to be saved; indeed it is recommended that data is saved regularly as you go through the data set up process. Saved files can of course be opened later. Saving and opening files is done through the File menu or via the Save and Open toolbar buttons.

The interface consists of a number of separate pages. Sections 6.4 onwards describe the data requirements for each of these pages in turn. All data should be entered for a page before moving on to the following page.

6.2 The DIADEM Control file

6.2.1 Overview

All data entered via the GUI is saved to a control file. Control files are saved and opened using the familiar File>Open, Save and Save As menu commands. New files are created using File>New.

From version 3 onwards of DIADEM, control files are in xml format and have a .xml extension. xml stands for eXtensible Markup Language.

The basic idea of xml is that it uses tags in angle brackets to identify and describe the data. For example:

<version>5.0</version>

indicates that the data item 'version' takes a value of 5.0 (i.e. this control file is from DIADEM version 5.0).

It is by no means necessary to understand xml to be able to use DIADEM. All editing of data can (and in most cases should) be done through the DIADEM GUI and there is no need to work with the xml files directly. If you do want to find out more there is plenty of material on the internet (a search for 'xml tutorial' will bring up some possibilities).

6.2.2 Viewing xml data

The control file data can also be viewed via the menu option View>Data as tables. This displays the data in your default internet browser. It can then be printed or copied to a word processor (for example). This could be useful if you want someone else to review the file or to include it in a report.

6.2.3 Editing xml data

It is recommended that all editing of DIADEM data is done via the GUI, as this will ensure that the integrity of the data is maintained. However, other methods of editing xml data are available and may be used if



only very minor changes are required, e.g. altering a file name or parameter values. Major changes involving altering the structure of the model, such as adding a demand segment, should not be made in this way.

xml files can be opened and edited in any standard text editor. However, it is far easier to use an editor specifically designed for use with xml as these will interpret the file so that the data can be displayed in a more structured way which makes it easier to distinguish between the tags (which shouldn't be changed) and the data itself (which can be). A huge number of xml editors is available on the internet, many of which are free for commercial use.

Please contact DIADEM support if you require further advice in this area.

6.2.4 Backwards compatibility

DIADEM 5.0 can open control files created in all previous versions of DIADEM. This includes plain text-based control files created using version 2.1. However, it will always save control files in DIADEM 5.0 xml format.


6.3 General information

Before entering the data page by page the choice between using SATURN and CONTRAM assignment models should be made.



6.4 Page 1: forecast network files(s) and segmentation

Figure 6.1: Page 1: Segmentation (SATURN version)



The first step is to define the time periods that are being modelled. Time periods can be further divided into time slices. Time periods are intended to be fairly long, say the whole of the AM peak (e.g. 0700-1000) or the inter-peak (e.g. 1000-1600), whereas time slices are typically much shorter, say 10 to 30 minutes long.

The main purpose of timeslices is to provide a profile of demand and travel costs within the time period for the HADES arrival time choice model. Before the HADES option was introduced it was standard practice to use one time slice per time period.

Note that the main demand model operates at the time period level using costs averaged over all time slices in the period, with demand by time period then being split to time slices either using HADES, or by applying user-defined profiles, depending on the options selected by the user.

A SATURN network file (.dat) must be defined for each time slice, representing the scenario you are forecasting.



To define a time period you can:

- Access the time period menu (on the main menu or right click in the time period box) and select 'Add Time Period', or
- Click the 'Add Time Period' toolbar button

Time periods can be renamed and deleted via the same time period menu. To define time slices and, simultaneously, specify the SATURN network file for the time slice choose 'Add time slice/SATURN Network' from the right click menu.

If time slices are linked using the PASSQ option then this can be indicated using the check box above the time periods box. It is strongly recommended that this is selected if the HADES model is to be used, otherwise there is a significant risk that the FIFO principle (first-in first-out) will be violated. If selected, PASSQ will be applied **within** each time period but not **between** time periods.

NB: If you are using the option to run SATURN assignments in parallel (see Section 6.11) then you must put the SATURN network files for each time *period* in a separate directory. This will reduce the risk of file opening errors, with different SATURN programs trying to access the same file at the same time.

It is also necessary to specify the duration of each time slice. This is done by right clicking on the SATURN network file name for the time slice and choosing 'Change Duration'. For the first time slice in the period the start and end times must be defined, using the 24 hour clock (e.g. 0800, 1700 etc.). For subsequent time slices in the period only the end time needs to be defined (the assumption is that time slices are contiguous, so the start time of each time slice must be the end time of the previous one).

The specified durations must cover the full period represented by the assignment model, even if the model is only an average hour from that period. For example if the inter-peak period from 1000 to 1600 is modelled with a single time slice representing an average hour within the period then the start and end times of the time slice should be entered as 1000 and 1600 respectively. When using PA modelling it is important that together the time periods cover a full 24 hour period.

In the current version of DIADEM there are some restrictions on the way the SATURN network files should be set up:

- PASSQ should be set to FALSE within the .dat file. If you want to link time periods using the PASSQ option you should check the 'Use PASSQ' box in DIADEM.)
- SAVEIT should be set to TRUE, if you want to skim average costs (see section 6.6).
- FILTIJ (i.e. the trip matrix name) should not be specified.
- The GONZO parameter should be set to 1.0 (the default).

DIADEM will check how many user classes are specified in the first SATURN network and set up the correct number of user classes in the user class window. The user classes can be renamed via the user class menu (main menu or right click).



It is then necessary to define the correspondence between assignment user classes and purposes. It is possible for more than one purpose to be grouped into a single user class, perhaps to minimise assignment run times.

Each demand segment can have a completely different demand model but to keep run times down it may be desirable to aggregate some demand segments together for the purposes of assignment. For example there may be demand segments of 'home-based employer's business' and 'non home-based employer's business', which are combined in a single 'employer's business' user class for assignment. Thus the time and distance skims used in the demand model will be the same for each demand segment within the user class.


Purposes are added to user classes by right clicking on the user class and selecting 'Add Purpose'. Once they have been created Purposes can be deleted and renamed. At least one Purpose must be created for each user class. One person type is automatically created for each purpose. Additional person types can be added by right clicking on the purpose and choosing either 'Add Person Type' or 'Add No Car Person Type'. DIADEM does not include trips for 'no car' person type in the matrices used in the SATURN assignment.

The right click and Purpose menus can be used to rename and delete purposes and person types.

Having completed the Segmentation page it is then possible to move to the next page – Model Parameters.



6.5 Page 2: Model Parameters



This page is used to define the demand model structure and associated parameters for each demand segment.

6.5.1 Defining the demand model type

The first step on this page is to specify the type of demand model used for each purpose. Initially all purposes appear in the Fixed Purposes box. Trip purposes to be treated as variable demand then need to be dragged to one of the other boxes, depending on the desired type of demand model (incremental or absolute, OD or PA, or even simple elasticity). The data that needs to be filled in on the rest of the page then varies according to which model form has been selected.



6.5.2 Model hierarchy

The demand segment is selected using the drop down box at the top of the page. The numbering of demand segments is determined by the order in which they are added to the Segmentation page.

The model hierarchy needs to be specified for all variable demand segments (except those using an elasticity model).

The available model responses appear in the left hand side of the Model Hierarchy frame. The right hand side of the frame displays the responses that DIADEM will model; this is initially blank. Model responses are added to the right hand side by either double clicking the response on the left or highlighting the response and clicking the button between the two boxes. Deselecting responses works in a similar way.

There are certain restrictions on which combinations of choices can be selected for each demand segment:

- Only one form of distribution model can be selected
- Frequency can only used in incremental models and can only be selected if a distribution option is also selected
- No responses can appear above frequency
- HADES is only available in absolute models and, if selected, must be at the bottom of the hierarchy.

The different distribution options are discussed in Section 4.1.6.

The hierarchy of responses is also defined in this box. To change the position of a response in the hierarchy highlight it with a left mouse click and then use the up or down button to move it. The most sensitive response should be at the bottom of the hierarchy and the least sensitive at the top. This should be reflected in the values of the parameters associated with each response (see below).

Once all the data has been defined for a particular demand segment it is possible to move on to the next one. This can be done in a number of ways:

- Select a different demand segment from the drop down box
- Click the 'Go to next DS' button to go to the next demand segment
- Click the 'Copy to next DS' button to copy the settings from this demand segment to the next. This can be useful when setting up the data for the first time as there will often be only small differences in the parameters for different demand segments.

6.5.3 Parameters

Model parameters must be defined for each of the selected responses (the parameter boxes for responses not selected will be greyed out).

For the logit-based models the spread (or dispersion) parameter λ must be defined for the choice at the bottom of the hierarchy. λ must be negative.



For choices above the bottom the scaling parameter θ must be defined. For each level this determines the sensitivity of the response relative to the level below. θ must be greater than zero and less than or equal to 1.

It will be clear from which boxes are greyed out for each response whether θ or λ needs to be defined.


See Section 5.1 for an explanation of θ and λ . Illustrative parameter values can be found in Section 1.11 of WebTAG Unit 3.10.3 (Variable Demand Modelling - Key Processes), or they can be calibrated locally if suitable data are available.

In general, the appropriate value of λ depends on the units used for generalised cost. DIADEM always uses generalised minutes – this is consistent with the illustrative parameters in WebTAG.

In accordance with WebTAG advice when mode choice appears above distribution in the hierarchy it is possible to define separate distribution parameters for car and PT modes. If mode choice is below distribution then only a single parameter can be defined.

The elasticity model uses the Tanner function (see Appendix B.3) so two parameters are needed, although often one of them will be zero. The first parameter, λ , corresponds to the exponential part of the function and the second parameter, γ , to the power function. Thus to implement a power elasticity function set λ to zero, and to implement an exponential elasticity function set γ to zero. Non-zero parameters must be negative . Note that λ corresponds to the B parameter in the WebTAG notation and γ corresponds to the A parameter.

Parameters relating to the use of the HADES model (if selected) are defined separately, on the 'HADES Data' page.



6.5.4 Advanced distribution options

There are two features available under the advanced distribution options: calculating intra-zonal costs and spatial segmentation.

Assignment models have trouble producing costs for intra-zonal trips and will typically return a value of zero. Even when a non-zero value is returned it may not be reliable. However, redistribution of trips between inter and intra-zonals is a possible response. To model this correctly a reasonably accurate intra-zonal cost is required. DIADEM estimates this as a factor ρ multiplied by the *minimum* inter-zonal cost. ρ =0.5 is a sensible value to use. It is possible to define a minimum intra-zonal cost. This can be useful if, for any reason, the inter-zonal costs in the network model are not accurate (e.g. the minimum inter-zonal cost may be zero because of unusual centroid connector configurations for adjacent zones).



For incremental models intra-zonal costs are only relevant if there are intra-zonal trips in the reference matrix. If this is the case it is important that the intra-zonal trips are a reasonable estimate and not just an artefact of matrix building procedures.

For absolute models it is recommended that intra-zonal cost estimation is always used.

Spatial segmentation is a feature in DIADEM whereby the distribution model parameter (λ or θ , depending on its position in the hierarchy) can vary according to the zone pair. When this option is selected the distribution parameters are defined in a separate file, which has the following comma-separated variable format:

origin sector, destination sector, demand segment, mode, distribution model parameter

The zone to sector correspondence list is defined on the PA Model Data page. Mode=1 for highway and mode=2 for PT; mode=0 can be used in cases where distribution is above mode choice in the hierarchy to indicate that the parameter is not segmented by mode.

Note that the options selected on this page apply to all demand segments.

6.5.5 Generalised cost coefficients

The generalised cost function used in DIADEM is:

$$60 \cdot \left(t + \frac{ppk \cdot d + toll}{VOT}\right)$$
 for highway trips

$$60 \cdot \left(t + \frac{fare}{VOT}\right)$$
 for PT trips

where

t is the time in hours

d is the distance in kilometres

toll is the toll (or parking charge) in pence

fare is the PT fare in pence

ppk is the vehicle operating cost in pence per kilometre

VOT is the value of time in pence per hour

t, d, toll and fare are obtained by DIADEM by automatically skimming the costs, or via user-supplied files (see subsequent input pages for details). On this screen it is necessary to define the value of time and, for highway trips, the vehicle operating cost coefficient.

Values of time and vehicle operating costs for the calculation of the cost coefficients can be found in WebTAG Unit 3.5.6 ('Values of Time and Operating Costs').

6.5.5.1 Differences between reference and forecast cost coefficients

In an incremental demand model the forecast demand depends on the difference between the latest forecast generalised cost from the scenario currently being modelled and a reference generalised cost.



When pivoting off the base year the reference cost coefficients must be the base year coefficients. The forecast cost coefficients must be the future year coefficients.

Values of time increase in the future as a result of increasing incomes. Similarly, operating costs change as a result of changing fuel costs and improved vehicle efficiency. These changes should be accounted for when calculating cost coefficients for future years.

This means that VOT and VOC values for the 'forecast' scenario should be different from the 'reference' values, when pivoting off the base year. When modelling the DS by pivoting off the DM they would normally be the same. The most common exception to this would be if fuel costs change between DM and DS, as would be the case when undertaking realism testing (see Section 8.1.2).

See section 4.1.5 for a fuller discussion of pivoting.

6.5.5.2 Using assignment costs (SATURN)

Wherever possible it is recommended that the same generalised cost function is used in the assignment and demand models. Otherwise there may be problems achieving convergence.

If the 'Use Assignment Costs' option is checked then DIADEM will skim the total generalised cost from the SATURN model. Implicitly this means that the same values of time (PPM parameters) and vehicle operating costs (PPK parameters) will be used in the assignment and demand models. Future year PPM and PPK values will need to be adjusted to reflect changes in values of time and fuel costs, as discussed above.

The use of this option is recommended unless there is particular requirement to use different cost functions in the demand and assignment models. This option cannot be used if cost damping is to be applied.

If this option is selected for all car-available variable demand segments then the user can choose between skimming costs on the minimum cost path, or as an average over all used paths. (This choice is made on the Highway Reference Trip/Cost data page. See Section 6.6.4 for more information and advice on the preferred option.) Otherwise only the 'average' option is available.

All money charges specified in the network data files, such as tolls, must be in the same price base in all networks, even if they relate to different modelled years.

6.5.5.3 Units for PT time and fare skims

Unlike highway costs, PT cost components are a user input and DIADEM has no control over which units are used. DIADEM therefore needs to know which units have been used in the input time and fare matrices so that it can calculate generalised costs correctly. Input time skims may be in hours, minutes or seconds, and fare skims may be in pounds or pence

6.5.5.4 Including the full trip costs


For absolute demand models and/or if cost damping is being used it is particularly important that the generalised cost for each zone pair represent the full trip costs, i.e. the costs on the centroid connector must be an accurate representation of the costs of that section of the trip that does not take place on the



main model network. Similarly, on the PT side it is important that fares and times are included so that the full costs are taken into account by the model.

6.5.5.5 Cost damping

Cost damping is explained in Section 4.3.2. Clicking the 'Cost Damping' button brings up the following data input screen:



Parameters are defined by trip purpose and by mode.



The default parameters are such that cost damping does not actually alter the cost compared to the undamped value. This means that if you want to use, say, the 'power function of cost' damping mechanism you only need to change the parameters in that section.

Note that the 'varying non-working time by distance' option should, by definition, not be applied to employer's business trips. Also, it should not be used at the same time as the log plus linear cost method for a given demand segment.

The following restrictions apply to the parameter values:

Table 6.1: Restrictions on values of cost damping parameters

Parameter(s)	Acceptable values
k, μ, δ	>0
d', d _c , d ₀ , ε, γ	\geq 0; if $d' > 0$ then must have $d' = k$
α, n _c	≥0, < 1, $\alpha + n_c$ < 1
β	>0, ≤ 1

Clicking the Reset option will make all parameters revert to their default values and, in effect, turn off cost damping. The following table shows the default values for each cost damping function:

Table 6.2: Parameter values needed to turn off cost damping options

rable 0.2. I arameter values needed to turn on cost damping options		
Damping option	Parameter values to turn off (defaults)	
Function of distance	$k = 1$, $\alpha = 0$, $d' = 0$	
Power function of cost	$\mu = 1, \beta = 1$	
Varying non-working time by distance	$n_c = 0, d_c = 0, d_0 = 1$	
Log plus linear cost	$\varepsilon = 0$, $\delta = 0.1$, $\gamma = 0$	

The four text boxes at the bottom of the screen are used to define the shortest distance for each OD pair. This information is only required if the 'damping by a function of distance' or 'varying non-working value of time by distance' is being used, i.e. if either α or η is changed from its default value of zero. A file should be defined for reference and forecast, for highway and PT trips (the actual file used in each case may be the same).

These files should be in 'TUBA format 2' i.e. comma-separated variable:

origin zone, destination zone, distance (in kms)

6.5.6 Occupancy

Occupancy is used to convert between vehicle trips and passenger trips when calculating mode choice. It represents the average number of private vehicle occupants for the demand segment. It should be greater than or equal to 1. If the input reference highway trips are in units of pcus then the occupancy should be the average number of occupants per pcu unit; if they are in units of vehicles then it should be the average number of occupants per vehicle.



6.6 Page 3: Highway Trip/Cost Data

Page 3: Highway Trip/Cost Data (SATURN version) Figure 6.3: DIADEM : C:\DIADEM\2011DoMin.xml _ | × SATURN C CONTRAM Segmentation | Model Parameters | Highway Trip/Cost Data | PT Trip/Cost Data | PA Model Data | Absolute Model Data | DIADEM Parameters | HADES Data | SATURN Settings | • Define UFS Files for Reference Costs O Define Reference Cost Matrices UFS Files -Matrices 1 AM peak 0000-0300 Select Root Directory • C:\DIADEM\BaseYrAM.ufs c:\diadem\ Browse 01 C:\DIADEM\BaseYrAM.ufs 02 C:\DIADEM\BaseYrIP.ufs 2011DMRefTripsHW Trips 03 C:\DIADEM\BaseYrPM.ufs 04 C:\DIADEM\BaseYrOP.ufs Time SATURN GC Distance Toll Clear Skim Costs Average over all paths C Minimum Cost path only Demand profile for non-HADES segments and time periods : Browse Run DIADEM Help Close

6.6.1 Overview

This page is used to define the highway reference demand and cost data, which is used mainly for incremental demand models. However, reference costs are also needed for absolute demand models with trip ends defined.

For an incremental model the reference data represent a hypothetical situation, i.e. *if* the forecast costs were equal to the reference cost *then* the demand would be equal to the reference demand. In other words it defines a point on the demand curve. However, it is not expected to represent the equilibrium situation for the current scenario; this is because when the reference demand is assigned to the network the output forecast costs will not be the same as the reference costs.



The incremental demand model in DIADEM adjusts the input reference demand according to the differences between the reference cost and the actual forecast costs. This process is know as pivoting (see Section 4.1.3 for more information).

Reference trips should not be defined for demand segments using the absolute logit model. Reference costs *may* be needed, depending on the way the absolute model is set up, but have a different role from when they are used with an incremental model. When trip ends are defined for the absolute model the reference costs are used to produce an initial set of trip matrices to be assigned. They then play no further role in the model.

For the absolute model the reference costs should represent the best guess of what the costs will be in the scenario being forecast. The more accurate the guess the less time DIADEM will take to converge.

There are two main ways of setting up reference data for an incremental model: pivoting off the base year or pivoting off the do-minimum.

Reference trips should be defined by time **period**, reference costs by time **slice**. Trips by time period are converted to trips by time slice in one of two ways:

- For demand segments and time periods which use the HADES model, the conversion is carried out as part of the HADES process.
- For all other demand segments and time periods the conversion is carried out using fixed demand profiles, as defined on the bottom of this page.

6.6.1.1 Pivoting off the base year

When pivoting off the base year the reference costs should come from the validated base year assignment. The reference demand should represent the unrestrained forecast of travel demand in the forecast year being modelled in DIADEM, i.e. assuming no change in costs. In the UK this would typically be obtained by taking the base year validated matrix and increasing it with factors obtained from TEMPRO (for cars and PT passenger travel) and other DfT forecasts for goods vehicles.

For every non-zero cell in the reference trip matrix there must be a corresponding cost in the reference cost file. This may not be the case if, for instance, the reference trip matrix contains OD trips that do not exist in the base matrix. Therefore zoning systems in the base and forecast networks must be the same, even if some zones do not have any trips in the base matrix.

6.6.1.2 Pivoting off the DM

Pivoting off the DM requires that DIADEM has already been run for one scenario for the year under consideration. Typically the DM would have been pivoted off the base year (see above). When running DIADEM for the do something (DS) in the same year it is possible to pivot off the DM rather than the base year. In this case the reference demand should be the trip matrix output by the DM DIADEM run and the reference costs from the assignment of that matrix to the corresponding DM network.

The advantage of this approach is that DIADEM should be starting at a point closer to the DS equilibrium and thus converge more quickly.



WebTAG recommends pivoting off the DM when modelling the DS.

6.6.1.3 Pivoting summary

The following table summarises how the reference data can be obtained according to whether the base year or DM is used as the pivot point:

Pivot	Reference costs	Reference cost coefficients	Forecast cost coefficients	Reference demand
Base year	Base year costs	Base year coefficients	Forecast year coefficients	Unrestrained growth from base year to forecast year applied to base year matrix
Do-minimum	DM costs from converged DIADEM run (same forecast year)	Forecast year coefficients	Forecast year coefficients	DM demand from converged DIADEM run (same forecast year)

Innumerable pivoting options are possible but the above are the most common.

6.6.2 Important note on reference costs

It is important that reference costs for incremental models are defined for all origin/destination/time period/demand segment/mode combinations that have non-zero trips in the reference trip matrix. The most common reason for not doing this occurs when the forecast network has additional zones that are not in the networks used to provide the reference costs. All networks in DIADEM (reference and forecast, PT and highway) must have the same zoning system.

An example of this is as follows. Suppose we are pivoting off the base year (i.e. reference costs are skimmed from the base year assignments) and additional development zones are added to the forecast networks. In this case no reference costs are available to and from the development zones and the demand model calculations will be incorrect. The solution in this case is to make sure the development zones are included in the base year network, even if there are no trips in the base year matrix. This will ensure that reference costs can be skimmed for all necessary movements.

When used with absolute demand models, reference costs must be available for every zone pair.

6.6.3 Entering data

Highway reference trip data must be defined for each car-available demand segment and time period for which an incremental model is used. Potentially there are a large number of combinations of demand segments and time periods so DIADEM uses a file naming convention to reduce the data entry requirements on this screen. Reference trip data file names for OD-based modelling have the format:

????_TX_DS Y.dat

for time period X and demand segment Y. ???? is any user-defined string; X and Y are integers.



Note that the above data is defined by time **period** then split by time **slice** using either HADES (if selected) or user-defined profiles (otherwise).

For PA-based modelling the reference trips should be in the form of a 24 hour PA matrix, therefore the file name excludes any reference to the time period:

????_DSY.dat

Note that in the PA reference matrix a value of 1 gives two OD trips: one from the production zone to the attraction zone and another in the reverse direction.

Note that Y refers to the number of the demand segment as used in the drop down box on the Model Parameters page. The numbering of demand segments is determined by the order in which they are added to the Segmentation page. The demand segment number for each purpose/person type combination can be viewed in the Demand segment drop-down box on the Model Parameters page.

Rather than specifying the file name separately for each individual demand segment and time period combination it is only necessary to define the 'root' name (???? in the above examples) and the directory where the files are located. For example suppose the reference trip files take the form 'reftrip_TX_DSY.dat' then just 'reftrip' is entered in the 'Trips' box on this screen. reftrip_T1_DS3.dat would be the reference trip matrix for time period 1, demand segment 3.

The format used in these files is a comma-separated variable format with three numbers on each line representing the origin zone, destination zone and matrix value. For example:

101,102,23.5 104,103,42.1

defines a value of 23.5 from zone 101 to zone 102 and a value of 42.1 from zone 104 to zone 103. This is the same as TUBA format 2.

It is important to note that in the SATURN version of DIADEM zone names rather than sequential numbers should be used in all input matrices.

DIADEM relies on the reference trip matrix to build up a complete list of zone names. Therefore each zone name should appear at least once in the reference trip matrix. If, for some reason, there are zones with no trips to or from them in the reference matrix then the simplest thing to do is to add them as an intra-zonal OD pair with zero trips, e.g. for zone 101 put

101,101,0

in the reference trip matrix file.

OD trip matrices should be defined in units of vehicle or pcu trips per hour. PA matrices should be total vehicle or pcu PA trips over the 24 hour period (remembering that a value of 1 in a PA matrix cell implies one outbound trip and one return trip in 24 hours). If vehicle trips are used then the occupancy on the Model Parameters page should be occupancy per vehicle; if pcu trips are used then it should be occupancy per pcu.



There are two available methods for entering reference cost matrix (SATURN GC, time and distance) data:

Method 1:

This is similar to the way reference trip matrix data is entered. Reference cost data must be defined for each user class and time period. As for reference trips, a file naming convention is used as follows:

????_TSX_UC Y.dat

for time slice *X* and user class *Y*. (Note that OD costs should be defined in this format even for demand segments using PA modelling; DIADEM will calculate PA costs from OD.)

The root ???? is defined separately for SATURN GC, time, distance and (optionally) toll matrices. Note that reference trips are defined by demand segment and reference costs by user class.

For example, suppose the root is defined as 'refTime' then DIADEM would expect the file refTime_T1_UC2.dat to contain reference times for time period 1, user class 2.

The units used should be hours for SATURN GC and time, kilometres for distance, pence for tolls.

Method 2:

This method is simpler than Method 1 and reduces the risk of errors being introduced due, say, to skimming costs in incorrect units. For each time slice a SATURN UFS file must be defined, from which DIADEM will skim the reference costs automatically. For instance, if you are pivoting off the base year then you would specify the UFS files for the base year assignment. If you are skimming an average over used paths (see section 6.6.3) the corresponding SATURN output UFC file(s) must be in the same directory as the UFS file(s), but do not need to be defined by the user.

Reference costs and trips for non-car available demand segments are specified on the PT Trip/cost data page.

6.6.4 Skimming costs with SATURN

There are two options for skimming costs from SATURN assignments:

- Averaging (flow-weighted) over all used paths (so-called 'forest' skims), and
- Skimming the current minimum cost path only

In a perfectly converged assignment the generalised costs skimmed using the two methods are identical. However, individual components (time, distance, toll) are unlikely to be.

The minimum cost path option is recommended, provided that a) the assignment converges very well (e.g. assignment gap of 0.1% or less) and b) the demand model uses the same cost function as the assignment (which also precludes the use of cost damping). Indeed this option will be greyed out unless the latter condition is true for all variable demand car-available demand segments.



In other situations the 'average' option should be selected. When using this option, it is essential that the SAVEIT assignment carried out in SATURN is as accurate as possible, to minimise the amount of noise in the costs passed to DIADEM. This usually requires setting the SATURN parameter NITA_S sufficiently high. For more information see Section 15.23 of the SATURN manual (version 10.9).

Skimming average cost paths can take much longer than minimum costs.

If the reference cost matrices are input manually into DIADEM (rather than letting DIADEM skim them from UFS files) they should be consistent with the skim method selected, e.g. if average skims are selected then the reference costs should represent average skims.

6.6.5 Demand profile for non-HADES segments and periods

This file is only needed if there is more than one time slice per time period.

Since the main demand model operates at the time period level, DIADEM needs a way to disaggregate demand by time period from the demand model to demand by time slice for assignment.

For HADES demand segments and time periods this is done using the HADES arrival time choice model.

For other demand segments and time periods this is done with user-defined profiles. These are specified via an input file that is defined on this section of the page. The file should be in comma-separated variable (csv) format as follows:

origin zone, destination zone, demand segment, time period, proportion of demand in first time slice within the time period, proportion of demand in second time slice in period, etc..

The first four values are integers; the rest are real numbers greater than or equal to zero and less than or equal to one.


The sum of the proportions for a given origin, destination, demand segment and time period must equal 1.0

Data must be defined for all combinations of origin, destination, demand segment and time period for which HADES is not used.



6.7 Page 4: PT Trip/Cost data

Figure 6.4: Page 4: PT Trip/Cost data



This page is only used if mode choice, or non-car available demand segments, are being modelled.

DIADEM assumes that PT forecast costs (times and fares) do not change in response to changes in PT or highway demand, unlike highway costs. PT forecast costs are therefore fixed for the duration of the DIADEM process, whereas DIADEM automatically skims forecast highway costs from the latest assignment. PT reference and forecast costs, which may be different, must be input by the user.

Reference trips and reference and forecast times must be defined for all car available demand segments for which mode choice is being modelled, and for all non-car available demand segments, for all time periods.

Definition of reference and forecast fares is optional. However, it is recommended that they are always defined unless the reference and forecast fare cost coefficients are the same and the reference and forecast fares themselves are the same. All fares must be entered in the same price base (consistent with that used elsewhere, e.g. values of time), even if they relate to different modelled years.



Please see Section 7.6.1 for an explanation of reference costs and demand. The forecast times and fares are the times and fares for the scenario being modelled by DIADEM.

By definition the PT reference demand for car-available demand segments should exclude any trips that are captive to public transport.

DIADEM is designed to be used with outputs from any PT assignment package so a simple matrix format is used and it is assumed that each matrix file contains data for only one data type, demand segment and time period. The format used is a comma-separated variable format with three numbers on each line representing the origin zone, destination zone and matrix value. For example:

101,102,23.5 104,103,42.1

defines a value of 23.5 from zone 101 to zone 102 and a value of 42.1 from zone 104 to zone 103. This is the same as TUBA format 2.

The files are defined as follows: select a data type from the drop down menu and specify a file name. Then select to which time period(s) and demand segment(s) the data applies, click on the appropriate check boxes. It is expected that cost data will quite often apply to more than one demand segment, and possibly time period, but it is unlikely that trip data will. It is possible that the same cost data apply to both the reference and forecast cases. In this situation the file only needs to be defined once provided the 'Use reference costs as forecast costs' box is checked. Having done all that click the 'Use' button – a summary of the input data then appears in the box in the bottom half of the page. Note that facilities to edit data once it appears in this box are currently limited, although lines can be deleted by right clicking on them and choosing 'Delete Selected' or 'Delete All'.

OD trip matrices should be defined in units of passengers per hour. PA matrices should be total passenger PA trips over the 24 hour period (remembering that a value of 1 in a PA matrix cell implies one outbound trip and one return trip in 24 hours).


PT time matrices can be generalised time matrices and include components such as wait time, walk time and transfer penalties which may have been weighted. Some PT packages include fares when skimming generalised time. These can be used in DIADEM as long as care is taken that there is no double counting with the fare matrices.

PT time matrices can be in hours, minutes or seconds and fare matrices may be in pounds or pence. The units used should be specified in the Generalised Cost Coefficients section of the Model Parameters page.



6.8 Page 5: PA Model Data

Figure 6.5: Page 5 : PA Model Data



This page is used to define three file names related to PA/tour demand modelling. The files should contain the following data:

File	Contents
Outbound proportions	The proportion of all trips that go out in each time period, defined by production and attraction sector, demand segment, and mode. These proportions are typically obtained from local survey data.
Return proportions	As outbound proportions, but for the return trips.
Tour proportions	An initial estimate of tour proportions, which will then be adjusted using the above data. Defines the proportion of trips going out and returning in each combination of outbound and return time periods, by origin and destination sector, demand segment and model. Typically these will based on the data file supplied with DIADEM (which comes from an analysis of NTS data) but in some cases may be based on local survey data. Note that the former assumes all zones are grouped together into a single sector.

The files need only contain data for demand segments for which PA-based demand modelling is being used, whether it is an incremental or absolute model.



For a description of PA modelling in DIADEM and more details of how the data in these files is used please see section 4.2.

6.8.1 File formats

All files are in comma-separated variable format as follows:

Outbound and return time period proportions:

production sector, attraction sector, demand segment, mode, proportion in period 1, proportion in period 2, etc

Initial tour proportions:

production sector, attraction sector, demand segment, mode, outbound time period r, proportion in going out in r returning in period 1, proportion going out in r returning in period 2, etc

Notes:

For modes, mode=1 represents highway, mode=2 is public transport. When this data is used with an absolute model with mode choice then the proportions should not be segmented by mode; this is indicated by putting mode=0.

All proportions should be between 0 and 1 (inclusive).


For a given demand segment and mode the sum of the outbound proportions over all time periods should equal one. Similarly for the return time periods.

For a given demand segment and mode the sum of the initial tour proportions over all outbound and return time periods should equal one.



6.9 Page 6: Absolute Model Data

Figure 6.6: Page 6: Absolute Model Data



This page is used to define various file names containing data for the absolute demand model. The data falls into two categories: trip data and model constants (mode constants and size variables).

Trip data may be defined in one of two ways: as trip ends, or as a full initial guess matrix.

6.9.1 Initial guess

Defining the initial guess requires full trip matrices by demand segment and mode. These are specified in a similar way to the reference trip matrices used for the incremental model, i.e. OD matrices by time period for OD-based models and 24 hour PA matrices for PA-based models. The initial guess is used as the matrix to be assigned on the first iteration by DIADEM. It is also used to calculate the trip end constraints to be applied during the model. Definition of the initial guess matrix is very similar to defining highway reference trip data:

For all PT data and SATURN highway data:



OD trips:

????_TX_DS Y.dat

for time period X and demand segment Y. ???? is any user-defined string; X and Y are integers.

For PA-based modelling the initial guess trips should be in the form of a 24 hour PA matrix, therefore the file name excludes any reference to the time period:

????_DS Y.dat

The root of the file name (????, which need not be limited to four characters) is defined separately for HW and PT initial guess in the appropriate text box.

6.9.2 Trip ends

When applying an absolute model a full estimate of the trip matrix may not be available, in which case just the trip ends can be defined instead. DIADEM then needs to distribute the trip ends to get a matrix suitable for the first assignment. It does this using reference costs defined on the previous highway and PT data pages. Note that the trip ends may be total trip ends over all modes, or separately for each mode, depending on the modelling options chosen:

Responses modelled for demand segment	Interpretation of trip ends
Mode choice modelled	Total over all modes
No mode choice	Single mode (highway if car available, PT if no car available)

Form of distribution model	Trip ends required
OD, origin constrained	Origin only
OD, destination constrained	Destination only
OD, doubly constrained	Origin and destination
PA, singly constrained	Origin only
PA, doubly constrained	Origin and destination

6.9.3 Constants

Definition of constants is optional. For the distribution model it is possible to define size variables for origins (for destination-constrained models) or for destinations (for origin-constrained models). It is also possible to define K factors. Note that size variables are ignored for doubly-constrained models.

For the mode choice model mode constants can be defined.

For more details on the use of constants refer to Section 4.1.2.



6.9.4 File formats

All files are in comma-separated variable format (except highway initial guess for CONTRAM) as follows:

Initial guess uses the same file format and file naming convention as reference highways trips (SATURN) version:

origin zone, destination zone, trips

(trips are trips per hour for OD, 24 hour total for PA).

Trip ends (PA modelling):

zone number, demand segment, trip end total

Trip ends (OD modelling):

zone number, demand segment, trip ends in time period 1, trip ends in time period 2, etc.

Size variables:

zone number, demand segment, size variable

K factors:

origin zone, destination zone, demand segment, K factor

Mode constants:

mode, demand segment, value of constant

Notes:

Origin trip ends are only required for demand segments using an origin or doubly-constrained model.

Destination trip ends are only required for demand segments using a destination or doubly-constrained model.

The units used for size variables and K factors are irrelevant – it is only their relative value that is important.

Size variables and K factors must be non-negative. A value of zero will result in no trips for the zone or zone pair in question.

Any size variables or K factors not specified in the files are assumed to be 1.

For modes, mode=1 represents highway, mode=2 is public transport.


The mode constants should be in the same units as the generalised cost function. This is usually generalised minutes.



Mode constants only need to be defined for one mode – it is only the difference in the constants between modes that matters.

6.10 Page 7: DIADEM Parameters

Figure 6.7: Page 7: DIADEM Parameters



This page defines settings related to the algorithms used to achieve convergence between supply and demand. Depending on the model set up, two levels of convergence may be relevant.

6.10.1 Main demand-supply loop

Three algorithms are available from the drop down menu:

 Fixed Step Length (FSL): this is usually the best performing algorithm, achieving the required level of convergence in fewest iterations.



- Method of Successive Averages: this is the traditional 'slow but sure' method. Research to date shows that it will take a very long time to reach acceptable convergence levels.
- Algorithm 1: this performs like FSL in the early iterations, but can then use up a lot of run time without making further progress towards convergence.

Depending on the algorithm selected a number of parameters also need to be defined in the Algorithm frame. It is recommended that the default values are used to start with. The step length for FSL can be tweaked to improve run times and convergence, as explained in <u>Section 8.3</u>. For an explanation of the role of these parameters please see Appendix A.

The Convergence frame is used to specify the stopping criteria for DIADEM:

- Maximum Iterations: for MSA and FSL there is one assignment per iteration. For Algorithm 1 there may be more than one, particularly as equilibrium is approached.
- Maximum Flow Change: close to convergence DIADEM may make very small changes in the demand matrix which are virtually imperceptible to the assignment. When the largest change in cell values is less than the value of this criterion DIADEM will stop.
- Absolute Gap: DIADEM will stop when the absolute gap falls below this value. The value achievable is very dependent on the size of the problem being solved so it is usually advisable to set this to zero.
- Relative Gap: DIADEM will stop when the relative gap falls below this value. (See Section 1.5 of WebTAG Unit 3.10.4 (Variable Demand Modelling Convergence Realism and Sensitivity) for advice about convergence in variable demand models, for the formula used to calculate the gap and for the appropriate value for this parameter.)

6.10.2 HADES-assignment loop

This section will be greyed out unless HADES has been selected for at least one demand segment.

The FSL and MSA algorithms are also available for the HADES-assignment loop. In addition, the Social Pressure algorithm can be used. The latter is described in Section 4.2.3.5.

The stopping criteria are similar to the main demand-supply loop, but note that the gap is the HADES gap as defined in Section 4.2.3.5.

6.10.3 Sector file

This page can also be used to define a sector file. This is mandatory if PA-based modelling, HADES, or spatial segmentation is being used. A sector is a group of zones and the file contains a correspondence list between model zones and sectors.

The file should be in comma-separated variable format, with one line for each model zone:


zone number, sector number



Zone and sector numbers must be positive integers. It may help to avoid confusion if there is no overlap between zone numbers and sector numbers. For example, if the highest zone number is 935 the sector numbering could start at 1001.

6.11 Page 8: HADES Data

Figure 6.8: Page 8: HADES Data



6.11.1 HADES log file

The HADES log file is described in Section 7.1.4. It contains very detailed information, and, for large networks, can take up a lot of disk space. It is recommended that the "Output HADES Log File" option is selected, unless the output log file is so large that it causes problems.

6.11.2 Selection of HADES time periods

The selection of which demand segments which use HADES was made on the Model Parameters page. Here, it is necessary to define to which time periods HADES is applied.



The theory behind HADES is based on the idea of a preferred arrival time at the destination and was developed to explain the behaviour of commuters in the AM peak. Arguably, it is less applicable to other time periods. This section therefore allows the user to choose to apply HADES in certain periods only.

6.11.3 Interpretation of assignment time slices

Assignments may be assumed to be based on either trip departure times or trip mid-point times. The choice is made by selecting the appropriate radio button. For CONTRAM it should always be departure times; for SATURN it is up to the modeller, depending on what was assumed when building the model.

6.11.4 Input files containing HADES parameters

Most HADES-related data is defined via four user-defined input files. These files are in comma-separated variable (csv) format and contain the following data:

- Definitions of arrival time windows
- Scheduling parameters, by destination sector and demand segment
- The profile of demand by preferred arrival time window, by origin, destination and demand segment
- Pre and post-peak travel durations by assignment user class

6.11.4.1 Arrival time window definitions

This file contains the definition of the arrival time windows. The time period being modelled should be divided into a series of contiguous arrival time windows, in a similar way to the division of the modelled period into a series of assignment time slices. However, as explained below, the period covered by the arrival time windows will usually need to be longer than that covered by the assignment.

Every trip in the model is allocated to one of these windows, as its preferred arrival time (PAT).

Several sets of windows may be specified. Different demand segment/destination sector/time period combinations may each use a different set.

It is good practice for a single set to apply only to a single time period, so as a minimum there would be one set of windows for each time period. However, it is also possible to define a single set of windows covering the whole day and to use that set for each time period (setting demand in some windows to zero, as appropriate for the time period.)

The set to be used for each demand segment, destination sector and time period is defined in the scheduling parameters definition file (see below). It is expected that for the vast majority of applications a single set of arrival time windows for each time period should be sufficient.

The format for each row in the file is:

ID for arrival time window set, start of first window, start of second window, ...start of last window, end of last window

The ID should be a unique integer identifying this set (i.e. the same ID cannot be used on any other row in the file). Times are in *hhmm* format, for example 0830 or 1115. Times should be strictly increasing from left

DIADEM User Manual Version 5.0 (SATURN)



to right. The format ensures that the windows are contiguous and non-overlapping. There is no practical limit on the number of windows within each set.

The following example defines a set of four windows with ID=1, with the start of the first window at 0800 and the end of the last window at 0900. The times covered by the four windows are 0800-0820, 0820-0830, 0830-0840 and 0840-0900:

1,0800,0820,0830,0840,0900

Arrival time windows within a given set may be of different lengths. The different sets are, in effect, independent. Each set may start and finish at different times and the durations of the windows differ between sets. However, the appropriate start and end times of the set will need to be set appropriately for the time periods being modelled, as discussed below.

The period covered by the arrival time windows clearly needs to be related to that covered by the assignment. For example if the arrival time windows go from 0700-1000 and the assignment covers 1600-1700 then no flow will get assigned.

The arrival time windows should start no later than the arrival time of a trip departing at the beginning of the assignment period. This is most easily handled by making sure that the arrival time windows and the assignments start at the same time.

At the other end, the arrival time windows should finish no earlier than the arrival time of a trip departing at the end of the assignment period. The end of the last arrival window should, ideally, be no earlier than the end of the period covered by the assignment plus the duration of the longest trip in the network.

If these conditions are not met then it is likely that the assignment will be missing trips, i.e. in reality, the assignment period includes trips which arrive outside of the period defined by the arrival time windows, but because these are not represented in the HADES model they will not be included in the assignment. A warning will be issued to the .log file if this is the case.

6.11.4.2 Scheduling parameter definitions

This file is used to define, for each destination sector, demand segment and time period, which set of arrival time windows to use, and the β (early) and γ (late) scheduling parameters.

Note that within HADES in DIADEM, generalised costs are expressed in time units. The β and γ parameters in this file should therefore be expressed relative to a unit of travel time. For example a β value of 0.3 would indicate that 1 minute of early arrival has the same cost as 0.3 minutes of travel duration.

The format for each row in the file is:

destination sector, demand segment, time period, early arrival parameter (β), late arrival parameter(γ), arrival time window ID

There should be a row in the file for each destination sector and demand segment for which the HADES demand model has been selected.



The destination sector must be an integer and must have been defined in the sector definition file that is specified on the 'DIADEM parameters' page (Section 6.10.3).

 β and γ must be non-negative.

The arrival time window ID must have been defined in the arrival time window definitions file (as described in 6.11.4.1.

The following example defines that destination sector 2, demand segment 5, time period 1 should use arrival time windows with ID=1, with β =0.3 and γ =0.8.

2,5,1,0,3,0,8,1

Table 6.3 is taken from the Good Practice Guide for the previous version of HADES (Mott MacDonald, 2004) and presents a summary of evidence for the β and γ parameters. These are for one minute of early or late arrival, relative to one minute of travel duration. The table also includes a column for 'Lateness penalty'. This is a fixed cost of late arrival, regardless of exactly how late that is. Note that this is **not** included in the HADES costs within DIADEM.

Table 6.3: Summary of the evidence on the valuation of schedule delay.

Source	Early arrival (β)	Late arrival (γ)	Lateness penalty
Small (1982)	0.61	2.40	5.47
Polak and Bates (1996)			
Arrival constrained	0.13	0.64	
Arrival+departure constrained	0.16	0.42	
No constraints	0.02	0.25	
Whole sample	0.13	0.43	
Polak (1991 – Trondheim)			
Fixed hours commuters	0.66	1.02	
Flexible hours commuters	0.61	0.77	
Other	0.78	0.52	
All	0.52	0.49	
Polak (1994 – LCC dataset)			
Commuters	2.81	3.48	
Employers' business	0.55	1.40	
Shopping and Leisure	0.66	0.40	
Wardman (1998 – average of 13 European studies)	0.64	0.69	7.4

Source: Mott MacDonald (2004)

6.11.4.3 Demand profile by PAT window

This file defines the demand profile for each Preferred Arrival Time (PAT) window, for each origin-destination (OD) zone pair and demand segment, i.e. the proportion of travellers within each PAT window. It is used to split the total demand by time period to demand by PAT window. Depending on which other demand model responses have been selected, the total demand may be the output from the main demand model, or a fixed user-supplied value.

DIADEM User Manual Version 5.0 (SATURN)



The format is:

origin zone, destination zone, demand segment, time period, proportion of demand for preferred arrival time window 1, proportion of demand for preferred arrival time window 2, etc.

The first four values are integers; the rest are real numbers greater than or equal to zero and less than or equal to one.

The sum of the proportions must not exceed 1.0, otherwise DIADEM will issue an error message and stop. If the sum of proportions is less than 1.0 then a warning message will be issued to the log file but DIADEM will continue to run; this is to allow the situation where the defined trip numbers represent the demand over a longer period than that defined by the arrival time window (though this unlikely to be appropriate where HADES is being used in conjunction with a mode choice or distribution model).

Note that different OD pairs, demand segments and time periods may use different sets of arrival time windows, and that the number of windows within each set might be different. This means that the number of items on each row of this file may vary.

Obtaining data on preferred arrival times is one of the biggest challenges in using HADES. Software has previously been developed for DfT for inferring preferred arrival times from actual arrival times, but that is not on general release.

An alternative approach that has been suggested is to assume that preferred arrival times equal actual arrival times in the model base year. HADES can then be used in forecasting (with or without a scheme) to give a broad indication of how arrival and departure time profiles might change in the future.

6.11.4.4 Pre and post-peak travel times

Pre and post-peak travel times are defined in this file. For an explanation of their use see Section 4.2.3.5 (specifically the section discussing the interpolation of travel durations by arrival time).

The format is:

origin zone, destination zone, user class, time period, pre-peak travel duration, post-peak travel duration

The first four values are integers; the last two are real numbers greater than zero.

Travel durations should be specified in minutes.


Note that durations are defined by assignment user class, not by demand segment. However, they are applied by demand segment, with the demand segment to user class correspondence (defined on the Segmentation page) used to identify which user class values to apply to a given demand segment.

These travel times are defined by time period. HADES is applied independently to each time period, Travel times within each period are taken from the assignment model, but travel times before and after the period must be defined by the user.



6.12 Page 9: SATURN Settings

Figure 6.9: Page 9: SATURN Settings.



This page contains settings relating to the way SATURN should be run.

SATURN may be run in 'quiet' mode, which switches off all screen output when running SATURN modules such as SATALL. This means that while DIADEM is running there is little visible indication of progress, other than a small DIADEM progress window. Windows Task Manager can be used to monitor program activity.

The second box specifies the path where the SATURN executable files (.bat, .exe) are located. If the default options were used when installing SATURN this will usually be C:\SATWIN\XEXES. If more than one version of SATURN is installed then this should be the location of the executable files for the version that should be used for this particular DIADEM run. The last chosen location is remembered by DIADEM and will be used as the default for new control files.



It is possible to set up DIADEM so that assignments for different time periods are run in parallel, provided appropriate hardware is available (minimum of a dual core processor). This can greatly reduce run times, for example running four SATURN assignments in the same time it takes to run one. This page will report how many processors the operating systems reports are available. It is recommended that the number of assignments set to run in parallel should not exceed this value – there will be no run time advantages in doing so and there is a risk the whole DIADEM run may take longer. Run time reductions from this option are likely to be small if you are using the multi-core version of SATURN.

For this option to work it is necessary that the file SAT10KEY.DAT is read-only. DIADEM will look for this file in ..\DAT\ folder (relative to the location of the exes) and offer to make it read-only if it is not already.

Running assignments in parallel does not apply if the PASSQ option has been selected on the Segmentation page – the assignments must then be run one after the other so that the correct queues can be passed from one time period to the next.

NB: If you are using the option to run SATURN assignments in parallel then you must put the SATURN network files for each time period in a separate directory. This will reduce the risk of file opening errors, with different SATURN programs trying to access the same file at the same time.

6.13 Running DIADEM

Once all the data has been set up the control file should be saved. The DIADEM process is started by clicking on the 'Run DIADEM' button at the bottom of the window. After a few moments an assignment will start. When the first assignment finishes a small DIADEM progress window will appear, reporting the iteration number and the current value of the relative gap function.

Depending on the convergence criteria, a number of further assignments will be carried out. If any errors arise during the process a window will appear with an error message. Otherwise DIADEM will have successfully completed when all the assignments have stopped. Note that for very large models there may be a gap of up to a few minutes between assignments.

When DIADEM has finished a message will appear saying 'DIADEM run completed.'

6.13.1 Batch mode

Several DIADEM control can be set up to run consecutively, without any user intervention. To do this create a plain text file. Each line of this file should contain the name of a control file, with the full path and including the .xml extensions, e.g.

c:\diadem\test1.xml c:\diadem\test2.xml etc....

In the user interface go to File>Batch File and open the above text file. The first control file will start running immediately. Any error messages will be written to a log file.



7. DIADEM output

7.1 Output files

There are various DIADEM output files: a series of demand files, a log file and a summary convergence file. In addition there will be a series of files produced by the assignment software. In the following descriptions 'root' represents the name of the DIADEM control file; it is used in the names of several output files.

7.1.1 Checking results

The following sections describe the DIADEM output files in more detail. Briefly, the following should be checked for any DIADEM run:

- Deal with any error messages issued during the run.
- Look in the log file to see if there are any warning messages and deal with these as appropriate.
- Look at the convergence file to make sure DIADEM has reached an adequate level of convergence
- Check that the travel behaviour is consistent with the scenario being modelled. For the DM it would be sensible to compare the output trip matrices with the reference trip matrices; the DS output trip matrices can be compared with the DM trip matrices. Results to look at include:
- Total trip numbers are reported in the convergence file; these will only change if the trip frequency response is modelled or an elasticity model is used.
- Total trip numbers by mode and time period can be calculated from the output trip matrices. These can be used to check the mode and time period choice responses are reasonable.
- The trip matrices can be used in a trip length distribution analysis.

7.1.2 Log file

This file is called root.log.

This file contains a log of the timing of each step of the DIADEM process. It also includes any warnings that are produced. Note that these warnings are not serious enough to cause the DIADEM run to fail, but should be investigated further (see Section 7.2 for more on warning messages).

Note that this file is appended to rather than replaced, i.e. if the same DIADEM control file is run twice then the log will contain output relating to both runs – running it a second time does not delete the output from the first.



7.1.3 Convergence files

7.1.3.1 Main demand-assignment loop

A summary convergence file in comma-separated variable format (extension _results.csv) is produced. The root of the file name will be the same as the DIADEM control file. This file contains the following information for each subiteration:

- Step length (see Appendix A: for explanation)
- The maximum change in a matrix cell value (compared with the matrix produced at the end of the last main iteration)
- Objective function value (see Appendix A for explanation)
- The absolute and relative gap values (see WebTAG for formulae)
- Statistics on the stability of costs at the matrix cell level (relative average absolute difference, average absolute difference, root mean square difference, % of cells changing by less than 5%)
- Statistics on the stability of trip numbers at the matrix cell level (same measures as cost stability)
- The total trips in the system (this should be constant unless an elasticity or frequency model is being used)
- The total cost in the system

Note that some statistics are only output for the last subiteration in each main iteration.

Advice on appropriate levels of convergence can be found in Section 1.5 of WebTAG <u>Unit 3.10.4</u> (Variable Demand Modelling - Convergence Realism and Sensitivity). Note that the trip matrix closest to equilibrium (the one with the minimum gap) may not be the final trip matrix output by DIADEM. The convergence results should be used to identify the best iteration/subiteration and the corresponding trip matrix should be used as the basis of subsequent analysis and appraisal. As described in the following section, DIADEM automatically identifies the trip matrices from the best iteration/subiteration (defined as the one with the lowest relative gap).

If the best trip matrices are not the ones from the final subiteration then it will be necessary to reassign the best matrices to obtain cost matrices, link flows etc. for subsequent analysis and appraisal.

7.1.3.2 HADES-assignment loop

If HADES is being used, a summary convergence file for each HADES-assignment loop is produced for each time period. The loop number and the time period are included in the file name which has the format <root>_IterX_TY_HADES_results.csv. This is very similar to the main results.csv file, but it reports the HADES gap value for each iteration of the HADES-assignment loop, and does not report an objective function value or the absolute gap value.



7.1.4 HADES log file

This is an extra file in csv format containing the following information for every iteration, origin, destination, demand segment, preferred arrival time and actual arrival time:

- Travel duration
- Total generalised cost
- Number of trips

The scheduling cost can be calculated by subtracting the travel duration from the total generalised cost.

As with the HADES-assignment loop convergence file, a separate file is produced for each time period and iteration of the main demand-assignment loop.

This file can get quite large, so its output can be suppressed on the HADES Data page when setting up the DIADEM run.

7.1.5 Trip matrices

7.1.5.1 Highway

All intermediate OD trip matrices produced by DIADEM are saved with a file name of the form *root_*HWtrips_TX_DSY_M_N.dat where X is the time period, Y is the demand segment, M is the main iteration number and N is the subiteration number. The matrices from the best iteration are copied to *root_*HWtrips_TX_DSY_best.dat. The units used are vehicle or PCU trips per hour (whichever was used for the input matrices).

For demand segments that use a PA demand model, PA trips are output for each iteration in the form of 24 hour PA and PA tour matrices. A 24 hour PA matrix is produced with a file name of the form *root_HWtrips_DSY_M_N.dat*. Tour matrices are produced with file names of the form *root_HWtrips_ToutX_TretZ_DSY_M_N.dat* where X is the outbound time period, Z the return time period. The units used are absolute vehicle (or PCU) numbers. Note that the 24 hour PA matrix is just the sum of the corresponding tour matrices over all outbound and return time periods.

The UFM matrices from the last subiteration, as used in the final assignment, are called UFM_TX.UFM (all assignment user classes stacked together).

7.1.5.2 Public transport

PT trip matrices are output only for those demand segments for which mode choice is modelled. OD trip matrices are called *root_*PTtrips_TX_DSY_M_N.dat where X is the time period, Y is the demand segment, M is the main iteration number and N is the subiteration number. The matrices from the best iteration are copied to *root_*PTtrips_TX_DSY_best.dat. The units used are passenger trips per hour.

For demand segments that use a PA demand model, PA trips are output for each iteration in the form of 24 hour PA and PA tour matrices. A 24 hour PA matrix is produced with a file name of the form $root_PTtrips_DSY_M_N.dat$. Tour matrices are produced with file names of the form $root_PTtrips_ToutX_TretZ_DSY_M_N.dat$ where X is the outbound time period, Z the return time period. The units used are absolute passenger numbers.



7.1.6 Other files

In addition to the files described above other files may be produced by the assignment software as follows:

Skim cost matrices from the final assignment (tim_TX_UCY.dat, dis_TX_UCY.dat, cst_TX_UCY.dat).

UFN, UFC, UFS, LPN, and LPT files are created during the assignment (carried out using the SATURN module). The LPT file may provide useful information if DIADEM stops due to a failed SATURN assignment.

LOG, LPX. UFM files are created by the MX module, which is used to build UFM files from ASCII files output by DIADEM.

LOG, LPL, DAT files (cst*.dat, tim*.dat, dis*.dat) are created by SATLOOK, which is used to skim cost matrices (the DAT files) in ASCII format from completed assignments.

Note that very large numbers of LOG files (MX*.LOG, SATLOOK*.LOG) may be produced. It is usually safe to delete them.

7.2 Dealing with error and warning messages

7.2.1 Overview

Error messages in DIADEM will usually appear in their own window and will cause the program to stop before it has successfully completed.

Warning messages will appear in the log file. They do not prevent DIADEM running to completion, but may indicate problems with the input data that may mean the results are unreliable. Some of the more common messages are discussed below. For more help with these and any other messages please contact DIADEM technical support.

7.2.2 'Division by zero in elasticity demand function calculation' (error)

This message appears in a pop-up window and will include information on the origin, destination, demand segment, and time period concerned. It will usually occur just after the first assignment. It can only appear when an elasticity model is being used with a non-zero γ parameter. DIADEM will report this message if either the reference or the forecast cost is zero.

This is usually a result of not setting the 'Assign zero packets' parameter to TRUE.

This will usually be because the reference trip matrix includes intra-zonal trips; the skimmed cost will be zero for these trips. Because intra-zonal trips are not assigned they do not affect the costs for other trips and can safely be removed from the reference trip matrix.

It may also be a result of centroid connectors being defined in such as way as to allow OD routes to take place solely on connectors and to have no time or distance.



7.2.3 'MatrixFile::read Cannot open file name for input' (error)

This usually occurs very shortly after clicking the 'Run DIADEM' button. It is because a path has not been specified correctly, a specified file does not exist or a particular file has not been specified at all.

It can also occur later in the DIADEM run as a result of a failure to skim costs from an assignment. Look in the SATLOOK .lpl files for clues, or SATALL .lpt files if the assignment itself failed. Also, see Section 8.2.5 for likely causes of this in SATURN.

7.2.4 'Warning: N origin/destination/demand segment/ time period combinations have highway trips but no PT trips' (warning)

This message will appear if there are zero PT trips but non-zero highway trips (or vice versa) in the reference matrices for a particular origin/destination/demand segment/ time period combination. In this situation the mode choice model can still be applied but it will not model any change in mode share for that particular combination, i.e. it is fixed at 100% for one mode.

7.2.5 Spawn of SATURN process returned error code XXXX (error)

If this occurs shortly after clicking 'Run DIADEM' and there is no evidence of SATURN being run then it is likely that DIADEM cannot find the SATURN program files. Check that the path to the SATURN executable files that you defined is correct.

If this occurs later in the DIADEM run and SATURN is being run then it indicates a failure in one of the SATURN modules used by DIADEM. The DIADEM error message will often be preceded by a SATURN error message. In this case check the LP file from the latest SATURN module to be run for information on the cause of the failure. Common reasons for SATURN failures include:

- Spaces in file and path names (not a problem with SATURN 10.5 or later).
- SATNET: errors in forecast network .dat file(s).
- SATALL: semi-fatal errors in SATNET meaning UFN file cannot be used for assignment; incompatibility
 of zoning systems in matrix and network files (see Section 7.6.3 about including all zone names in
 reference trip matrix file).
- SATLOOK: previous failure of SATALL meaning costs cannot be skimmed from UFS file(s).

7.2.6 'Furness not converged in doubly-constrained distribution' (error)

The doubly-constrained distribution model uses furnessing to ensure trip end constraints are met. Furnessing is an iterative procedure and usually converges very quickly. This message will be issued if the furnessing process does not converge. The most likely cause is using an incremental version of the model with a very sparse reference trip matrix, i.e. one with lots of zeros. In particular, it is worth looking out for any rows or columns with just one or two non-zero entries.

The solution is to fill in as many of the gaps in the reference matrix as possible. Simply 'seeding' the matrix by replacing zeroes with some fixed value is unlikely to be acceptable as it will distort the distribution of trips in the matrix.



7.2.7 HADES-specific messages

7.2.7.1 Time period boundary outside defined range for linear interpolation

This message indicates that the period covered by the arrival time windows is too short relative to the period covered by the assignment model.

The message will state which origin, destination and demand segment are affected. It will also report a range of departure times (or trip mid-points) corresponding to the departure time of a trip arriving at the start of the first arrival time window, to the departure time of a trip arriving at the end of the last arrival time window. The start and end of every assignment time slice must be within this range. If not, the interpolation method described in Section 4.2.3.5 cannot be used and demand within the assignment time slice will be under-represented.

The solution is to extend the period covered by the arrival time windows, or reduce the period covered by the assignment time slices. As discussed in Section 4.2.3.5, the arrival time windows should start no later than the arrival time of a trip departing at the beginning of the assignment period, and should finish no earlier than the arrival time of a trip departing at the end of the assignment period.

If this message appears in relation to early iterations, but not for the final few iterations of the HADES run it is less important to take action. This can happen because demand is too peaked in the early iterations (everyone arriving close to their preferred time), leading to excessive travel durations. As the iterations progress the peak flattens out, travel durations reduce, and all trips now arrive within the period covered by the arrival time windows.

7.2.7.2 Pre-peak travel durations not increasing/ Post-peak travel durations not decreasing

As described in Section 4.2.3.5, interpolation and extrapolation is used to estimate the travel duration for any given arrival time. For arrivals near the beginning of the modelled period this works best if travel durations are increasing, i.e. the pre-peak travel duration is less than the travel duration from the first assignment time slice, which is less than that from the second time slice. Conversely, at the end of the modelled period travel durations should be decreasing.

This message may indicate that the (fixed) pre or post-peak travel durations are too high, or that the period covered by the assignment is too short (hence travel durations do not increase at the beginning of the period, and decrease at the end, as would be expected if the whole of the peak period were modelled).

7.2.7.3 Possible FIFO violation

FIFO stands for 'First In First Out', meaning that if, for a particular OD pair and user class, vehicle X **departs** before vehicle Y then it should also **arrive** before vehicle Y. This message will be produced if this condition is not met. For example the travel duration for a vehicle departing at 0800 might be 20 minutes (implying arrival at 0820), but a later departure at 0805 might have a 10 minute travel duration (implying an earlier arrival at 0815).

This should never happen in a CONTRAM model. In SATURN it can usually be fixed by using the PASSQ option on the DIADEM Segmentation page. If this doesn't work then please contact DIADEM technical support for further advice.



8. Hints and tips

8.1 Realism testing with DIADEM

8.1.1 Overview

Realism testing is an important part of making sure the demand model is compliant with WebTAG. It is essential when importing model parameters (e.g. using the WebTAG illustrative parameters) rather than calibrating them locally. The relevant part of WebTAG is Section 1.6 of Unit 3.10.4 (Variable Demand Modelling - Convergence Realism and Sensitivity)

8.1.2 Fuel cost elasticity

The main requirement is to test the outturn elasticity of vehicle kilometres with respect to the cost of fuel. This is calculated from the following formula:

$$E = \frac{\log\left(\frac{T^1}{T^0}\right)}{\log\left(\frac{C^1}{C^0}\right)}$$

where T^0 and C^0 are the base model vehicle kilometres and fuel cost respectively, and T^1 and C^1 are the equivalent quantities after an increase in the cost of fuel. WebTAG recommends that the calculation is done on a network basis (i.e. vehicle kilometres summed over links) and a matrix basis (i.e. vehicle kilometres summed over matrix cells). In both cases vehicle kilometres should exclude movements and vehicle types that are not subject to variable demand.

To obtain the required data from DIADEM the procedure is as follows:

- Decide on what increase in fuel cost to test. WebTAG suggests 10%. In some cases this small increase
 can get lost in convergence noise so 20% may be better. This gives you the value of (1.1 for a 10%
 increase, 1.2 for 20%).
- For each demand segment/user class calculate how much of the distance coefficient in the generalised cost represents fuel costs. If non-fuel VOCs are not included then this will be 100%, if they are included it will be less.
- 3. From (1) and (2) calculate how much the distance coefficient needs to be increased to reflect your chosen fuel cost increase. For example, if you increase fuel costs by 20%, and fuel costs represent 60% of your distance coefficient then you need to increase your distance coefficient by 20% x 60%=12%.
- 4. Create forecast scenario network file(s). This should be the base year network with the distance coefficient increased according to (3). No other changes from the base year network should be made.
- 5. Obtain T^0 . The method for doing this depends on the demand model being used:
 - a. Incremental OD: T^0 comes from the validated base model assignments



- b. Incremental PA and Absolute PA/OD: T^0 obtained from assigning the results of a DIADEM run set up to model the base year without the fuel cost increase
- 6. Set up a DIADEM control file for the increased fuel cost scenario. The inputs should be as follows:
 - a. Forecast network files should be those created in (4) above
 - b. For an incremental model:
 - i. Reference costs should be base year costs
 - ii. Reference trip matrices should be base year trip matrices
 - c. For an absolute model:
 - i. Initial guess matrix should be base year trip matrices
- Run DIADEM to convergence.
- 8. Extract forecast vehicle kilometres T^1 from the assignments and calculate the elasticity of vehicle kilometres with respect to fuel cost using the above formula. This can be done by user class and time period.

If the outturn elasticity is not acceptable then some adjustment of the demand model parameters may be required. The elasticity is roughly proportional to the distribution lambda parameters input to DIADEM (assuming distribution is at the bottom of the hierarchy). So if the elasticity for a particular demand segment is 50% too high then the distribution lambda parameter should be factored by 1/1.5. There is no need to adjust the theta parameters for responses higher up the hierarchy – these just reflect the relative strengths of the different responses and should be maintained.

More information on model adjustment can be found in WebTAG 3.10.4.

8.1.3 Journey time elasticity

WebTAG also recommends the calculation of other elasticities. Elasticities with respect to parking charges and public transport fares can be calculated by adapting the above procedure. Elasticities with respect to car travel times are more problematic and require a more approximate approach. The elasticities of vehicle kilometres with respect to fuel costs and journey times are related as follows:

$$E^{time} = E^{fuel} \frac{p^{time}}{p^{fuel}}$$

where p^{time} is the cost of travel as a proportion of total generalised cost, and p^{fuel} is the cost of fuel as a proportion of total generalised cost.

If you know the total vehicle kilometres, K, and the total vehicle hours, T, then you can calculate an average value for $\frac{p^{time}}{p^{fuel}}$ as:

$$\frac{p^{time}}{p^{fuel}} = \frac{aT}{bK}$$

where a is the cost per hour from the generalised cost function and b is the cost per km.



The elasticity of vehicle kilometres with respect to journey time can then be estimated as:

$$E^{time} = E^{fuel} \frac{aT}{bK}$$

This is only a crude estimate. If the result is close to the WebTAG recommended limit of -2.0 then please contact DIADEM support for advice on obtaining a more accurate value.

8.2 Reducing run times

The vast majority of the total DIADEM run time is spent running assignments and skimming costs. To reduce run times you therefore need to reduce the time spent on these tasks and minimise the number of iterations that DIADEM does.

Skimming costs as an average over all used paths in SATURN takes much more time than skimming minimum cost paths. As noted in Section 6.6 it is acceptable to skim minimum cost paths provided that the assignment is well converged.

Assignment run times in SATURN can often be reduced significantly by adjusting the convergence parameters. Setting SATURN parameters similar to the following values is often successful in minimising run times:

If you are skimming minimum cost paths you can also set SAVEIT=F, but when final assignments are being run to provide inputs to TUBA it will need to be set to T and NITA_S will need to be sufficiently high to make the SAVEIT assignment as accurate as possible (for more information see Section 15.23 of the SATURN manual).

Of course, each network is different and some experimentation with the above parameters may be necessary.

If you are using SATURN version 10.6.17 or later you can make use of the 'warm start' facility. This means that the SATURN assignment can make use of the route and cost information from the previous DIADEM iteration, reducing the time required to get a converged assignment. To do this make the following modifications to your network.dat files:

- Set UPDATE to 'T' under &OPTION
- Set WSTART to 'T' under &OPTION
- Set SAVUFO to 'T' under &PARAM

The last two options are likely to be most successful if you are using the origin-based assignment (OBA) option, but are sometimes worth trying in other cases.

When you run DIADEM you may see a SATURN dialogue box asking you for a UFS file to update from. You can select your base year UFS file. This will only happen on the first DIADEM iteration. Subsequently the warm start and update will be based on the results of the previous DIADEM iteration.

DIADEM User Manual Version 5.0 (SATURN)



It should be noted that in some cases the extra time taken for SATURN to produce the UFO file might offset other time savings, particularly for a high value of NITA_S, so significant savings cannot be guaranteed.

For more information on warm starts see Section 22 of the SATURN manual. The above information is based on the manual for SATURN version 10.7.10 and may not be appropriate for later versions.

To minimise the number of iterations it is worth experimenting with different algorithms to see which works best for your model. It can also be worth experimenting with the initial step length for Algorithm 1 and the fixed step length algorithm. The values in the Max Flow Change column of the _results.csv file can provide a useful indication of how to change the step length. A sequence of values of the same sign is usually an indication that the step length can be increased, for example: -9.98, -7.85, -6.37, -5.16 etc. Conversely, alternating signs can be an indication that the step length needs to be decreased: -9.98, 8.56, -7.45, 6.78 etc. High step lengths tend to be more successful in relatively uncongested networks and vice versa.

8.3 Improving convergence

There are a number of things to adjust to try to improve DIADEM convergence:

- Increase the maximum number of iterations
- Decrease the stopping values for the gap values
- Decrease the value of the 'maximum flow change' parameter
- Improve your assignment convergence
- Adjust the initial step length (for Algorithm 1 and Fixed Step Length)

In the majority of cases improving assignment convergence is the most effective action. The main measure of this is the assignment gap (post-simulation in SATURN). Values of 0.1% or lower may be required. However a low global gap value can sometimes hide local problems that cause difficulties for DIADEM. Since DIADEM uses the costs from the assignment it is important that costs in the assignment are as stable as possible.

If you are skimming costs over an average of used paths in SATURN then the accuracy of the SAVEIT assignment is also important; it should match the 'actual' assignment as closely as possible and you may need to increase the value of the NITA_S parameter. See Section 15.23 of the SATURN manual for further information. CONTRAM users can improve convergence by using smaller packet sizes.

It is recommended that the gap is used as the stopping criterion in SATURN. This requires setting KONSTP=1 in the SATURN .dat network file, and STPGAP equal to the stopping value; 0.1 is recommended as a good starting point and can be reduced later if required.

It can be worth experimenting with different algorithms. Algorithm 1 is normally the most effective, but can be sensitive to assignment convergence noise, in which case the Fixed Step Length method may give better convergence. As a last resort, Method of Successive Averages can be used, but this is likely to be slow to converge to an acceptable level.

DIADEM User Manual Version 5.0 (SATURN)



8.4 Freezing particular movements

In many variable demand modelling applications it is desirable to freeze certain movements in the trip matrix, i.e. they are not subject to variable demand. This is most often done for external to external trips, on the basis that the costs (and the changes in costs) are not usually fully modelled for such trips.

In DIADEM the decision to use variable demand modelling is made at the trip purpose level. So this requires setting up additional trip purposes and demand segments for the fixed trips. For example, suppose a subset of movements for employer's business trips is to be frozen. This suggests the following set up of trip purposes in DIADEM:

- Home-based employers business (VDM): modelled as variable demand (PA)
- Non-home based employers business (VDM): modelled as variable demand (OD)
- Employers business (fixed): modelled as fixed demand

All three purposes can be combined into a single assignment user class.

The reference matrices (in an incremental model) or trip ends (for an absolute model) for the variable demand segments should exclude those trips which are being treated as fixed demand.



9. References

Arnott, R., de Palma, A., Lindsey, R. (1994). Welfare effects of congestion tolls with heterogeneous commuters. Journal of Transport Economics and Policy.

Bates J, Ashley D and Hyman G (1987). The nested incremental logit model: theory and application to model choice. Proceedings 15th PTRC Summer Annual Meeting, University of Bath, England.

Bates J (2007). Practical modelling of trip re-scheduling under congested conditions. Transportation Research Part A 41 (2007) pp788-801.

Daly A. (2010). Cost Damping in Travel Demand Models. Report of a study for the Department for Transport. Available from http://www.dft.gov.uk/pgr/economics/rdg/costdamping/ [Accessed 24 March 2010]

Gordon A, Daly A, Bates J and Oladeinde F (2007). Modelling time period choice in large-scale hierarchical demand models: some problems and a solution. Proceedings of European Transport Conference. Available from http://etcproceedings.org/paper/modelling-time-period-choice-in-large-scale-hierarchical-demand-models-some-pr [Accessed 30 April 2010]

Mott MacDonald (2004). HADES Good Practice Guide. http://www.dft.gov.uk/pgr/economics/rdg/dtc/phase2/hades/ [accessed 18/11/09]

Mott MacDonald (2005a). HADES Extension Validation Report. Available from http://www.dft.gov.uk/pgr/economics/rdg/dtc/phase3/ [accessed 02/11/09]

Mott MacDonald (2005a). HADES B Final Report. Available from http://www.dft.gov.uk/pgr/economics/rdg/dtc/phase3 / [accessed 02/11/09]

Mott MacDonald (2005a). HADES User Manual 4.0. Available from http://www.dft.gov.uk/pgr/economics/rdg/dtc/phase3/ [accessed 02/11/09]

Mott MacDonald (2011). Incorporating HADES into DIADEM: Results of testing programme. Report reference 241930/05.

Small, K.A., (1982). The scheduling of consumer activities: work trips. American Economic Review 72 (3), 467–479.

Small, K.A., (1992a). Trip scheduling in urban transportation analysis. American Economic Review (Papers and Proceedings) 82 (2), 482–486.

Small, K.A., (1992b). Urban Transportation Economics. In: Fundamentals of Pure and Applied Economics, 51. Harwood Academic Publishers.

Vickrey, W.S., (1969). Congestion theory and transport investment. American Economic Review (Papers and Proceedings) 59, 251–261.

DIADEM User Manual Version 5.0 (SATURN)



Appendices

Appendix A.	Description of algorithms	88
Appendix B.	Demand model functions	90
Appendix C.	Initial tour proportions from NTS data	97
Appendix D.	History of DIADEM changes	99



Appendix A. Description of algorithms

A.1. Definitions and notation

DIADEM deals with commodity flows. Each combination of origin, destination, mode, time period and demand segment constitutes a unique commodity.

The following notation is used:

X	a vector of commodity flows with elements X_s
C(X)	a vector of commodity costs with elements $C_{\mathfrak{s}}(X)$, obtained from the assignment of X
<i>V</i> (<i>X</i>)	the value of the objective function for flows X
U(X)	the search direction vector for flows X
λ	auxiliary cost estimate vector with elements λ_s (DMM only)
UX_s	the upper limit on the flow for commodity s (DMM only)
<i>UC</i> _s	the upper limit on the cost for commodity s (DMM only)
α	step length
R	factor for reducing step length
nsucc	number of iterations without a reduction in step length before step length is increased

A.2. Algorithm 1/MSA/FSL

A.2.1. Framework

N is the main iteration counter. M is the subiteration counter. L counts the number of iterations since the step length was decreased.

- 1. Initialise N=1, M=1, L=1
- Calculate demand XN

For N=1 use reference demand, otherwise calculate search direction U and

$$X^{N} = X^{N-1} + \alpha U^{N-1} (X^{N-1})$$

Any negative elements of X^{N} should be reset to zero



(Note: for MSA we always have $\alpha=1/N$; for FSL α remains constant throughout)

- 3. Assign demand X^N to obtain associated costs $C(X^N)$
- 4. Calculate objective function $V^N = V(X^N)$.
- 5. If N>1 and algorithm is not MSA or FSL check if $V^N < V^{N-1}$. If not set $\alpha = R\alpha$, L=0, recalculate X^N (as in step 2), M=M+1, check max flow change not below user-defined limit (if it is then whole algorithm is deemed to have converged) and go to step 3.
- 6. Check for convergence. If converged then exit loop
- 7. Set N=N+1. M=1. L=L+1
- 8. If L=nsucc then $\alpha = 2\alpha$ (does not apply to MSA)
- 9. Go to step 2
- A.2.2. Algorithm 1 objective function

$$V(X) = \frac{1}{2} \sum_{s} \{D_{s}(C(X)) - X_{s}\}^{2}$$

A.2.3. Algorithm 1 and MSA search direction

$$U_s(X) = D_s(C(X)) - X_s$$



Appendix B. Demand model functions

B.1. Logit model

B.1.1. Incremental multinomial logit

Three types of choice model can use the incremental logit formulation in DIADEM: distribution, mode and time period choice. They can be joined together in a hierarchy in any order.

The standard incremental multinomial logit model is given by:

$$\rho_{i} = \frac{\rho_{i}^{0} \exp(\Theta \Delta U_{i})}{\sum_{i} \rho_{j}^{0} \exp(\Theta \Delta U_{j})}$$
(B.1)

where

is the forecast probability of choosing alternative *i*

 p_i^0 is the reference case probability of choosing alternative i (calculated from the input reference demand)

 θ is the scaling parameter (always =1 for the bottom level of the hierarchy)

 ΔU_i is the *change* in the utility of alternative *i*

For the choice at the bottom level of the hierarchy the change in utility is given by

$$\Delta U_i = \lambda (C_i - C_i^0)$$

where

 C_i^0 is the reference generalised cost and

 C_i is the forecast generalised cost, skimmed from the latest assignment

λ is the spread or dispersion parameter (defined by the user); it should be negative

For choices above the bottom level of the hierarchy the change in utility is the composite change over the alternatives in the level below:

$$\Delta U^* = \ln \sum_i \rho_i^0 \exp(\Delta U_i)$$

This model formulation is used for mode choice, time period choice and singly constrained distribution. In the latter, for OD-based demand modelling, origin-constrained distribution is treated as a model of destination choice and destination-constrained distribution is a model of origin choice.

B.1.2. Absolute multinomial logit

The absolute multinomial model is:



$$p_i = \frac{\exp(\theta U_i)}{\sum_{j} \exp(\theta U_j)}$$

Composite utilities are given by:

$$U^* = \ln \sum_{i} \exp(U_i)$$

The generalised $cost C_i$ might include mode constants. Additional constants B (size variables) and K (K factors) can be used for a distribution model:

$$\rho_{j|i} = \frac{B_j K_{ij} \exp(\theta U_{ij})}{\sum_{k} B_k K_{ik} \exp(\theta U_{ik})}$$

B.1.3. Extension to doubly-constrained distribution

A modified version of the incremental model is used for doubly-constrained distribution:

$$T_{ij} = O_i \frac{B_j T_{ij}^0 \exp(\theta \Delta U_{ij})}{\sum_{k=1}^{N} B_k T_{ik}^0 \exp(\theta \Delta U_{ik})}$$
(B.2)

where

 T_{ij} is the forecast number of trips travelling from zone i to zone j

 T_{ii}^0 is the reference case number of trips travelling from zone i to zone j

O_i is the number of trips travelling from zone i

 B_j are destination-based constants, normalised so that $\sum_i B_j$ is equal to the number of zones

The B_b are calculated by DIADEM to ensure that the destination trip-end constraints are met (the model formulation ensures the origin constraints are always met). This is done using a Furnessing procedure.

Note that destination constraints are summed over all person types within a purpose, and across all modes and time periods, if those choices have been modelled.

The change in composite utility for origin zone a is calculated using:

$$\Delta U_a^* = \ln \sum_b B_b \frac{T_{ab}^0}{O_a^0} \exp(\theta \Delta U_{ab})$$



B.2. The hierarchical model

The above multinomial logit model is easily extended to a hierarchical formulation as follows:

- The probabilities calculated at each level are conditional on the choices made at the level(s) above (except for the top level of the hierarchy)
- The change in costs used at each level should be the change in composite costs from the level immediately below (except for the bottom level of the hierarchy)

For a full explanation of the incremental hierarchical logit model see Bates et al (1987).

B.2.1. Frequency model

The incremental frequency model used is:

$$T_i = T_i^0 \exp(\theta_{freq} \Delta U_i^*)$$

When origin or doubly constrained distribution is used this formula modifies the origin trip end totals in response to changes in origin composite costs. For destination-constrained distribution it modifies the destination trip end totals.

B.2.2. Elasticity model

The elasticity model uses a Tanner formulation:

$$X_s = X_s^0 \exp\left(\lambda \left(C_s - C_s^0\right)\right) \left(\frac{C_s}{C_s^0}\right)^{\gamma}$$
(B.2.3)

where

X is flow (forecast or reference)

C is generalised cost (forecast or reference)

 λ and γ are user-defined parameters

s indicates 'commodity' (a particular combination of origin, destination, time period,

mode and demand segment)

0 indicates reference cost or flow

The reference cost and flow are input by the user. The forecast cost is skimmed from an assignment.

The power and exponential elasticity functions are special cases of the Tanner function obtained by setting one or other of the parameters to zero.

B.3. A general note on the demand models

For the incremental model all trip end constraints etc. are calculated by demand segment from the input reference demand matrix.



The demand model is essentially the same for OD and PA-based modelling. The key difference is in the interpretation of any time dimension. In the OD model this simply refers to the time period, t, in which the trip takes place. In the PA model it is a combination of the outbound time period, t, and return time period, t.

B.4. Example implementation of incremental logit model

B.4.1. Introduction

This section shows all the calculations involved in the application of the OD-based incremental hierarchical logit for a particular model structure. In this example we assume the following:

- Single trip purpose split into:
- Two person types (say car available and car not available)
- Car available hierarchy (from top to bottom): frequency, mode choice, time period choice, distribution (doubly constrained)
- Car not available hierarchy (from top to bottom): frequency, time period choice, distribution (doubly constrained)

B.4.2. Inputs

Inputs to the demand model are:

C_{ijmtpc}^0	reference generalised cost from zone i to zone j by mode m in time period t , trip
	purpose p , person type c
C _{ijmtpc}	corresponding forecast generalised cost, skimmed from latest assignment
$\mathcal{T}^0_{\mathit{ijmtpc}}$	corresponding reference demand, defined via the user interface

In all the above, there is no data for the highway mode for the no-car person type

B.4.3. Bottom level utilities

The first step is to calculate the change in utility for the lowest level of the hierarchy:

$$\Delta U_{ijmtpc} = \lambda_{mc}^{dest} \left(C_{ijmtpc} - C_{ijmtpc}^{0} \right)$$

where λ_{mc}^{dest} is the mode-specific distribution λ parameter

B.4.4. Doubly-constrained distribution

Since the lowest level is a doubly constrained distribution model we need to find the balancing factors B_{jp} . This requires solving the set of equations given by:



$$T_{ijmtpc} = O_{imtpc} \frac{B_{jp} T_{ijmtpc}^{0} \exp(\Delta U_{ijmtpc})}{\sum_{k=1}^{N} B_{kp} T_{ikmtpc}^{0} \exp(\Delta U_{ikmtpc})}$$

such that the destination trip end constraints are met:

$$\sum_{imtc} T_{ijmtpc} = D_{jp}$$

The destination constraints are calculated from the reference demand matrix:

$$D_{jp} = \sum_{imtc} T_{ijmtpc}^{0}$$

Note that the destination trip end constraints depend on destination and trip purpose only.

The balancing factors are normalised so that

$$\sum_{i} B_{jp} = N$$

where N is the number of destination zones.

On the first iteration only of the demand model the origin trip ends are calculated from the reference demand matrix:

$$O_{imtpc} = \sum_{i} T_{ijmtpc}^{0}$$

For subsequent iterations they are obtained from the application of the conditional probabilities described in section B.4.6.

B.4.5. Composite utilities

The change in the composite utility from the distribution, time period choice and mode choice stages is then calculated:

$$\Delta U_{imtpc}^{*} = \ln \sum_{j} B_{jp} \frac{T_{ijmtpc}^{0}}{O_{imtpc}^{0}} \exp(\Delta U_{ijmtpc})$$

$$\Delta U_{impc}^{\star} = \ln \sum_{t} p_{t|imcp}^{0} \exp \left(\theta_{c}^{time} \Delta U_{imtpc}^{\star} \right)$$

$$\Delta U_{ipc}^{*} = \ln \sum_{m} p_{m|icp}^{0} \exp \left(\theta_{c}^{mode} \Delta U_{impc}^{*} \right)$$
 (car available person type)

$$\Delta U_{ipc}^* = \Delta U_{impc}^*$$
 (car not available person type, m= PT)



The reference case probabilities are calculated from the input reference demand as follows:

$$p_{m|icp}^{0} = \frac{\displaystyle\sum_{jt} T_{ijmtpc}^{0}}{\displaystyle\sum_{jtk} T_{ijktpc}^{0}}$$

$$p_{t|imcp}^0 = rac{\displaystyle\sum_{j} T_{ijmtpc}^0}{\displaystyle\sum_{jk} T_{ijmkpc}^0}$$

B.4.6. Conditional probabilities

Having calculated the change in the composite utilities it is possible to calculate the conditional utilities for each level of the model

Mode choice:

$$p_{m|ipc} = \frac{p_{m|ipc}^{0} \exp(\theta_c^{mode} \Delta U_{impc}^*)}{\sum_{i} p_{k|ipc}^{0} \exp(\theta_c^{mode} \Delta U_{ikpc}^*)}$$
(car available person type)

$$p_{m|ipc} = \begin{cases} 1 & \text{if } m = public \ transport \\ 0 & \text{otherwise} \end{cases}$$
 (car not available person type)

Time period choice:

$$p_{t|impc} = \frac{p_{t|impc}^{0} \exp(\theta_{c}^{time} \Delta U_{imtpc}^{*})}{\sum_{k} p_{k|impc}^{0} \exp(\theta_{c}^{time} \Delta U_{imkpc}^{*})}$$

Distribution (destination choice):

$$\rho_{j|imtpc} = \frac{B_{jp}T_{ijmtpc}^{0} \exp(\Delta U_{ijmtpc})}{\sum_{k=1}^{N} B_{kp}T_{ikmtpc}^{0} \exp(\Delta U_{ikmtpc})}$$

B.4.7. Updated trip matrix

The application of the conditional probabilities gives an updated trip matrix

$$T_{ijmtpc} = T_{ipc}^{0} \rho_{m|ipc} \rho_{t|impc} \rho_{j|imtpc}$$

and updated origin totals:



$$O_{imtpc} = T_{ipc}^0 p_{m|ipc} p_{t|impc}$$

B.4.8. Iteration

The origin totals O_{imtpc} calculated in B.4.7 implicitly depend on the balancing factors B_{jp} through the calculation of composite utilities and conditional probabilities. However, these balancing factors were based on a potentially different set of origin totals. The result is that the trip matrix calculated in B.4.7 may no longer meet the destination trip end constraints.

The solution is to iterate steps B.4.4 to B.4.7 until a consistent result is obtained, i.e. the matrix from B.4.7 satisfies the trip end constraints. To aid convergence, trip ends are averaged between iterations.

B.4.9. Application of frequency model

The frequency model is only applied after the above process has converged. This gives the final trip matrix from the demand model:

$$T_{\textit{ijmtpc}} = \exp\!\left(\!\theta_{\textit{c}}^{\textit{freq}} \Delta U_{\textit{ipc}}^{*}\right)\! T_{\textit{ipc}}^{0} \rho_{\textit{m|ipc}} \rho_{\textit{t|impc}} \rho_{\textit{j|imtpc}}$$

This matrix will be further modified according to the DIADEM algorithm being used before being assigned.



Appendix C. Initial tour proportions from NTS data

The following tables show the proportion of trips going out and returning in each time period for home-based trip purposes, by mode. The time periods following the standard definitions:

AM peak 0700-1000

Inter-peak (IP) 1000-1600

PM peak 1600-1900

Off-peak (OP) 1900-0700

Table C.1: Initial tour proportions for home-based work.

			Return time				
			AM	IP	PM	OP	Total
Car	_	AM	2.50%	13.56%	45.18%	5.64%	66.88%
	Outbound time	IP	0.00%	3.79%	7.03%	3.39%	14.21%
	tbou	PM	0.18%	0.10%	3.01%	3.30%	6.59%
) t	OP	1.59%	4.02%	3.05%	3.66%	12.32%
		Total	4.27%	21.47%	58.27%	15.99%	100.00%
Bus	_	AM	2.69%	14.49%	48.00%	5.94%	71.12%
	l un «	IP	0.00%	3.78%	6.87%	3.33%	13.98%
	Outbound time	PM	0.15%	0.09%	2.56%	2.81%	5.61%
) tr	OP	1.20%	3.04%	2.30%	2.75%	9.29%
		Total	4.04%	21.40%	59.73%	14.83%	100.00%
Rail	-	AM	3.19%	17.11%	56.84%	7.09%	84.23%
	l ar	IP	0.00%	2.46%	4.55%	2.19%	9.20%
	Outbound time	PM	0.07%	0.04%	1.15%	1.25%	2.51%
	Out t	OP	0.52%	1.32%	1.01%	1.21%	4.06%
		Total	3.78%	20.93%	63.55%	11.74%	100.00%



Table C.2: Initial tour proportions for home-based employer's business.

					Return time		
			AM	IP	PM	OP	Total
Car	-	AM	3.47%	14.34%	25.18%	5.52%	48.51%
	oun e	IP	0.00%	14.89%	13.47%	3.47%	31.83%
	tbou	PM	0.00%	0.00%	4.09%	6.05%	10.14%
	Outbound time	OP	0.78%	0.59%	0.72%	7.43%	9.52%
		Total	4.25%	29.82%	43.46%	22.47%	100.00%
Bus	-	AM	3.20%	13.23%	23.22%	5.09%	44.74%
	Outbound time	IP	0.00%	16.08%	14.54%	3.75%	34.37%
	tbou	PM	0.00%	0.00%	4.28%	6.33%	10.61%
	O t	OP	0.84%	0.64%	0.78%	8.02%	10.28%
		Total	4.04%	29.95%	42.82%	23.19%	100.00%
Rail	-	AM	3.48%	14.40%	25.31%	5.54%	48.73%
	l un e	IP	0.00%	16.51%	14.93%	3.85%	35.29%
	Outbound	PM	0.00%	0.00%	3.13%	4.63%	7.76%
		OP	0.67%	0.51%	0.62%	6.42%	8.22%
		Total	4.15%	31.42%	43.99%	20.44%	100.00%

Table C.3: Initial tour proportions for home-based other.

					Return time		
			AM	IP	PM	OP	Total
Car	-	AM	5.91%	12.16%	3.51%	0.30%	21.88%
	oun e	IP	0.00%	28.39%	10.40%	1.51%	40.30%
	Outbound time	PM	0.00%	0.05%	10.22%	7.42%	17.69%
	out t	OP	0.30%	0.29%	0.07%	19.47%	20.13%
		Total	6.21%	40.89%	24.20%	28.70%	100.00%
Bus	-	AM	9.30%	22.05%	7.67%	0.22%	39.24%
	oun e	IP	0.00%	34.81%	11.90%	1.53%	48.24%
	tbou	PM	0.00%	0.02%	3.61%	2.48%	6.11%
	Outbound time	OP	0.10%	0.10%	0.03%	6.18%	6.41%
		Total	9.40%	56.98%	23.21%	10.41%	100.00%
Rail	-	AM	6.45%	15.06%	5.28%	0.17%	26.96%
	Outbound	IP	0.00%	36.34%	12.97%	1.89%	51.20%
		PM	0.00%	0.05%	6.02%	4.24%	10.31%
	Out	OP	0.19%	0.20%	0.07%	11.07%	11.53%
		Total	6.64%	51.65%	24.34%	17.37%	100.00%



Appendix D. History of DIADEM changes

The following sections summarise the main functional changes between different versions of DIADEM. More details can be found in the release notes on the DIADEM website.

D.1. Changes between 4.1 and 5.0

- HADES model of arrival time choice made available as a demand response for trip purposes that use absolute demand modelling.
- PA trip matrices are now output on each iteration.

D.2. Changes between 3.1 and 4.1

- Fundamental change to the way generalised cost coefficients are defined.
- Cost damping option introduced.

D.3. Changes between 3.0 and 3.1

DIADEM 3.1 was released in June 2009 and included the following new features.

- Greatly reduced memory requirements, reducing the risk of out of memory errors while running DIADEM.
- The option to carry out SATURN assignments in parallel, with significant reductions in run time (subject to appropriate hardware being available).
- Greater detail in reporting in the .log file.

D.4. Changes between 2.1 and 3.0

DIADEM 3.0 was released in March 2008 and included the following new features.

- Demand modelling functionality extended to include production-attraction/tour-based modelling. This
 gave full compatibility with WebTAG guidance for the modelling of home-based trips.
- The absolute version of hierarchical logit model was added.
- A "spatial segmentation" option was introduced. This allowed the use of different distribution model parameters for different zone pairs.
- A new option to estimate intra-zonal costs. This allowed the choice between inter and intra-zonal travel to be included as part of the distribution model.
- A re-engineered user interface.
- A new format for the control file using xml (eXtensible Markup Language).

DIADEM User Manual Version 5.0 (SATURN)



• The location of SATURN executable files now stored with the control file. This made it easier to work with multiple versions of SATURN and ensure that the correct version is used for a given DIADEM run.

A separate document is available from the DIADEM <u>website</u> that provides a screen by screen guide to what's new in the user interface for DIADEM 2.1 users.

Version 2.1 of DIADEM was the first general release, in December 2005.