



SNOWER APIS

Snowier 2.0

Abstract

The Snowier API is a RESTful web service that provides programmatic access to snow analytics data. It enables third party integration with snow analytics data into their applications, allowing them to analyze and visualize the data in real-time.

Contents

POST login.....	2
POST set_area.....	3
POST regions_list	5
POST areas_list	7
POST monitors_list	9
POST monitor_active_status.....	11
POST monitor_location.....	13
POST monitor_status	15
POST readings_list.....	18
POST snow_depth_readings_list	23
POST temperature_readings_list.....	26
POST last_reading	29
POST last_snow_depth	32
POST last_temperature	34
POST snow_depth_difference.....	36

POST login

https://app.snowier.fi/api/login

Authenticates the user and provides the API key that could be used for authorization in the remaining API calls.

Prerequisites:

- A valid username and password; the user should have the `api-access` role.

Inputs:

- username (required): the username to be used should be received from the API admin.
- password (required): the password to be used should be received from the API admin.

Output:

- Authentication key: the key to be used in all snowier api in the headers to authenticate the user before proceeding to the endpoint logic.

BODY raw

```
{
  "username": {username},
  "password": {password}
}
```

Example Request login

Example 1

```
POST https://app.snowier.fi/api/login
{
  "username": {username},
  "password": {password}
}
```

Example 1 Response 200 - OK

```
{
  "authentication_key": "{auth_key}"
}
```

POST set_area

```
https://app.snowier.fi/api/set_area
```

Sets the saved default area for the current user. This area can then be omitted out in the upcoming API usages and this default value will be used instead.

Prerequisites:

- A valid domain name that exists in snowier.
- A valid authentication key which can be fetched from login endpoint, the user should have an account tied to the specified domain.
- A valid area name and the used area name should be exists in snowier. You can find the valid areas names from the `areas_list` build.

Inputs:

- area (required): the area name to be set for the current user.

HEADERS

authentication-key

```
{{snowier_endpoints_auth_key}}
```

key to authenticate the user before proceeding in the login of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{  
  "area": "Lappi/Lapland"  
}
```

Example Request

set_area

Example 1

```
POST https://app.snower.fi/api/set_area
{
  "area": "Lappi/Lapland"
}
```

Example 1 Response

200 - OK

```
{
  "results": "The requested action was executed successfully."
}
```

POST regions_list

```
https://app.snower.fi/api/regions_list
```

Returns the list of regions for the specified domain. The output can be used in other endpoints.

Prerequisites:

- A valid domain name that exists in snower.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.

Inputs:

- domain (required): Domain name to get the regions list for.

Output:

- List of regions existing in the given domain.

HEADERS

authentication-key

{{snower_endpoints_auth_key}}

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "domain": "Test"
}
```

Example Request

regions_list

Example 1

```
POST https://app.snower.fi/api/ regions_list
{
  "domain": "test"
}
```

Example 1 Response

200 - OK

```
[
  " test_region1"
]
```

POST areas_list

```
https://app.snowier.fi/api/areas_list
```

Returns the list of all available areas for the given region. The output can be used in other endpoints.

Prerequisites:

- A valid domain name that exists in snowier.
- The region name you want to get the areas list of. it can be fetched from [regions_list](#) endpoint
- A valid authentication key which can be fetched from login endpoint, the user should have an account tied to the specified domain.

Inputs:

- region (required): region name to get the areas list for.

Output:

- A list contains all the available areas in the region specified.

HEADERS

authentication-key

{{snowier_endpoints_auth_key}}

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{  
  "region": "test_region1"  
}
```

Example Request

areas_list

Example 1

```
POST https://app.snowier.fi/api/areas_list  
{
```

```
}    "region": "test_region1"
```

Example 1 Response

200 - OK

```
[    "Kadut/Streets",  
    "Demo locations"
```

POST monitors_list

```
https://app.snowe.fi/api/monitors_list
```

Returns the list of monitors for the specified area.

Prerequisites:

- A valid domain name that exists in snowe.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.

Output:

- List of monitors existing in the given area.

HEADERS

authentication-key

```
{{snowe_endpoints_auth_key}}
```

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{  
  "area": "Demo locations"  
}
```

Example Request

monitors_list

Example 1

```
POST https://app.snower.fi/api/monitors_list
{
  "area": "Demo locations"
}
```

Example 1 Response

200 - OK

```
[
  "Aistin Level #9077 (Parkkisenkangas)",
  "Parkkisenkangas takapiha"
]
```

Example 2

```
POST https://app.snower.fi/api/monitors_list
{
}
```

Example 2 Response

200 - OK

```
[
  "Aistin Level #9077 (Parkkisenkangas)",
  "Parkkisenkangas takapiha"
]
```

POST monitor_active_status

```
https://app.snowier.fi/api/monitor_active_status
```

Checks if the monitor is active or not.

The monitor is considered inactive if it doesn't receive any data in the last 24 hours.

Prerequisites:

- A valid domain name that exists in snowier.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.

Output:

- map that contains one boolean variable that determines whether the monitor is active or not.

HEADERS

authentication-key

```
{{snowier_endpoints_auth_key}}
```

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Request

monitor_active_status

Example 1

```
POST https://app.snower.fi/api/monitor_active_status
{
  "area": "Pohjois-Suomi/Northern Finland",
  "monitor": "Oulu - Parkkisenkangas"
}
```

Example 1 Response

200 - OK

```
{
  "active_status": false
}
```

Example 2

```
POST https://app.snower.fi/api/monitor_active_status
{
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 2 Response

200 - OK

```
{
  "active_status": true
}
```

POST monitor_location

```
https://app.snowe.fi/api/monitor_location
```

Returns the specified monitor's location.

Prerequisites:

- A valid domain name that exists in snowe.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.

Output:

- map that contains one object `location` that contains lat and lng.

HEADERS

authentication-key

```
{{snowe_endpoints_auth_key}}
```

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Request

monitor_location

Example 1

```
POST https://app.snower.fi/api/monitor_location
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 1 Response

200 - OK

```
{
  "location": {
    "lat": 65.019795,
    "lng": 25.530448
  }
}
```

Example 2

```
POST https://app.snower.fi/api/monitor_location
{
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 2 Response

200 - OK

```
{
  "location": {
    "lat": 65.019795,
    "lng": 25.530448
  }
}
```

POST monitor_status

```
https://app.snower.fi/api/monitor_status
```

Gets the monitor status and message configured by the admin in Snower domain

Prerequisites:

- A valid domain name that exists in snower.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.

Output:

- The status body can be one of the following:
 - Not Evaluated
 - Low Risk
 - Moderate Risk
 - Significant Risk
 - High Risk
 - Extreme Risk
 - Note
- The message is a string describe the monitor status and added any extra info for the user, the message can be in English or Finnish language.

HEADERS

authentication-key

`{{snower_endpoints_auth_key}}`

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Request

monitor_status

Example 1

```
POST https://app.snowier.fi/api/monitor_status
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 1 Response

200 - OK

```
{
  "message": {
    "en": "Visit https://snowier.fi for more info.",
    "fi": "Huomio https://snowier.fi aaaa bb aaa1234o9999"
  },
  "status": {
    "body": "High Risk",
    "type": "5"
  }
}
```

Example 2

```
POST https://app.snowier.fi/api/monitor_status
{
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 2 Response

200 - OK

```
{
  "message": {
    "en": "Visit https://snower.fi for more info.",
    "fi": "Huomio https://snower.fi aaaa bb aaa1234o9999"
  },
  "status": {
    "body": "High Risk",
    "type": "5"
  }
}
```

POST readings_list

```
https://app.snower.fi/api/readings_list
```

Returns the readings list for the provided date range. Filters can be provided using the readings types body field and if it was not added, it will return the default types: (snow_depth, probe_temperature).

Prerequisites:

- A valid domain name that exists in snower.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The default area to be added to the current user if the area field is omitted, and this is done using set_area endpoint.
- The exact area name and monitor name, and those can be fetched from [areas_list](#) and [monitors_list](#) endpoints respectively.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.
- start_date (required): start date as string given in the format: %Y-%m-%d %H:%M:%S.%f%z.
- end_date (required): end date as string given in the format: %Y-%m-%d %H:%M:%S.%f%z.
- readings_types (optional): optional list of readings types; the list content should include only supported types.
 - Supported readings types:
 - snow_depth
 - probe_temperature
 - ir_temperature
 - humidity
 - Readings types are case sensitive, and it should be in snake_case.

Output:

- Readings in map format and each reading has the key of its datetime.

HEADERS

authentication-key

{{snower_endpoints_auth_key}}

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)",
  "readings_types": ["snow_depth", "probe_temperature"]
}
```

Example Request

readings_list

Example 1

```
POST https://app.snower.fi/api/readings_list
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)",
  "readings_types": ["snow_depth", "probe_temperature"]
}
```

Example 1 Response

200 - OK

```
{
  "2023-03-18 11:19:58.241000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 11:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.1
    }
  },
  "2023-03-18 11:49:59.299000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 11:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:20:00.723000": {
    "snow_depth": { "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 12:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:50:01.839000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.400000000000006
    }
  },
  "2023-03-18 12:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.6
    }
  }
}
```

Example 2

POST https://app.snower.fi/api/readings_list

```
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)",
  "readings_types":["snow_depth","probe_temperature"]
}
```

Example 2 Response

200 - OK

```
{
  "2023-03-18 11:19:58.241000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 11:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.1
    }
  },
  "2023-03-18 11:49:59.299000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 11:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:20:00.723000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 12:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:50:01.839000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.400000000000006
    }
  },
  "2023-03-18 12:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.6
    }
  }
}
```

Example 3

```
POST https://app.snower.fi/api/readings_list
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)",
  "readings_types": ["probe_temperature"]
}
```

Example 3 Response

200 - OK

```
{
  "2023-03-18 11:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.1
    }
  },
  "2023-03-18 11:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.6
    }
  }
}
```

POST snow_depth_readings_list

```
https://app.snowier.fi/api/snow_depth_readings_list
```

Returns the snow depth readings list for the provided date range.

Prerequisites:

- A valid domain name that exists in snowier.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- `area` (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- `monitor` (required): considered monitor name, this field is required.
- `start_date` (required): start date as string given in the format: %Y-%m-%d %H:%M:%S.%f%z.
- `end_date` (required): end date as string given in the format: %Y-%m-%d %H:%M:%S.%f%z.

Output:

- Snow depth readings in map format and each reading has the key of its datetime.

HEADERS

authentication-key

{{snowier_endpoints_auth_key}}

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Request

snow_depth_readings_list

Example 1

POST https://app.snower.fi/api/snow_depth_readings_list

```
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 1 Response

200 - OK

```
{
  "2023-03-18 11:19:58.241000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 11:49:59.299000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 12:20:00.723000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 12:50:01.839000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.400000000000006
    }
  }
}
```

Example 2

```
POST https://app.snowier.fi/api/snow_depth_readings_list
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 2 Response

200 - OK

```
{
  "2023-03-18 11:19:58.241000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 11:49:59.299000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 12:20:00.723000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.599999999999994
    }
  },
  "2023-03-18 12:50:01.839000": {
    "snow_depth": {
      "unit": "cm",
      "value": 53.400000000000006
    }
  }
}
```

POST temperature_readings_list

```
https://app.snower.fi/api/temperature_readings_list
```

Returns the probe temperature readings list for the provided date range.

Prerequisites:

- A valid domain name that exists in snower.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.
- start_date (required): start date as string given in the format: %Y-%m-%d %H:%M:%S.%f%z.
- end_date (required): end date as string given in the format: %Y-%m-%d %H:%M:%S.%f%z.

Output:

- Probe temperature readings in map format and each reading has the key of its datetime.

HEADERS

authentication-key

{{snower_endpoints_auth_key}}

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Request

temperature_readings_list

Example 1

POST https://app.snower.fi/api/temperature_readings_list

```
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 1 Response

200 - OK

```
{
  "2023-03-18 11:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.1
    }
  },
  "2023-03-18 11:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.6
    }
  }
}
```

Example 2

POST https://app.snower.fi/api/temperature_readings_list

```
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 2 Response

200 - OK

```
{
  "2023-03-18 11:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.1
    }
  },
  "2023-03-18 11:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:23:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.3
    }
  },
  "2023-03-18 12:53:00.000000": {
    "probe_temperature": {
      "unit": "Celcius",
      "value": 2.6
    }
  }
}
```

POST last_reading

```
https://app.snower.fi/api/last_reading
```

Fetches the last reading for the provided monitor. If the `readings_types` filter was not provided, all reading keys will be retrieved. If the filtering array was provided, only the elements in the filter will be retrieved.

Prerequisites:

- A valid domain name that exists in snower.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.
- readings_types (optional): optional list of readings types; the list content should include only supported types.
 - Supported readings types:
 - snow_depth
 - probe_temperature
 - ir_temperature
 - humidity
 - Readings types are case sensitive, and it should be in snake_case.

Output:

- Last readings for the given monitor.

HEADERS

authentication-key

{{snower_endpoints_auth_key}}

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

```
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)",
  "readings_types":["snow_depth","probe_temperature"]
}
```

Example Request

last_reading

Example 1

POST https://app.snower.fi/api/last_reading

```
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)",
  "readings_types":["snow_depth","probe_temperature"]
}
```

Example 1 Response

200 - OK

```
{
  "snow_depth": {
    "date_time": "2023-04-06T12:24:19.863000Z",
    "unit": "cm",
    "value": 67.5
  },
  "probe_temperature": {
    "date_time": "2023-04-06T12:26:52.439000Z",
    "unit": "Celcius",
    "value": 14.7
  }
}
```

Example 2

POST https://app.snower.fi/api/last_reading

```
{
  "monitor": "Aistin Level #9077 (Parkkisenkangas)",
  "readings_types":["snow_depth","probe_temperature"]
}
```

Example 2 Response

200 - OK

```
{
  "snow_depth": {
    "date_time": "2023-04-10T07:27:16.837000Z",
    "unit": "cm",
    "value": 58.599999999999994
  },
  "probe_temperature": {
    "date_time": "2023-04-10T07:29:54.074000Z",
    "unit": "Celcius",
    "value": 14.2
  }
}
```

Example 2

POST https://app.snower.fi/api/last_reading

```
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)",
  "readings_types": ["snow_depth"]
}
```

Example 2 Response

200 - OK

```
{
  "snow_depth": {
    "date_time": "2023-04-10T07:27:16.837000Z",
    "unit": "cm",
    "value": 58.599999999999994
  }
}
```

POST last_snow_depth

```
https://app.snower.fi/api/last_snow_depth
```

Fetches the last snow depth value for the provided monitor.

Prerequisites:

- A valid domain name that exists in snower.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.

Output:

- Last snow depth reading for the given monitor.

HEADERS

authentication-key

```
{{snower_endpoints_auth_key}}
```

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Request

last_snow_depth

Example 1

```
POST https://app.snower.fi/api/last_snow_depth
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 1 Response

200 - OK

```
{
  "snow_depth": {
    "date_time": "2023-04-06T12:54:16.839000Z",
    "unit": "cm",
    "value": 68.1
  }
}
```

Example 2

```
POST https://app.snower.fi/api/last_snow_depth
{
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 2 Response

200 - OK

```
{
  "snow_depth": {
    "date_time": "2023-04-10T07:27:16.837000Z",
    "unit": "cm",
    "value": 58.599999999999994
  }
}
```

POST last_temperature

```
https://app.snowier.fi/api/last_temperature
```

Fetches the last probe temperature value for the provided monitor.

Prerequisites:

- A valid domain name that exists in snowier.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.

Output:

- Last probe temperature reading for the given monitor.

HEADERS

authentication-key

```
{{snowier_endpoints_auth_key}}
```

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Request

last_temperature

Example 1

```
POST https://app.snower.fi/api/last_temperature
{
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 1 Response

200 - OK

```
{
  "probe_temperature": {
    "date_time": "2023-04-06T12:26:52.439000Z",
    "unit": "Celcius",
    "value": 14.7
  }
}
```

Example 2

```
POST https://app.snower.fi/api/last_temperature
{
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 2 Response

200 - OK

```
{
  "probe_temperature": {
    "date_time": "2023-04-10T07:29:54.074000Z",
    "unit": "Celcius",
    "value": 14.2
  }
}
```

POST snow_depth_difference

```
https://app.snower.fi/api/snow_depth_difference
```

Returns the snow depth difference for the specified time interval. The time interval can be specified in two ways:

- Start date and end date.
- Time period.

Prerequisites:

- A valid domain name that exists in snower.
- A valid authentication key that can be fetched from login endpoint, the user should have an account tied to the specified domain.
- The area name you want to get the monitors list either by setting it in the default area using the `set_area` endpoint or by sending the exact area name in the body. the exact name of the area which can be fetched from `areas_list` endpoint.
- The exact monitor name. it can be fetched from `monitors_list` endpoint.

Inputs:

- area (optional): Area name to get the monitors list for. If not given the api will use the default area for the given user authentication key.
- monitor (required): considered monitor name, this field is required.
- start_date (*optional): start date as string given in the format: %Y-%m-%d %H:%M:%S.%f%z.
- end_date (*optional): end date as string given in the format: %Y-%m-%d %H:%M:%S.%f%z.
- filter_period (*optional): period formatted in string like: "1w 2d 4h" which means one week, two days and four hours.

Note: the endpoint accepts start and end dates or filter period.

Output:

- The difference of snow depth in the start and end of the given period.

HEADERS

authentication-key

```
{{snower_endpoints_auth_key}}
```

key to authenticate the user before proceeding in the logic of the endpoint. It can be fetched from `login` endpoint.

domain-id

the name of the domain that contains the resources you want to access or edit.

BODY raw

```
{
  "filter_period": "1d",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Request

(default_area) snow_depth_difference

Example 1

```
POST https://app.snower.fi/api/snow_depth_difference
{
  "filter_period": "1d",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 1 Response

200 - OK

```
{
  "snow_depth_difference": {
    "unit": "cm",
    "value": -3.3000000000000114
  }
}
```

Example 2

```
POST https://app.snower.fi/api/snow_depth_difference
{
  "start_date": "2023-03-18 10:55:00.00+00:00",
  "end_date": "2023-03-18 12:55:00.00+00:00",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example 2 Response

200 - OK

```
{
  "snow_depth_difference": {
    "unit": "cm",
    "value": -0.19999999999998863
  }
}
```

Example 3

```
POST https://app.snower.fi/api/snow_depth_difference
{
  "filter_period": "1d",
  "area": "Demo locations",
  "monitor": "Aistin Level #9077 (Parkkisenkangas)"
}
```

Example Response

200 - OK

```
{
  "snow_depth_difference": {
    "unit": "cm",
    "value": 2
  }
}
```