



(A) Bolin number ($Bo = \frac{\tau_{\text{heavy}}}{\tau_{\text{total}}}$) [1]**(B)** $\frac{R_{\text{liq}}}{R_{\text{vap}}} - Bo$ [1]

Figure 1: The Bolin number (A) equals 1 when the isotopic composition of liquid droplets is not changing (i.e., $\frac{dR_{\text{liq}}}{dt} = 0$). For the isotopic composition of ambient vapour (B) to be in equilibrium (i.e., $\frac{dR_{\text{vap}}}{dt} = 0$), the following condition must be met: $\left(\frac{R_{\text{liq}}}{R_{\text{vap}}} - Bo = 0\right)$. The isotopologue considered in both plots is $^1\text{H}^2\text{H}^{16}\text{O}$.

Black lines: isotopic equilibrium curves from Gedzelman & Arnold (1994, Fig. 2);
 red line: phase equilibrium ($\text{RH} = 100\%$); white dot: phase and isotopic equilibrium, $R_{\text{liq}} = \alpha(T) R_{\text{vap}}$.

The environmental setting follows that of the paper: $T = 10^\circ\text{C}$, $\delta_{2\text{H}} = \frac{R_{\text{vap}}}{R_{\text{SMOW}}} - 1 = -200\text{‰}$.