

1 Time-Controlled Host Interfacing

Usage

You use the time-controlled host interfacing in order to transfer files from other systems (e.g. ERP systems) to the HYDRA server on a cyclical basis (time-controlled) or in order to transfer files from the HYDRA server to other systems using HYDRA Scheduler.

The different interface files are each processed, or rather made available, on the HYDRA server by the HYDRA MLE file port interface.

Here, the system supports the following transmission type and operating system combinations:

		HYDRA server	
		Linux	Windows
External system	UNIX	FTP, NFS	FTP
	Windows	FTP	FTP, UNC
	Other (e.g. AS/400)	FTP	FTP

Requirement

To use the time-controlled host interfacing, the requirements listed below must be met:

Transfer protocol

In order to exchange data with an external system, it must be possible to access it via **FTP** (Port 21). If both systems run on identical operating systems, alternately you can also make use of the following solutions:

UNIX⇔UNIX: Specify the path on the mounted **NFS** share (Network File System)

Windows⇔Windows Specify **UNC** path (Universal Naming Convention) on a network share

Access authorization for NFS connections

The external system's NFS share must be installed on the HYDRA server.

HYDRA (user "**hydadm**") requires **read and write access rights** to the installed directory in order to be able to rename, copy and delete files there.

Access authorization for UNC connections

HYDRA (user "**hydadm**") requires **read and write access rights** to the network share in order to be able to rename, copy and delete files there.


To test the access rights to the network share via the specified UNC path, log onto the HYDRA server as user "**hydadm**" and enter the following command in a Windows command prompt:

```
"dir \\ServerName\FreigabeName"
```

The content of the network share "ShareName" must be displayed without any errors.

User account of the "HYDRA<n> Scheduler" service

Exchanging data by specifying a path for a Windows - Windows connection requires that the "HYDRA<n> Scheduler" service is run as the user "hydadm".



The user "hydadm" on the HYDRA server must be able to access the shares on the external system, which requires that he has the relevant access rights.

FTP command needed for an FTP connection

"open", "login": USER, PASS

"binary": TYPE I (only "ASCII" is possible on AS/400)

"rename": RNFR, RNTD

"ls": LIST

"delete": DELE

"put": STOR

"get": RETR

"cd": CWD

"close": QUIT

"r(emote)help": HELP

"quote time": (AS/400: increase inactivity timeout)




FTP interfacing causes problems on various HP-UX systems if the clear text name of the PPS server is being used. At this time, the problem can only be avoided by using the IP address .



The FTP server version 1.7.212.1 on HP-UX 10.20.x is faulty and therefore cannot be used.

The currently available and tested version for this platform is 1.7.212.5.

Data exchange process - external system → HYDRA



Parameter	Use/ possible entries	only for FTP	Optional for FTP	Optional
MOD=PUT GET	Defines the direction of communication PUT HYDRA → external system GET External system → HYDRA			
HOST=	Host name of the external system	X		
USER=	User name used to log on	X		
PWD=	User's password	X		
REMOTE=	File name on the external system			
REMOTEMASK=	Alternately, the remote system file that is defined via the REMOTE parameter can be created so that it is formatted as specified in the REMOTEMASK parameter. The following options are available for formatting.			
LOCAL=	File name on the HYDRA system			
LOCALMASK=	Alternately, the local file that is defined via the LOCAL parameter can be created so that it is formatted as specified in the LOCALMASK parameter. The following options are available for formatting.			
TMP=	File name of the temporary file (both for the remote as well as for the local server) If the external system runs on an AS/400 operating system, this parameter must be specified.		X	

Parameter	Use/ possible entries	only for FTP	Optional for FTP	Optional
FTPMOD=B A	FTP transfer mode B Binary (default) A ASCII If the external system runs on an AS/400 operating system, "A" must be used.		X	
CMD=	Shell script on the local server that starts in "GET" mode after the file transfer in "PUT" mode before the file transfer . If the CMD specification contains spaces, the CMD must be enclosed within quotation marks! Example: CMD="sh.exe hy6adrck.scr"			X
ALARM=	Time out Communication is interrupted after the defined time (in seconds) (only in Windows) .			

Configuration – Ext. System (Windows) → HYDRA (Windows) via UNC

Edit entries for the HYDRA input batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	sh.exe ./hyd_zhk.scr MOD=GET

Parameter name	Value
	LOCAL=./inf_int/interf/HY72PPS.dat REMOTE="//server/freigabe/pfad/dateiname"
Comment:	Data supply ERP → HYDRA
Interval	5

Configuration – Ext. System (UNIX) → HYDRA (Linux) via NFS

Edit entries for the HYDRA input batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	sh.exe ./hyd_zhk.scr MOD=GET LOCAL=./inf_int/interf/HY72PPS.dat REMOTE="//server/freigabe/pfad/dateiname"
Comment:	Data supply ERP → HYDRA
Interval	5

Configuration – Ext. System (UNIX) → HYDRA (Linux) via FTP

Edit entries for the HYDRA input batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV

Parameter name	Value
Command (Windows):	sh.exe ./hyd_zhk.scr MOD=GET HOST=<server> USER=<ftpuser> PWD=<ftppasswd> LOCAL=./inf_int/interf/HY72PPS.dat REMOTE="/pfad/dateiname"
Comment:	Data supply ERP → HYDRA
Interval	5

Configuration – Ext. System (AS/400) → HYDRA (Windows) via FTP

Edit entries for the HYDRA input batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	sh.exe ./hyd_zhk.scr MOD=GET HOST=<server> USER=<ftpuser> PWD=<ftppasswd> LOCAL=./inf_int/interf/HY72PPS.dat REMOTE="/pfad/dateiname" FTPMODE=A TMP=tmp_hy72pps.dat
Comment:	Data supply ERP → HYDRA
Interval	5



The temporary intermediate file must not have the extension .tmp, otherwise the datasets will be abbreviated!



If AS/400 is configured to use periods in file names, only "members" of a file are deleted during deletions via FTP, not the entire file. For this reason, in order for a process flow to run correctly, you will need to coordinate additional file handling measures with MPDV.

Configuration – Ext. System (Linux) → HYDRA (Windows) via FTP

Edit entries for the HYDRA inbound processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	sh.exe ./hyd_zhk.scr MOD=GET HOST=<server> USER=<ftpuser> PWD=<ftppasswd> LOCAL=./inf_int/interf/HY72PPS.dat REMOTE="/pfad/dateiname"
Comment:	Data supply ERP → HYDRA
Interval	5

Configuration – Ext. System (AS/400) → HYDRA (Linux) via FTP

Edit entries for the HYDRA input batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV

Parameter name	Value
License key	SIS-MWV
Command (Windows):	./hyd_zhk.scr MOD=GET HOST=<server> USER=<ftpuser> PWD=<ftppasswd> LOCAL=./inf_int/interf/HY72PPS.dat REMOTE="/pfad/dateiname" FTPMODE=A TMP=tmp_hy72pps.dat
Comment:	Data supply ERP → HYDRA
Interval	5



The temporary intermediate file must not have the extension .tmp, otherwise the datasets will be abbreviated!



If AS/400 is configured to use periods in file names, only "members" of a file are deleted during deletions via FTP, not the entire file. For this reason, in order for a process flow to run correctly, you will need to coordinate additional file handling measures with MPDV.

Configuration – HYDRA (Windows) → Ext. System (Windows) via UNC

Edit entries for the HYDRA output batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	sh.exe ./hyd_zhk.scr MOD=PUT LOCAL=./inf_int/interf/HY72ADRCK_TT.dat

Parameter name	Value
	REMOTE="\\\\\\\\\\\\server\\\\\\\\freigabe\\\\\\\\pfad/dateiname"
Comment:	Data supply HYDRA → ERP
Interval	5

Configuration –HYDRA (Linux) → Ext. System (UNIX) via NFS

Edit entries for the HYDRA output batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	./hyd_zhk.scr MOD=PUT LOCAL=./inf_int/interf/HY72ADRCK_TT.dat REMOTE="\\\\\\\\\\\\server\\\\\\\\freigabe\\\\\\\\pfad/dateiname"
Comment:	Data supply HYDRA → ERP
Interval	5

Configuration –HYDRA (Linux) → Ext. System (UNIX) via FTP

Edit entries for the HYDRA output batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	./hyd_zhk.scr MOD=PUT

Parameter name	Value
	HOST=<server> USER=<ftpuser> PWD=<ftppasswd> LOCAL=./inf_int/interf/HY72ADRCK_TT.dat REMOTE="/pfad/dateiname"
Comment:	Data supply HYDRA → ERP
Interval	5

Configuration –HYDRA (Windows) → Ext. System (AS/400) via FTP

Edit entries for the HYDRA output batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	sh.exe ./hyd_zhk.scr MOD=PUT HOST=<server> USER=<ftpuser> PWD=<ftppasswd> LOCAL=./inf_int/interf/HY72ADRCK_TT.dat REMOTE="/pfad/dateiname" FTPMODE=A TMP=tmp_HY72ADRCK_TT.dat
Comment:	Data supply HYDRA → ERP
Interval	5



The temporary intermediate file must not have the extension .tmp, otherwise the datasets will be abbreviated!



If AS/400 is configured to use periods in file names, only "members" of a file are deleted during deletions via FTP, not the entire file. For this reason, in order for a process flow to run correctly, you will need to coordinate additional file handling measures with MPDV.

Configuration –HYDRA (Windows) → Ext. System (Linux) via FTP

Edit entries for HYDRA outbound processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV
License key	SIS-MWV
Command (Windows):	sh.exe ./hyd_zhk.scr MOD=PUT HOST=<server> USER=<ftpuser> PWD=<ftppasswd> LOCAL=./inf_int/interf/HY72ADRCK_TT.dat REMOTE="/pfad/dateiname"
Comment:	Data supply HYDRA → ERP
Interval	5

Configuration – HYDRA (Linux) → Ext. System (AS/400) via FTP

Edit entries for the HYDRA output batch processing in [HYDRA Scheduler](#) (using the EIS-ERP interface as an example):

Parameter name	Value
Product key	SIS-MWV

Parameter name	Value
License key	SIS-MWV
Command (Windows):	./hyd_zhk.scr MOD=PUT HOST=<server> USER=<ftpuser> PWD=<ftppasswd> LOCAL=./inf_int/interf/HY72ADRCK_TT.dat REMOTE="/pfad/dateiname" FTPMODE=A TMP=tmp_HY72ADRCK_TT.dat
Comment:	Data supply HYDRA → ERP
Interval	5



The temporary intermediate file must not have the extension .tmp, otherwise the datasets will be abbreviated!



If AS/400 is configured to use periods in file names, only "members" of a file are deleted during deletions via FTP, not the entire file. For this reason, in order for a process flow to run correctly, you will need to coordinate additional file handling measures with MPDV.

Options for REMOTEMASK/ LOCALMASK

Format Code	Meaning
%a	Abbreviated weekday name
%A	Full weekday name
%b	Abbreviated name of a month
%B	Full name of a month
%c	Date and time display matching local settings
%d	Day of the month as a decimal number (01 - 31)
%H	Hour in a 24-hour format (00 - 23)
%I	Hour in a 12-hour format (01 - 12)
%j	Day of the year as a decimal number (001 - 366)
%m	Month as a decimal number (01 - 12)
%M	Minute as a decimal number (00 - 59)
%p	Display of A.M. or P.M. for the 12-hour format
%S	Second as a decimal number (00 - 59)

Format Code	Meaning
%U	Week of the year as a decimal number, whereas Sunday is the first day of the week (00 - 53)
%w	Weekday as a decimal no. (0 - 6; Sunday is 0)
%W	Week of the year as a decimal number, whereas Monday is the first day of the week (00 - 53)
%x	Date display for local settings
%X	Time display for local settings
%y	Year not including century as a decimal number (00 - 99)
%Y	Year including century as a decimal number
%Z, %Z	Time zone name or abbreviation; no output if time zone is unknown
%%	Percentage

The # flag may prefix any formatting code. In that case, the meaning of the format code is changed as follows.

The # flag may prefix any formatting code. In that case, the meaning of the format code is changed as follows.

Format Code	Meaning
%%a, %%A, %%b, %%B, %%p, %%X, %%z, %%Z, %%%	# flag is ignored.
%%c	Long date and time display matching local settings For example: "Tuesday, March 14, 1995, 12.41: 29".
%%x	Long date display matching local settings For example: "Tuesday, March 14, 1995".
%%d, %%H, %%I, %%j, %%m, %%M, %%S, %%U, %%w, %%W, %%y, %%Y	Remove leading zeros (if any).