

1 Upload of Confirmations

Summary

Confirmation general

HYDRA BDE confirms to SAP on the basis of time tickets. Transferred are the labor data durations from the B-records (personnel postings). They are transferred to SAP together with the personnel number.

Which cost center (e.g. for staff or the workplace) is transmitted to SAP, whether the receiving object is a CO-internal order or a cost center can be configured in the interface. The configuration is explained in chapter **Error! Reference source not found. Error! Reference source not found.**.

Confirmation - direct activity allocation

Segment E1ACC_ACT_ALLOC000

Field name	T	L	Meaning	Meaning in HYDRA		
IGNORE_WARNINGS	Char	1	Ignore warnings	Not occupied		

Segment E1BPDOCHDRP000

Field name	T	L	Meaning	Meaning in HYDRA		
CO_AREA	Char	4	Controlling area	According to configuration		
DOCDATE	Char	8	Document date	Log. Date		
POSTGDATE	Char	8	Posting date	Set according to shift date of the B-records		
VERSION	Char	3	Version	According to configuration*)		
DOC_NO	Char	10	Document number	Not occupied		
VARIANT	Char	5	Fast document entry of CO-actual postings: Variant	According to configuration*)		
DOC_HDR_TX	Char	50	Document header text	Not used		
USERNAME	Char	12	Name of the user	According to configuration*)		
OBJ_KEY	Char	20	Reference key	Not used		
OBJ_TYPE	Char	5	Reference operation	Not used		
OBJ_SYS	Char	10	Logical system of the original document	Not used		

Segment E1BPAAITM002

Field	T	L	Meaning	Meaning in HYDRA		
SEND_CCTR	Char	10	Sending cost center	According to configuration*)		
ACTTYPE	Char	6	Activity type	According to configuration*)		
SENBUSPROC	Char	12	Sending business process	Not used		
ACTVTY_QTY	Char	17	Activities quantity	According to configuration*)		
ACTIVITYUN	Char	3	Activity unit	According to configuration*)		
ACTIVITYUN_ISO	Char	3	ISO-code unit of measurement	Not used		
PRICE	Char	25	Price total in the currency of the transaction	Not used		
CURRENCY	Char	5	Currency key	Not used		
CURRENCY_ISO	Char	3	Iso-code currency	Not used		
POS_OUTQTY	Char	17	Posted output quantity	Not used		
POSTOUTUN	Char	3	Posted output unit	Not used		
POSTOUTUN_ISO	Char	3	ISO-code unit of measurement	Not used		
PERSON_NO	Char	8	Personnel number	Personnel number		
SEG_TEXT	Char	50	Segment text	Not used		
REC_CCTR	Char	10	Receiving cost center	According to configuration*)		
REC_ORDER	Char	12	Receiving order	According to configuration*)		
REC_WBS_EL	Char	24	Receiving project structure element	Not used		
RECSALEORD	Char	10	Receiving sales order	Not used		
RECITEM	Char	6	Position number in recipient sales order	Not used		
RECCOSTOBJ	Char	12	Receiving cost object	Not used		
RECBUSPROC	Char	12	Receiving business process	Not used		
REC_NETWRK	Char	12	Receiving network	Not used		
RECOOPERATN	Char	4	Receiving network operation	Not used		
RECRUNSCHD	Char	12	Receiving repeat order	Not used		
MATERIAL	Char	18	Receiving material	Not used		
PROD_VERSN	Char	4	Production version of the recipient material	Not used		
PLANT	Char	4	Plant of the recipient material	Not used		
RECPRCMTPROC	Char	12	Receiving procurement process	Not used		
ITEMNO_ACC	Char	10	Position number of the accounting document	Not used		
REC_CALC_MOTIVE	Char	2	Recipient calculation motive	Not used		
RECACTTYPE	Char	6	Receiving activity type	Not used		

Field	T	L	Meaning	Meaning in HYDRA		
SRE_COMP_CODE	Char	4	Company code of the sending real estate object	Not used		
SRE_BUS_ENT	Char	8	Sending business unit real estate	Not used		
SRE_PROPERTY	Char	8	Sending lot of land real estate	Not used		
SRE_BUILDING	Char	8	Sending building real estate	Not used		
SRE_RENT_UNIT	Char	8	Sending rental unit real estate	Not used		
SRE_LEASE	Char	13	Sending rental agreement real estate	Not used		
SRE_MGMT_CON	Char	13	Sending administration agreement	Not used		
SRE_INC_EXP	Char	4	Sending incidental costs key real estate	Not used		
SRE_SETT_UNIT	Char	5	Sending accounting unit real estate	Not used		
SRE_REF_DATE	Char	8	Sending reference date settlement real estate	Not used		
SRE_CON_NO	Char	13	Sending contract real estate	Not used		
RRE_COMP_CODE	Char	4	Company code of the receiving real estate object	Not used		
RRE_BUS_ENT	Char	8	Receiving business unit real estate	Not used		
RRE_PROPERTY	Char	8	Receiving lot of land real estate	Not used		
RRE_BUILDING	Char	8	Receiving building real estate	Not used		
RRE_RENT_UNIT	Char	8	Receiving rental unit real estate	Not used		
RRE_LEASE	Char	13	Receiving rental agreement real estate	Not used		
RRE_MGMT_CON	Char	13	Receiving administration contract	Not used		
RRE_INC_EXP	Char	4	Receiving incidental costs key real estate	Not used		
RRE_SETT_UNIT	Char	5	Receiving accounting unit real estate	Not used		
RRE_REF_DATE	Char	8	Receiving reference date settlement real estate	Not used		
RRE_CON_NO	Char	13	Receiving contract real estate	Not used		
MATERIAL_EXTERNAL	Char	40	Long material number (future development) for the field MATER	Not used		
MATERIAL_GUID	Char	32	External GUID (future development) for the field MATERIAL	Not used		
MATERIAL_VERSION	Char	10	Version number (future development) for the field MATERIAL	Not used		

Confirmation - indirect activity allocation

Segment E1ACC_SENDER_ACTIVITIES

Field name	T	L	Meaning	Meaning in HYDRA		
IGNORE_WARNINGS	Char	1	Ignore warnings	Not occupied		

Segment E1BPDOCHDRP000

Field name	T	L	Meaning	Meaning in HYDRA		
CO_AREA	Char	4	Controlling area	According to configuration*)		
DOCDATE	Char	8	Document date	Log. Date		
POSTGDATE	Char	8	Posting date	Set according to shift date of the posting records		
VERSION	Char	3	Version	according to configuration*)		
DOC_NO	Char	10	Document number	Not occupied		
VARIANT	Char	5	Fast document entry of CO-actual postings: Variant	According to configuration*)		
DOC_HDR_TX	Char	50	Document header text	Not used		
USERNAME	Char	12	Name of the user	According to configuration*)		
OBJ_KEY	Char	20	Reference key	Not used		
OBJ_TYPE	Char	5	Reference operation	Not used		
OBJ_SYS	Char	10	Logical system of the original document	Not used		

Segment E1BPJAITM000

Field name	T	L	Meaning	Meaning in HYDRA		
SEND_CCTR	Char	10	Sending cost center	according to configuration*)		
ACTTYPE	Char	6	Activity type	according to configuration*)		
SENBUSPROC	Char	12	Sending business process	Not used		
ACTVTY_QTY	Quan	15.3	Activities quantity	according to configuration*)		
ACTIVITYUN	Char	3	Activity unit	according to configuration*)		
ACTIVITYUN_ISO	Char	3	ISO-code unit of measurement	Not used		
POS_OUTQTY	Quan	15.3	Posted output quantity	Not used		
POSTOUTUN	Char	3	Posted output unit	Not used		
POSTOUTUN_ISO	Char	3	ISO-code unit of measurement	Not used		
PERSON_NO	Numc	8	Personnel number			
SEG_TEXT	Char	50	Segment text	Not used		

