

1 Password of the HYDRA Database

Overview

HYDRA uses a separate database user and database password to access the corresponding database system. The database user "hydadm" is created along with a default password if it is a HYDRA standard installation.

This document describes how the database password can be changed on the database level and how HYDRA is informed about the password in encrypted manner.

The database password is transferred to the HYDRA console in an encrypted form; this prevents the database password from being read in an uncoded manner on the server or the client.

References to other documentation

Changing the HYDRA DB user password

Notes



Oracle and SQL server have a **separate user administration**. Consequently, the database user hydadm is not identical to the HYDRA administrator (hydadm).

Password change

The password of the HYDRA DB user "hydadm" can be changed as follows:

1. Exit HYDRA using the HYDRA Manager
2. Change the password as follows:

→ ORACLE

The database user is not identical to the HYDRA administrator (hydadm).

Start sqlplus and log in as user hydadm.

```
d:\hydra> sqlplus
```

Enter password and upon request, enter the old and the new password incl. confirmation (Syntax PASSW[ORD] [username]):

```
SQL> password
```

Changes the password for HYDADM

Old password: *****

New password: *****

Enter the new password once more: *****

```
SQL> exit
```

→

Start the SQL Server Enterprise Manager. Choose the server from the left-hand side. Select "security" and click the "user name". In the detail area right click the user name to be changed and then select "properties". Enter a new password within the "password" field of the "general" tab and confirm the password.

3. Start an MS-DOS prompt and go to the HYDRA installation directory.

4. Now change the configuration as follows:

→

Enter the following entries that assign the new password (HYDBPW) to the user (HYDBUSER) hydadm in the "environment" section of hymap.cfg.

...

[Environment]

...

HYDBUSER=hydadm

HYDBPW={ new password}

...

Install the modified hymap.cfg file, in this context, the password of the **Windows user hydadm** is to be specified.

Please note: The Windows user is not identical to the Oracle user!

```
d:\hydra> ntinst -if hymap.cfg
```

→

Enter the following rows in hy_env.scr:

```
export HYDBUSER=hydadm
```

```
export HYDBPW={ New password}
```

5. Check the database connection via the "projekt" program. The program should output "HYDRA" or the set project. In the event of an error, a database error including the corresponding "sqlcode" occurs. Check the values entered in the configuration in cases of error and repeat step 4.

→  **Windows**

d:\hydra> **projekt.exe**

→  **UNIX**


/usr/hydra> **projekt.out**

6. Start HYDRA using the Hydra-Manager.

Generate encoded database password

The database password (HYDBPW) is defined in an encoded form on the HYDRA server.

The tool "DB-Password-Generator" generates an encrypted password for the specified user and the entered password (that has a maximum of ten characters).



This generated password (32 characters long) is to be entered as the new password and tested as described in section 2.2.

The "**hyd_pwd.exe**" program is provided in the following directory on the HYDRA server:

<HYDRADIR>/admtools/hyd_pwd

For installation purposes, copy the directory on a Windows PC and run the program "**hyd_pwd.exe**".

Other database users and passwords

Irrespective of HYDRA, different database users are created by the respective database system. The sections that follow describe these database users and their relation to HYDRA and MPDV Support.

ORACLE database

INTERNAL user

Used by MPDV:

MPDV uses this user to create the ORACLE instance.

MPDV Support uses this user to view the database.

Password can be changed:

YES

Password is changed by:

MPDV

MPDV Support has to be informed about the modification and the new password.

DBSNMP user

Used by MPDV:

MPDV does not use this user

Password can be changed:

YES

Password is changed by:

MPDV

Please note:

This user should not be deleted as it might be used by ORACLE Support.

OUTLN user

Used by MPDV:

MPDV does not use this user

Password can be changed:

YES

Password is changed by:

MPDV

Please note:

This user should not be deleted as it might be used by ORACLE Support.

SYS user

Used by MPDV:

MPDV Support uses this user to view the database.

Password can be changed:

YES

Password is changed by:

MPDV

MPDV Support has to be informed about the modification and the new password.

SYSTEM user

Used by MPDV:

MPDV Support uses this user to view the database.

Password can be changed:

YES

Password is changed by:

MPDV

MPDV Support has to be informed about the modification and the new password.

Microsoft SQL Server database

sa user

Used by MPDV:

MPDV uses this user to create the database instance and database.

MPDV Support uses this user to view the database.

The database user "sa" is created along with a default password if it is a HYDRA standard installation.

Password can be changed:

YES

Password is changed by:

MPDV

MPDV Support has to be informed about the modification and the new password.

hydadm user

Used by MPDV:

MPDV Support uses this user to view the database.

Password can be changed:

YES

Password is changed by:

MPDV

MPDV Support has to be informed about the modification and the new password.