

1 Transferring Account Balances

A person's current account balances can be set using the PNRKTO.UPDATE dialog.

To perform account modifications, the following combination of values can be transferred:

Combination	Compensation in HYDRA	Logging (e.g. in the "Account journal" list)
New account balance	The actual current account balance will be set to the new account balance that was transferred.	The actual old account balance is revised by the difference made up of the new to the old balance.
Account modification	The actual current account balance is revised by the transferred account modification.	The actual account balance is revised by the transferred modification.
New and old account balance	The desired modification is derived from the difference between the transferred old and new account balance. The actual current account balance is revised by the calculated account modification.	The old transferred account balance is revised by the calculated modification. Please keep in mind that the transferred account balance may deviate from the actual account balance at the time of the modification.

The details about the account balances and the account modifications are provided in different formats and do not depend on the account type:

1. Time accounts

The values are transferred in seconds for time accounts. Example: To achieve an account modification of one hour, the value "|PNRKTO.KTODIFF=3600|" is transferred. If there are any decimal places, these are ignored.

2. Day accounts

For day accounts, the values are expected as decimal places. Example: To achieve an account modification to the leave account by four and a half days, the value "|PNRKTO.KTODIFF=4.5|" is transferred. If there are any decimal places, they are only considered allowing for the number of decimal places defined at the time the accounts were configured.

If the value is negative, a minus sign is placed in front of the number.

1.1 Parameters for transferring the balance accounts

In the "Must" column in the table shown below you will see IDs that show the fields where the dialogs are necessary:

U For UPDATE

The following parameters are available:

Dialog: PNRKTO.UPDATE				
Parameter	Type	Must	Content	Description
PNRKTO.FIR	C4		Company	Person's company
PNRKTO.PNR	N8	U	Personnel number	Person's personnel number
PNRKTO.KTO	N1	U	Account number (1 to 8)	Number of the account to be modified. The assignment is shown at the console when the PZE accounts are configured.
PNRKTO.KTODIFF	N9.3	see above	Account modification	
PNRKTO.KTOSTAND	N9.3	see above	Old account balance	
PNRKTO.KTOSTAND:Z	N9.3	see above	New account balance	

1.2 Data record as an example of an account modification

The following example reduces the account balance of the account with the number 4 (usually a leave account) by one day:

DLG=PNRKTO.UPDATE | PNRKTO.PNR=906000 | PNRKTO.KTO=4 | PNRKTO.KTODIFF=-1.0 |