

1 Download of Master Data

Download of the work centers

SAP allows to download workcenters to run plausibility checks in the subsystem. These work centers can be transferred to HYDRA.

When these work centers will be transferred, the system will check for the respective SAP work center in the HYDRA configuration order standard whether an entry is stored for this SAP work center by which this entry will be transferred as HYDRA workplace. In the beginning, the workplace will be created with the responsibility area "SAP" by the user "SAP". Due to this it is necessary to create the user "SAP" and to assign it then to the responsibility area "SAP". During the adoption workplaces will be inserted or updated. Deletions are not possible.

Since work centers are only unique within a plant in SAP; it must be configured in HYDRA for which plant you wish to adopt the work centers. This configuration is made in the HYDRA Ini-configuration.

Name: PP-PDC

Section: PPCC2RECWORKCENTER

Key: Plant, for which the work centers are to be adopted, e.g. 1000

Value: <BLANK> (no value must be entered here)

Field name	T	L	D	Description	Usage in HYDRA
SOURCE_SYS	CHAR	10	0	Logical system	Not used
WORK_CNTR	CHAR	8	0	Work center	HYDRA machine/ workplace
PLANT	CHAR	4	0	Plant	Plant
SUBSYSTEM_GROUPING	CHAR	3	0	BDE group	Transfer to HYDRA
WORK_CNTR_DESCR	CHAR	40	0	Short text on the work center	Comment
VALID_START	DATS	8	0	Start of validity of the current cost center link	The data record will only be adopted when the current date is within this interval.
VALID_END	DATS	8	0	End of validity of the current cost center link	The data record will only be adopted when the current date is within this interval.
CO_AREA	CHAR	4	0	Controlling area of the current cost center link	Not used
COST_CNTR	CHAR	10	0	Cost center of the current cost center link	Cost center
ACTI1_TEXT	CHAR	20	0	Activity 1: Activity text	Not used
ACTI1_UNIT	UNIT	3	0	Activity 1: Activity unit	Not used
ACTI1_UNIT_ISO	CHAR	3	0	Activity 1: ISO code of the quantity unit	Not used
NOACTI1	CHAR	1	0	Activity 1: Indicator: Do not show activity text	Not used
RECORD_GRP1	NUMC	1	0	Activity 1: Record type group	Not used
ACTI2_TEXT	CHAR	20	0	Activity 2: Activity text	Not used
ACTI2_UNIT	UNIT	3	0	Activity 2: Activity unit	Not used

Field name	T	L	D	Description	Usage in HYDRA
ACTI2_UNIT_ISO	CHAR	3	0	Activity 2: ISO-code of the quantity unit	Not used
NOACTI2	CHAR	1	0	Activity 2: Indicator: Do not show activity text	Not used
RECORD_GRP2	NUMC	1	0	Activity 2: Record type group	Not used
ACTI3_TEXT	CHAR	20	0	Activity 3: Alternative activity text	Not used
ACTI3_UNIT	UNIT	3	0	Activity 3: Activity unit	Not used
ACTI3_UNIT_ISO	CHAR	3	0	Activity 3: ISO code of the quantity unit	Not used
NOACTI3	CHAR	1	0	Activity 3: Indicator: Do not show activity text	Not used
RECORD_GRP3	NUMC	1	0	Activity 3: Record type group	Not used
ACTI4_TEXT	CHAR	20	0	Activity 4: Activity text	Not used
ACTI4_UNIT	UNIT	3	0	Activity 4: Activity unit	Not used
ACTI4_UNIT_ISO	CHAR	3	0	Activity 4: ISO code of the quantity unit	Not used
NOACTI4	CHAR	1	0	Activity 4: Indicator: Do not show activity text	Not used
RECORD_GRP4	NUMC	1	0	Activity 4: Record type group	Not used
ACTI5_TEXT	CHAR	20	0	Activity 5: Alternative activity text	Not used
ACTI5_UNIT	UNIT	3	0	Activity 5: Activity unit	Not used
ACTI5_UNIT_ISO	CHAR	3	0	Activity 5: ISO code of the quantity unit	Not used
NOACTI5	CHAR	1	0	Activity 5: Indicator: Do not show activity text	Not used
RECORD_GRP5	NUMC	1	0	Activity 5: Record type group	Not used
ACTI6_TEXT	CHAR	20	0	Activity 6: Activity text	Not used
ACTI6_UNIT	UNIT	3	0	Activity 6: Activity unit	Not used
ACTI6_UNIT_ISO	CHAR	3	0	Activity 6: ISO code of the quantity unit	Not used
NOACTI6	CHAR	1	0	Activity 6: Indicator: Do not show activity text	Not used
RECORD_GRP6	NUMC	1	0	Activity 6: Record type group	Not used
CO_BUSPROC	CHAR	12	0	Business process	Not used
CO_BUSPROC_NAME	CHAR	20	0	General designation of the business process	Not used
COST_DRIVER	UNIT	3	0	Activity unit CO-ABC on the business process	Not used
COST_DRIVER_ISO	CHAR	3	0	Activity unit CO-ABC according to ISO on the business process	Not used

Download of the deviation reasons

SAP allows to download deviation reasons to run plausibility checks in the subsystem. These deviation reasons can be transferred to HYDRA.

When the deviation reasons are transferred, the system will first create a reason text with the number transferred from SAP. Then a reason together with the number transferred from SAP and referring to the created reason text will be created.

In the beginning, the reason texts and reasons are created by the "SAP" user. This user must exist in the system as HYDRA user. During the transfer reasons/ reason texts will be inserted or updated. Deletions are not possible.

Since deviation reasons are only unique within a plant in SAP, it must be configured in HYDRA for which plant you wish to transfer the deviation reasons. This configuration is made in the HYDRA Ini-configuration.

Name: PP-PDC

Section: DIFFE2

Key: Plant, for which the reasons are to be transferred, e.g. 1000

Value: Reason type
A Scrap
N Rework
P Problem quantity
G Yield
L Batch logs

Field name	Type	L		Meaning	Usage in HYDRA
WERKS	CHAR	4		Plant	Plant
REASON	CHAR	4		Variation cause	ID Reason Text ID Reason
GRDTX	CHAR	25		Text stating the reasons of the deviation	Scrap reason
SOURCE_SYS	CHAR	10		Logical system	Not used

Download of generally applicable units

SAP allows to download generally applicable units to run plausibility checks in the subsystem. These generally applicable units can be transferred to HYDRA.

In the beginning, the units are created by the "SAP" user. This user must exist in the system as HYDRA user. During the transfer the units will be inserted or updated. Deletions are not possible.

During the transfer the SI-units will not be identified and the ISO code for the units cannot be transferred.

Field name	Type	L	D	Meaning	Usage in HYDRA
MSEHI	CHAR	3		Quantity unit (internal key)	Not used
MSEHE	CHAR	3		Quantity unit (external key)	Unit
NENNR	CHAR	10		Denominator for the conversion into SI-unit	Not used
ZAEHL	CHAR	10		Numerator for the conversion into SI-unit	Not used
MSSIE	CHAR	3		SI-unit (internal key)	Not used
MSEHL	CHAR	25		Text on the quantity unit	Text on the quantity unit
ANDEC	CHAR	3		Number of decimal places	Not used
SOURCE_SYS	CHAR	10		Logical system	Not used

Download of material-dependent units

SAP allows to download material-dependent units to run plausibility checks in the subsystem. These units can be transferred to HYDRA.

In the beginning, the units are created by the "SAP" user. This user must exist in the system as HYDRA user. During the transfer the units will be inserted or updated. Deletions are not possible.

Field name	Type	L	D	Meaning	Usage in HYDRA
MATNR	CHAR	18		Material	Material
MEINH	CHAR	3		Alternative quantity unit of the material (internal key)	Unit of
MEINS	CHAR	3		Base quantity unit of the material (internal key)	Unit by
UMREZ	CHAR	7		Numerator for the conversion of alternatives in stock keeping unit	Numerator
UMREN	CHAR	7		Denominator for the conversion of alternatives in stock keeping unit	Denominator
SOURCE_SYS	CHAR	10		Logical system	Not used

