

1 Bonus Reasons

Summary

Menu	Master Data → Incentive Wages → Bonus Reasons
Transaction code	bonrea
Function authorization	bonrea.*

Bonus reasons are configured in this application.

The screenshot shows the 'Bonus reasons' application window. It features a top toolbar with icons for Request data, Cancel, Print preview, Print all, Insert, Copy, Edit, Delete, Save, and Help. Below the toolbar is a 'Selection' section with fields for Reason, Designation, and a checkbox for 'Show authorized entries only'. The main area is divided into two panes. The left pane displays a table of bonus reasons, and the right pane shows configuration details for a selected reason.

Reason	Designation	Affects
1	Machine malfunction	Target time
2	Material shortage	Target time
3	Missing carrier	Target time
10	Rework/common	Actual time
11	Rework/Chamfering	Actual time
12	Rework/Assembly	Actual time
20	Slower machine	Target time
30	Filter missing	Target time
50	Practice	Target time
55	Practice assistance	Target time
200	Tool damage	Actual time
500	Faster machine	Target time
510	Filter cooperation	Target time

Bonus reason configuration details:

- Reason: 1 ... Machine malfunction
- Designation: Machine malfunction
- Affects: ☒ Target time ☐ Actual time
- Posting indicator:
- Responsibility area:
- Entry:
 - BDE authorization: 3
 - ☒ Authorization required
 - ☐ Allocate if still subject to authorization
- Last editing:
 - Modified by: Miller
 - Modified on: 2/26/2003 4:25:27 PM

Selection Criteria

The application provides the following selection criteria:

Show authorized entries only

Bonus reasons are assigned to a responsibility area. If this option is checked only those bonus reasons are displayed for which the user has the corresponding responsibility area authorization for editing. Provided that the option is not active, all other bonus reasons may be displayed but not edited.

Field Descriptions

Reason, designation

Number and description of the bonus reason.

Affects

Affects target time or actual time when group bonuses are computed. Consequently, the bonus is processed as credit above the fraction line (target time) or below the fraction line (actual time), when the performance efficiency rate is calculated for the premium group.

This option does not affect bonuses for individual piecework. These bonuses/deductions are always charged to the standard time of piecework.

Posting indicator

Optional input. If this field includes "-AKK" bonuses/deductions with this bonus/deduction reason are not offset with piecework time tickets. This allows for any data to be recorded with bonuses/deductions, which exactly is not to be charged to piecework time tickets. The field is also used in premium/incentive wages based on formulas.

Responsibility area

Responsibility area to check authorizations. The responsibility area may also remain empty.

BDE authorization

If the bonus is entered by operators at the terminal: Authorization level for terminal postings. The person sending the posting must at least have the authorization level that is entered here. If no authorization level is entered the person sending the posting must at least be assigned to level 3.

Authorization required

If the bonus is entered by operators at the terminal:

If this option is checked the bonus requires approval if it is entered at the terminal.

If the bonus is entered by an administrator at the HYDRA client it is automatically considered as being approved.

Allocate if still subject to authorization

If the bonus is entered by operators at the terminal: If this option is checked the bonus is allocated for the computing of wages even if it is still subject to authorization. If the option is not checked bonuses that are subject to authorization are only allocated, once they have been approved.