

1 Configuration of Accounts

Overview

Menu	Master Data → Labor time → Configuration of Accounts
Transaction code	paco
Function authorization	paco

The accounts of the HYDRA PZW (Personnel Time Management) are continuous balances that are kept in hours or days (contrary to wage types always starting from 0 at the beginning of a month).

You can keep up to eight continuous accounts. Use this dialog to activate the accounts and specify their processing and name.

Configuration of accounts

Main page | Profile

Request data | Cancel | Print preview | Print all | Edit | Save | Help on operation | Help on application | Help on detail application | Help

Configuration of accounts

Drag a column here to group by that column

Account	Designation	Active	Account type	Decimal places	Responsibility area
1	Flextime	☒	Time account	0	
2	Overtime	☒	Time account	0	
3	Flexible time	☒	Time account	0	
4	Leave account	☒	Day account	0	
5	Monthly account	☒	Time account	0	
6		☐	Time account	0	
7		☐	Time account	0	
8		☐	Time account	0	

Configuration of accounts

Account: 1

Designation: Flextime

☒ Active

Account type: ☒ Time account ☐ Day account

Decimal places: ☒ 0 ☐ 1 ☐ 2 ☐ 3

Responsibility area:

Sorting

Account lists: 1

Terminal information: 1

Time sheet: 1

Account limits: 1

Upload positive account balances

☐ Upload positive account balances

Wage type: ...

Designation:

Upload negative account balances

☐ Upload negative account balances

Wage type: ...

Designation:

Sign: ☒ Positive ☐ Negative

Last editing

Modified by: Miller

Modified on: 3/2/2000 11:37:15 AM

Purpose

The number of accounts is fixed at 8. For this reason, the buttons *Insert*, *Copy* and *Delete* are not available.



The leave entitlement defined in the [HR master data](#) is offset using account 4. Use account 4 as leave account for this reason.

Field descriptions

Account, Designation

Number of the account ranging between 1 and 8 and its name.

Active

Status of account. Only an active account is used for bookings and can be evaluated.

Account type

Time account for keeping the account in hours and minutes.

Day account for keeping the account in days (e.g. leave).

Decimal places

With time accounts, the number of decimal places is zero.

With day accounts, you can define the number of decimal places. For example, if you have defined one decimal place for the leave account, you can offset half a leave day.



If you make changes in field *Decimal places* or if you change the *Account type* during running operation, this can cause wrong account balances and a wrong display.

Sorting of account lists, terminal information, time sheets, account limits

Sorting order of the accounts (position 1-8, 1 = first position) in the [account lists](#), the [terminal information](#) and the [time sheet](#). If the *Sorting* field remains empty, the account is not displayed in the respective application.

In field *Account limitation*, you can specify the order used to [limit the accounts](#). For example, you can use this setting if you repost from one account to another and you then want to limit the target account.



Terminals of the manufacturer Kaba Benzing and of type CTP-340 can only show a maximum of 4 accounts.

Green from, Green to, Yellow from, Yellow to

These fields of the group *Account indicator* specify the color used for the relevant account balance in the reports [Current account balances](#), the [Monthly results](#) and in the [Personnel scheduling](#). Account balances outside of the yellow range are displayed in red. If these fields remain empty, no color is used to highlight the fields.



These fields are only available if the extension [ColoredAccountBalances](#) is enabled.

Upload positive/negative account balance, Wage type, Sign

Use these options to specify whether the positive or negative account balance of an account is posted to the *Wage type* in the [Monthly results](#) so that the account balance is uploaded to the payroll accounting with the other wage types. Only few interfaces support the upload of wage types with negative duration. For this reason, it might be required to enter different wage types for positive and negative account balances and to convert the algebraic sign to a "positive" sign for negative account balances.



In addition to the application *Configuration of accounts* where you can define the accounts displayed on the terminal for the entire system, there is the application [Configuration terminal information](#) where you can overwrite the accounts displayed on the terminal and their names for entire companies, groups of persons (department, area, cost center,...) and for separate persons.