

1 Configuration of RFC Connections

RFC Server (MES inbound processing)

Parameter	Entry / Value
TYPE	The type of the server program depends on its behavior/performance. The entry "R" means that the server registers to an SAP gateway and is the default entry. STANDARD: "R"
PROGID	PROGID designates the name by which the server registers to the gateway. The entry in this field has to correspond to the entry for ALE customizing (SAP transaction SM59). STANDARD: "HYDRA_RFC_DISPATCH"
GWHOST	GWHOST designates the host name of the SAP system. This name can be requested from the system administrator of the SAP system.
GWSERV	GWSERV designates the service name/instance of the SAP gateway. This number can be requested from the system administrator of the SAP system. Please note that the number has to start with "sapgw". Example: sapgw00
RFC_TRACE	This entry specifies whether or not a log file is to be written by the SAP RFC library when receiving data from SAP R/3 using the RFC connection. Possible entries are: 0 → no tracing 1 → with tracing

RFC Client (MES outbound processing)

Parameter	Entry / Value
TYPE	The client type is to be entered. "3" has to be entered for the MLE client. STANDARD: "3"
ASHOST	ASHOST designates the host name of the specific application server. This name can be requested from the system administrator of the SAP system.
SYSNR	SYSNR designates the SAP system number. This number is to be requested from the system administrator of the SAP system. The number of the gateway has to be provided without "sapgw". The entry for an SAP system with instance "sapgw01" is therefore "01".
CLIENT	The SAP client number is to be entered here. This number is to be requested from the system administrator of the SAP system.
USER	The client logs on accordingly to access an SAP system. Normally, users do not have dialog authorizations and, as a result, they are no security risk.
PASSWD	Password to log in with the above-mentioned user. The password is encoded. The password has to be entered twice for confirmation purposes.

Parameter	Entry / Value
TRACE	This value specifies whether or not a log file is to be written when sending data to SAP R/3 using the RFC connection. Possible values are: 0 → without tracing 1 → with tracing
LANG	The value in the LANG field specifies the login language to the SAP system. STANDARD: "D" PLEASE NOTE: The language configured here has to match the language of the SAP system!!
RECONNECT_COUNT	RECONNECT_COUNT indicates how many attempts the client has to do if no connection can be established. STANDARD: "3"
RECONNECT_TIME	RECONNECT_TIME specifies the time in seconds the client waits between two connection attempts. STANDARD: "10"
RFC_DESTINATION_FOR_TRFC	If the PP-PI-PCS interface is in use this parameter defines to which RFC destination (defined in the transaction SM59 of SAP) return messages are to be sent by SAP. Generally, this entry corresponds to the RFC destination created for the SAP download.
Configuration of load balancing	
MSHOST	Host name of the SAP message server

Parameter	Entry / Value
MSSERV	Service of the SAP message server
R3NAME	Name of the SAP system
GROUP	Name of the application server group
USE_LOAD_BALANCING	Enabling of the Load Balancing mode; active = "1", inactive = "0"
IDoc settings	
Port number	The port number designates the physical place of data transfer in SAP. This place is determined for MLE within ALE customizing. In R/3 it can be determined via the port definition (SAP transaction WE21) or using the partner profile (SAP transaction WE20). The SAP system administrator can be asked for the port number of the R/3 system. The port mostly consists of "SAP" + system name. An SAP system with the name "CE6" has, for example, the following port number: "SAPCE6". Please note: R/3 assigns the port number for older SAP releases (incl. 4.0). They have the following form: Axxxxxxxxx.
Partner type	Logical systems specify the partner type. Generally, it corresponds to "LS".
Partner number	The partner number is the name of the logical system, with which the subsystem has been configured within ALE customizing. Please refer to the SAP distribution model for details on this (SAP transaction BD64). The SAP administrator can be asked for the partner number of the SAP system.



The port to be used has to be configured additionally on operating system level to establish the connection to a Load Balancing SAP system.

C:\WINDOWS\system32\drivers\etc\services

→ e.g.: sapmsCL1 3665/tcp