- 1. http://downloads.raspberrypi.org/raspbian/images/raspbian-2017-04-10/
- 2. https://github.com/dhruvvyas90/qemu-rpi-kernel

```
$ mkdir ~/qemu_vms/
```

Download:

```
$ sudo apt-get install qemu-system
$ unzip <image-file>.zip
$ fdisk -1 <image-file>
```

```
Disk 2017-03-02-raspbian-jessie.img: 4.1 GiB, 4393533440 bytes, 8581120 sectors

Units: sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disklabel type: dos

Disk identifier: 0x432b3940

Device Boot Start End Sectors Size Id Type

2017-03-02-raspbian-jessie.img1 8192 137215 129024 63M c W95 FAT32 (LBA)

2017-03-02-raspbian-jessie.img2 137216 8581119 8443904 4G 83 Linux
```

You see that the filesystem (.img2) starts at sector 137216. Now take that value and multiply it by 512, in this case it's 512 * 137216 = 70254592 bytes. Use this value as an offset in the following command:

```
$ sudo mkdir /mnt/raspbian
$ sudo mount -v -o offset=70254592 -t ext4 ~/qemu_vms/<your-img-file.img> /mnt/raspbian
```

\$ sudo nano /mnt/raspbian/etc/ld.so.preload

Comment out every entry in that file with '#', save and exit with Ctrl-x » Y.

\$ sudo nano /mnt/raspbian/etc/fstab

IF you see anything with mmcblk0 in fstab, then:

1. Replace the first entry containing /dev/mmcblk0p1 with /dev/sda1

\$ cd ~
\$ sudo umount /mnt/raspbian


Now you can emulate it on Qemu by using the following command:

\$ qemu-system-arm -kernel ~/qemu_vms/<your-kernel-qemu> -cpu arm1176 -m 256 -M versatilepb serial stdio -append "root=/dev/sda2 rootfstype=ext4 rw" -hda ~/qemu_vms/<your-jessieimage.img> -redir tcp:5022::22 -no-reboot

If you see GUI of the Raspbian OS, you need to get into the terminal. Use Win key to get the menu, then navigate with arrow keys until you find Terminal application as shown below.



From the terminal, you need to start the SSH service so that you can access it from your host system (the one from which you launched the qemu).



Now you can SSH into it from your host system with (default password – raspberry):

```
$ ssh pi@127.0.0.1 -p 5022
```

Troubleshooting

```
$ sudo update-rc.d ssh enable
```

If your emulated Pi starts the GUI and you want to make it start in console mode at startup, use the following command inside you

```
$ sudo raspi-config
>Select 3 - Boot Options
```

```
>Select B1 - Desktop / CLI
>Select B2 - Console Autologin
```

If your mouse doesn't move in the emulated Pi, click <Windows>, arrow down to Accessories, arrow right, arrow down to Terminal, enter.

Resizing the Raspbian image

Once you are done with the setup, you are left with a total of 3,9GB on your image, which is full. To enlarge your Raspbian image, follow these steps on your Ubuntu machine:

Create a copy of your existing image:

```
$ cp <your-raspbian-jessie>.img rasbian.img
```

```
$ qemu-img resize raspbian.img +6G
```

Now start the original raspbian with enlarged image as second hard drive:

```
$ sudo qemu-system-arm -kernel ~/qemu_vms/<kernel-qemu> -cpu arm1176 -m 256 -M versatilepb -
serial stdio -append "root=/dev/sda2 rootfstype=ext4 rw" -hda ~/qemu_vms/<your-original-
raspbian-jessie>.img -redir tcp:5022::22 -no-reboot -hdb raspbian.img
```

```
$ sudo cfdisk /dev/sdb
```

Delete the second partition (sdb2) and create a **New** partition with all available space. Once new partition is creates, use **Write** to commit the changes. Then **Quit** the cfdisk.

Resize and check the old partition and shutdown.

```
$ sudo resize2fs /dev/sdb2
$ sudo fsck -f /dev/sdb2
$ sudo halt
```

```
$ sudo qemu-system-arm -kernel ~/qemu_vms/<kernel-qemu> -cpu arm1176 -m 256 -M versatilepb -
serial stdio -append "root=/dev/sda2 rootfstype=ext4 rw" -hda ~/qemu_vms/raspbian.img -redir
tcp:5022::22
```

Advanced Networking

In some cases you might want to access all the ports of the VM you are running in QEMU. For example, you run some binary which opens some network port(s) that you want to access/fuzz from your host (Ubuntu) system. For this purpose, we can create a shared network interface (tap0) which allows us to access all open ports (if those ports are not bound to 127.0.0.1). Thanks to @0xMitsurugi for suggesting this to include in this tutorial.

This can be done with the following commands on your **HOST** (Ubuntu) system:

```
azeria@labs:~ $ sudo apt-get install uml-utilities
azeria@labs:~ $ sudo tunctl -t tap0 -u azeria
azeria@labs:~ $ sudo ifconfig tap0 172.16.0.1/24
```

After these commands you should see the tap0 interface in the ifconfig output.

```
azeria@labs:~ $ ifconfig tap0

tap0: flags=4099<UP,BROADCAST,MULTICAST> mtu 1500

inet 172.16.0.1 netmask 255.255.255.0 broadcast 172.16.0.255

ether 22:a8:a9:d3:95:f1 txqueuelen 1000 (Ethernet)

RX packets 0 bytes 0 (0.0 B)

RX errors 0 dropped 0 overruns 0 frame 0

TX packets 0 bytes 0 (0.0 B)

TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

You can now start your QEMU VM with this command:

```
azeria@labs:~ $ sudo qemu-system-arm -kernel ~/qemu_vms/<kernel-qemu> -cpu arm1176 -m 256 -M versatilepb -serial stdio -append "root=/dev/sda2 rootfstype=ext4 rw" -hda ~/qemu_vms/rasbian.img -net nic -net tap,ifname=tap0,script=no,downscript=no -no-reboot
```

When the QEMU VM starts, you need to assign an IP to it's eth0 interface with the following command:

```
pi@labs:~ $ sudo ifconfig eth0 172.16.0.2/24
```

If everything went well, you should be able to reach open ports on the **GUEST** (Raspbian) from your **HOST** (Ubuntu) system. You can test this with a netcat (nc) tool (see an example below).