# **Computer Architecture**

Floating Point Notes (Section 3.5)

## **Binary Real Numbers:**

A decimal point shows the dividing line between non-negative and negative exponents in decimal numbers

$$15.345 = 1 \times 10^{1} + 5 \times 10^{0} + 3 \times 10^{-1} + 4 \times 10^{-2} + 5 \times 10^{-3}$$
$$= 10 + 5 + 3/10 + 4/100 + 5/1000$$

A <u>binary point</u> shows the dividing line between non-negative and negative exponents in binary numbers

10.101 = 
$$1 \times 2^{1} + 0 \times 2^{0} + 1 \times 2^{-1} + 0 \times 2^{-2} + 1 \times 2^{-3}$$
  
=  $2 + 0 + 1/2 + 0/4 + 1/8$   
= 2.625 decimal

### Normalized Floating Point Representation:

1.xxxxx X 2<sup>yyyy</sup>

.xxxx is the <u>fraction</u> (or <u>mantissa</u>) given here in binary

yyyy is the <u>exponent</u> given here in decimal

For a normalized representation, the value of yyyy is increased or decreased to assure that 1 (not 0 or 10 or 11 or 100 etc.) is to the left of the binary point

The fraction represents an unsigned value between 0 and 1 (the sign bit is handled separately, floating point does not use 2's complement)

### *IEEE 754 Floating-Point Standard:*

**Single Precision** 

32 bits -> 1 sign bit, 8 exponent bits, 23 fraction bits

**Double Precision** 

64 bits -> 1 sign bit, 11 exponent bits, 52 fraction bits

#### Sign Bit

0 for positive, 1 for negative

### **Exponent Bits**

1) 1-254 (single precision) or 1-2046 (double precision)

Bias signed exponent value

1 most negative exponent value

254, 2046 most positive exponent value

127, 1023 exponent value of 0

Using biased notation for exponents and placing bits in the order sign, then exponent, then fraction allows standard integer sorting algorithms to work properly on floating point numbers

- 2) All zeros
  - a) Fraction all zeros -> floating point 0.0
  - b) Fraction not all zeros -> denormalized number (don't worry about what this means allows for some very large and very small magnitude values)
- 3) All ones (255 single precision or 2047 double precision)
  - a) Fraction all zeros -> floating point infinity
  - b) Fraction not all zeros -> floating point NaN (not a number)

IEEE 754 Single Precision Floating-Point to Decimal Conversion Example:

What is -4.25 decimal in IEEE 754 single precision notation?

 $-4.25 \text{ decimal} = -100.01 \text{ binary} (1X2^2 + 1X2^{-2})$ 

= -1.0001 X 2<sup>2</sup> normalized floating point

Sign bit = 1 (negative value)

Fraction bits =  $0001\ 0000\ 0000\ 0000\ 0000\ 000$  (23 bits)

Exponent = 127 + 2 = 129 (bias plus actual)

```
Exponent bits = 1000\ 0001 (8 bits)
```

= 0xC088 0000

# Floating-Point Addition:

1.xxxx is called the *significand* (1 + fraction)

- 1) Shift significand of number with smaller exponent right by difference in exponent values
- 2) Add the signifcands
- 3) Normalize the sum of significands
- 4) Determine if overflow/underflow occurs (exponent too large or too small)
- 5) Round such that fraction has the proper number of bits

Round values half way between representations up such that rounded values have the same mean as the unrounded values

If the bit to the right of rounded LSb is

```
0 -> truncate
1 -> truncate and add 1 to the LSb
```

$1.11\underline{0}0$	(1.75 decimal)	->	1.11	(1.75 decimal)
1.11 <u>0</u> 1	(1.8125 decimal)	->	1.11	(1.75 decimal)
1.11 <u>1</u> 0	(1.875 decimal)	->	10.00	(2.0 decimal)
1.11 <u>1</u> 1	(1.9375 decimal)	->	10.00	(2.0 decimal)
10.0 <u>0</u> 0	(2.0 decimal)	->	10.00	(2.0 decimal)

Note that adding 1 to LSb can result in un-normalized value

6) If value is no longer normalized, repeat steps 3 and 4

# Floating-Point Addition Example:

```
0x40E0 0000
                        0x3F40 0000
                                        (IEEE 754 S. P.)
        0011\ 1111\ 0100\ 0000\quad 0000\ 0000\ 0000\ 0000
        sign
                        exponent
                                        fraction
        0
                        1000 0001
                                        1100 0000 0000 0000 0000 000
                        0111 1110
                                        1000 0000 0000 0000 0000 000
        positive
                        129 = 127 + 2
                                        1100 0000 0000 0000 0000 000
                                        1000 0000 0000 0000 0000 000
        positive
                        126 = 127 - 1
1.11 X 2<sup>2</sup>
                        1.1 X 2<sup>-1</sup>
1.11 X 2<sup>2</sup>
                        0.0011 \times 2^{2}
                +
                                                [right 3 = 2 - (-1) places]
(1.1100 + 0.0011) \times 2^{2}
1.1111 X 2<sup>2</sup>
Round fraction to 23 binary places (already done)
Sum: positive
                        exponent is 129 = 127 + 2
                                                        fraction is 1111000...
0\ 1000\ 0001\ 1111\ 0000\ 0000\ \dots
0x40F8 0000
                (IEEE 754 S. P.)
```