## SOFTENG 364: Computer Networks

Link Layer Kurose and Ross, chapter 6





### Learning Outcomes

By the end of this module you should be able to:


- Describe what the link layer is and its purpose
- Explain what error detection and correction is and how it works
- Explain what the two types of "links" are and what are the different concerns for each
- Describe how channel partitioning protocols work
- Describe how random access protocols work
- Describe how "taking turns" protocols work
- For each protocol, explain the advantages and the disadvantages of the protocol
- Explain how the Ethernet protocols work, including the underlying technologies such as ARP
- Demonstrate how switches are self-learning
- Describe how data centres work and what are the differences from
   a typical network
- Demonstrate how a machine can connect to a webserver



### References

Computer Networking: A Top Down Approach, 7th edition (2016). *By J. Kurose & K. Ross.* 

Chapter 6






## Link layer: introduction

#### Terminology:

- Hosts and routers: nodes
- Communication channels that connect adjacent nodes along Communication path: links
  - Wired links
  - Wireless links
  - LANs
- Layer-2 packet: frame, encapsulates datagram

Data-link layer has responsibility of transferring datagram from one node to physically adjacent node over a link





## Link layer: context

Datagram transferred by different Transportation analogy: trip from link protocols over different links:

- e.g., Ethernet on first link, frame relay on intermediate links, 802.11 on last link Each link protocol provides different services
- e.g., may or may not provide RDT over link

Princeton to Lausanne

- Limo: Princeton to JFK
- Plane: JFK to Geneva
- Train: Geneva to Lausanne

Tourist = *datagram* Transport segment = communication link Transportation mode = *link layer* protocol Travel agent = routing algorithm



### Link layer services

#### Framing, link access:

- Encapsulate datagram into frame, adding header, trailer
- Channel access if shared medium
- "MAC" addresses used in frame headers to identify source, destination
  - Different from IP address!

#### Reliable delivery between adjacent nodes

- We learned how to do this already (chapter 3)!
- Seldom used on low bit-error link (fiber, some twisted pair)
- Wireless links: high error rates

Q: why both link-level and end-end reliability?

# Link layer services (more)

#### **ENGINEERING**

#### Flow control:

- Pacing between adjacent sending and receiving nodes
   Frror detection:
- Errors caused by signal attenuation, noise.
- Receiver detects presence of errors:
  - Signals sender for retransmission or drops frame

#### Error correction:

 Receiver identifies and corrects bit error(s) without resorting to retransmission

#### Half-duplex and full-duplex

 With half duplex, nodes at both ends of link can transmit, but not at same time


## Where is the link layer implemented?



**ENGINEERING** 

In each and every host Link layer implemented in "adaptor" (aka network interface card NIC) or on a chip


- Ethernet card, 802.11 card; Ethernet chipset
- Implements link, physical layer Attaches into host's system buses Combination of hardware, software, firmware



# Adaptors **Communicating**







#### Sending side:

- Encapsulates datagram in frame
- Adds error checking bits, rdt, flow control, etc.


#### Receiving side

- Looks for errors, rdt, flow control, etc.
- Extracts datagram, passes to upper layer at receiving side



## **Error Types**


Single bit error





## **Error Types**


Multiple bits error





## **Error Types**

Burst error



How do we know we have an error? How do we know which bits are in error?



### **Error detection**


EDC = Error Detection and Correction bits (redundancy)

D = Data protected by error checking, may include header fields

Error detection not 100% reliable!

Protocol may miss some errors, but rarely

Larger EDC field yields better detection and correction



## Forma



## **Format for Parity Checks**

USART (a serial protocol) has the following frame format:

- 1 start bit [Beginning of frame]
- 5, 6, 7, 8, or 9 data bits
  - This will limit the data ranges i.e., 25, 26, 27, 28, 29
- no, even or odd parity bit
- 1 or 2 stop bits [End of frame]



- St Start bit, always low
- (n) Data bits (0 to 8)
- P Parity bit. Can be odd or even
- Sp Stop bit, always high
- IDLE No transfers on the communication line (RxD or TxD). An IDLE line must be high

# Error<br/>Checking: Parity



**ENGINEERING** 

A parity bit is used for error checking

 The data is discarded if the revised parity bit does not match the parity computed from the received data

A parity bit is a bit added to a string of binary to ensure that the total number of 1-bits in the string is even or odd.

- Even: sets to '1' if count odd
- i.e. if five '1' bits then the parity bit is set to '1' to make six '1' bits
- Odd: sets to '1' if count even

The Parity bit is calculated by an exclusive-or (XOR) of all data bits. If odd parity is used, the result is inverted.

• If used, the parity bit is located between the last data bit and first stop bit of a serial frame.  $P_{even} = d_{n-1} \oplus ... \oplus d_3 \oplus d_2 \oplus d_1 \oplus d_0 \oplus 0$ 

 $P_{odd}^{r=1} = d_{n-1}^{r-1} \oplus ... \oplus d_3 \oplus d_2 \oplus d_1 \oplus d_0 \oplus 1$ 

P<sub>even</sub> Parity bit using even parity

Podd Parity bit using odd parity

d<sub>n</sub> Data bit n of the character




#### **ENGINEERING**

### **Parity checking**


#### Single bit parity:

Detect single bit errors



#### Two-dimensional bit parity:

Detect and correct single bit errors



correctable single bit error

# Internet checksum (review)



Goal: detect "errors" (e.g., flipped bits) in transmitted packet (note: used at transport layer only)

#### Sender:

- Treat segment contents as sequence of 16-bit integers
- Checksum: addition (1's complement sum) of segment contents
- Sender puts checksum value into UDP checksum field

#### Receiver:


- Compute checksum of received segment
- Check if computed checksum equals checksum field value:
  - No: error detected
  - Yes: no error detected. But maybe errors nonetheless?

# Cyclic Redundancy Check Redundancy Check



More powerful error-detection coding View data bits, D, as a binary number Choose r+1 bit pattern (generator), G Goal: choose r CRC bits, R, such that

- <D,R> exactly divisible by G (modulo 2)
- Receiver knows G, divides <D,R> by G. If non-zero remainder: error detected!
- Can detect all burst errors less than r+1 bits
   Widely used in practice (Ethernet, 802.11 WiFi, ATM)





#### **ENGINEERING**

## CRC example

#### Want:

 $D \cdot 2^r XOR R = nG$ 


Equivalently:

 $D \cdot 2^r = nG XOR R$ 

#### Equivalently:

if we divide D<sub>2</sub>r by G, want remainder R to satisfy:


$$R = remainder[\frac{D \cdot 2^r}{G}]$$



## Error correction techniques

#### Some approaches:

- Hamming Codes
- Binary Convolution Code
- Reed Solomon Code
- Low-Density Parity-Check Code





### Multiple access links

Two types of "links":

Point-to-point


- PPP for dial-up access
- Point-to-point link between Ethernet switch, host Broadcast (shared wire or medium)
- Old-fashioned Ethernet
- Upstream HFC
- 802.11 wireless LAN



shared wire (e.g., cabled Ethernet)



shared RF (e.g., 802.11 WiFi)



shared RF (satellite)



humans at a cocktail party (shared air, acoustical)

# Multiple access protocols



Single shared broadcast channel

Two or more simultaneous transmissions by nodes: interference

Collision if node receives two or more signals at the same time

#### Multiple access protocol

- Distributed algorithm that determines how nodes share channel,
   i.e., determine when node can transmit
- Communication about channel sharing must use channel itself!
  - No out-of-band channel for coordination

# An ideal multiple access protocol multiple access protocol

Given: broadcast channel of rate R bps Desiderata:

- 1. When one node wants to transmit, it can send at rate R.
- 2. When M nodes want to transmit, each can send at average rate R/M
- 3. Fully decentralized:
  - No special node to coordinate transmissions
  - No synchronization of clocks, slots
- 4. Simple

## MAC Protocols: taxonomy

#### Channel partitioning

Divide channel into smaller "pieces" (time slots, frequency, code)

**ENGINEERING** 

Allocate piece to node for exclusive use

#### Random access

- Channel not divided, allow collisions
- "Recover" from collisions

#### "Taking turns"

 Nodes take turns, but nodes with more to send can take longer turns

# Time Division AUCKLAND ENGINEERING Multiple Access (TDMA)


Access to channel in "rounds"

Each station gets fixed length slot (length = packet transmission time)

in each round


Unused slots go idle

Example: 6-station LAN, 1,3,4 have packets to send, slots 2,5,6 idle



# Frequency Division Multiple Access

Channel spectrum divided into frequency bands
Each station assigned fixed frequency band
Unused transmission time in frequency bands go idle
Example: 6-station LAN, 1,3,4 have packet to send, frequency bands
2,5,6 idle



# Random access protocols



#### When node has packet to send

- Transmit at full channel data rate R.
- No a priori coordination among nodes

Two or more transmitting nodes → "collision",

#### Random access MAC protocol specifies:

- How to detect collisions
- How to recover from collisions (e.g., via delayed retransmissions) Examples of random access MAC protocols:
- Slotted Al OHA
- ALOHA
- CSMA, CSMA/CD, CSMA/CA



### **Slotted ALOHA**

#### Assumptions:


- All frames same size
- Time divided into equal size slots (time to transmit 1 frame)
- Nodes start to transmit only slot beginning
- Nodes are synchronized
- If 2 or more nodes transmit in slot, all nodes detect collision

#### Operation:

- When node obtains fresh frame, transmits in next slot
  - If no collision: node can send new frame in next slot
  - If collision: node retransmits frame in each subsequent slot with probability p until success



### **Slotted ALOHA**



#### **Pros**:

- Single active node can continuously transmit at full rate of channel
- Highly decentralized: only slots in nodes need to be in sync
- Simple

#### Cons:

- Collisions, wasting slots
- Idle slots
- Nodes may be able to detect collision in less than time to transmit packet
- Clock synchronization

# Slotted ALOHA: efficiency



Efficiency: long-run fraction of successful slots (many nodes, all with many frames to send)

- Suppose: N nodes with many frames to send, each transmits in slot with probability p
- Probability that given node has success in a slot =  $p(1-p)^{N-1}$
- Probability that any node has a success = Np(1-p)<sup>N-1</sup>

- Max efficiency: find p\* that maximizes
   Np(1-p)<sup>N-1</sup>
- For many nodes, take limit of *Np\*(1-p\*)<sup>N-1</sup>* as *N* goes to infinity, gives:

 $Max \ efficiency = 1/e = .37$ 

At best: channel used for useful transmissions 37% of time!



### Pure (unslotted) ALOHA


Unslotted Aloha: simpler, no synchronization

When frame first arrives

Transmit immediately

Collision probability increases:

Frame sent at t<sub>0</sub> collides with other frames sent in [t<sub>0</sub>-1,t<sub>0</sub>+1]





### Pure ALOHA efficiency

P(success by given node) = P(node transmits)

P(no other node transmits in  $[t_0-1,t_0]$  P(no other node transmits in  $[t_0-1,t_0]$ 

$$= p \cdot (1-p)^{N-1} \cdot (1-p)^{N-1}$$
  
=  $p \cdot (1-p)^{2(N-1)}$ 

... choosing optimum p and then letting  $n \rightarrow \infty$ 

$$= 1/(2e) = .18$$

even worse than slotted Aloha!

### 

**CSMA**: listen before transmit:

- If channel sensed idle: transmit entire frame
- If channel sensed busy, defer transmission

Human analogy: don't interrupt others!



### **CSMA** collisions

spatial layout of nodes

#### Collisions can still occur:

propagation delay means two nodes may not hear each other's transmission

Collision: entire packet transmission time wasted

 Distance & propagation delay play role in in determining collision probability



# CSMA/CD (collision detection)


CSMA/CD: carrier sensing, deferral as in CSMA

- Collisions detected within short time
- Colliding transmissions aborted, reducing channel wastage Collision detection:
- Easy in wired LANs: measure signal strengths, compare transmitted, received signals
- Difficult in wireless LANs: received signal strength overwhelmed by local transmission strength

Human analogy: the polite conversationalist



### CSMA/CD



# Ethernet CSMA/CD algorithm

- NIC receives datagram from network layer, creates frame
- 2. If NIC senses channel idle, starts frame transmission. If NIC senses channel busy, waits until channel idle, then transmits.
- 3. If NIC transmits entire frame without detecting another transmission, NIC is done with frame!

 If NIC detects another transmission while transmitting, aborts and sends jam signal

- 5. After aborting, NIC enters binary (exponential) backoff:
  - after mth collision, NIC chooses K at random from {0,1,2, ..., 2m-1}. NIC waits K:512 bit times, returns to Step 2
  - longer backoff interval with more collisions



## CSMA/CD efficiency

 $t_{prop}$  = max prop delay between 2 nodes in LAN

 $t_{trans}$  = time to transmit max-size frame

$$efficiency = \frac{1}{1 + 5t_{prop}/t_{trans}}$$

Efficiency goes to 1

- as  $t_{prop}$  goes to 0
- as  $t_{trans}$  goes to infinity

Better performance than ALOHA: and simple, cheap, decentralized!

# "Taking turns" MAC protocols

#### Channel partitioning MAC protocols:

- Share channel efficiently and fairly at high load
- Inefficient at low load: delay in channel access, 1/N bandwidth allocated even if only 1 active node!

#### Random access MAC protocols

- Efficient at low load: single node can fully utilize channel
- High load: collision overhead

#### "Taking turns" protocols

Look for best of both worlds!

## "Taking




**ENGINEERING** 

## turns" MAC protocols

#### *Polling:*

- Master node "invites" slave nodes to transmit in turn
- Typically used with "dumb" slave devices
- Concerns:
  - Polling overhead
  - Latency
  - Single point of failure (master)



## "Taking




**ENGINEERING** 

## turns" MAC protocols

#### Token passing:


- Control token passed from one node to next sequentially.
- Token message
- Concerns:
  - Token overhead
  - Latency
  - Single point of failure (token)





### Cable access network


Internet frames, TV channels, control transmitted downstream at different frequencies



- Multiple 40Mbps downstream (broadcast) channels
  - Single CMTS transmits into channels
- Multiple 30 Mbps upstream channels
- Multiple access: all users contend for certain upstream channel time slots (others assigned)



### Cable access network



**DOCSIS**: data over cable service interface spec

- FDM over upstream, downstream frequency channels
- TDM upstream: some slots assigned, some have contention
  - downstream MAP frame: assigns upstream slots
  - request for upstream slots (and data) transmitted random access (binary backoff) in selected slots



### MAC addresses and ARP

#### 32-bit IP address:

- Network-layer address for interface
- Used for layer 3 (network layer) forwarding


MAC (or LAN or physical or Ethernet) address:

- Function: used 'locally" to get frame from one interface to another physically-connected interface (same network, in IP-addressing sense)
- 48 bit MAC address (for most LANs) burned in NIC ROM, also sometimes software settable
- e.g.: 1A-2F-BB-76-09-AD
   hexadecimal (base 16) notation
   (each "numeral" represents 4 bits)



### LAN addresses and ARP

Each adapter on LAN has unique *LAN* address





### LAN addresses (more)

MAC address allocation administered by IEEE

Manufacturer buys portion of MAC address space (to assure uniqueness)

#### Analogy:

- MAC address: like Social Security Number
- IP address: like postal address

MAC flat address → portability

- Can move LAN card from one LAN to another
- IP hierarchical address not portable
- Address depends on IP subnet to which node is attached

## ARP: Address Auckland Revolution Protocol

#### **ENGINEERING**

Question: how to determine interface's MAC address, knowing its IP address?

137.196.7.23 137.196.7.23 137.196.7.14 137.196.7.14 137.196.7.14 137.196.7.14 137.196.7.14

ARP table: each IP node (host, router) on LAN has table

- IP/MAC address mapsome LAN nodes: < IP address; MAC address; TTL>
- TTL (Time pings for To Live): time after which address mapping will be forgotten (typically 20 min)



### ARP protocol: same LAN

A wants to send datagram to B

 B's MAC address not in A's ARP table.

A broadcasts ARP query packet, containing B's IP address

- Destination MAC address = FF-FF-FF-FF-FF
- All nodes on LAN receive ARP query

B receives ARP packet, replies to A with its (B's) MAC address

Frame sent to A's MAC address (unicast)

A caches (saves) IP-to-MAC address pair in its ARP table until information becomes old (times out)

 Soft state: information that times out (goes away) unless refreshed

ARP is "plug-and-play":


 Nodes create their ARP tables without intervention from net administrator

## Addressing: Addres

Walkthrough: send datagram from A to B via R

Focus on addressing – at IP (datagram) and MAC layer (frame)

- Assume A knows B's IP address
- Assume A knows IP address of first hop router, R (how?)
- Assume A knows R's MAC address (how?)




## 

**ENGINEERING** 

A creates IP datagram with IP source A, destination B


A creates link-layer frame with R's MAC address as destination address, frame contains A-to-B IP datagram



## Addressing: Auckland Engineering to another LAN

Frame sent from A to R


Frame received at R, datagram removed, passed up to IP



# Addressing: Auckland Engineering Touting to another LAN

R forwards datagram with IP source A, destination B


R creates link-layer frame with B's MAC address as destination address, frame contains A-to-B IP datagram



# Addressing: Auckland Engineering Touting to another LAN

R forwards datagram with IP source A, destination B

R creates link-layer frame with B's MAC address as destination address, frame contains A-to-B IP datagram




## Addressing: Courting to anoth



## routing to another LAN

R forwards datagram with IP source A, destination B

R creates link-layer frame with B's MAC address as dest, frame contains A-to-B IP datagram






### **Ethernet**

"Dominant" wired LAN technology:

- Single chip, multiple speeds (e.g., Broadcom BCM5761)
- First widely used LAN technology
- Simpler, cheap
- Kept up with speed race: 10 Mbps 10 Gbps




Metcalfe's Ethernet sketch

# Ethernet: physical topology


**ENGINEERING** 

Bus: popular through mid 90s

- All nodes in same collision domain (can collide with each other)
   Star: prevails today
- Active switch in center
- Each "spoke" runs a (separate) Ethernet protocol (nodes do not collide with each other)



**bus**: coaxial cable



## Ethernet frame structure



Sending adapter encapsulates IP datagram (or other network layer protocol packet) in Ethernet frame

preamble dest. source address address (payload) CRC

#### Preamble:

- 7 bytes with pattern 10101010 followed by one byte with pattern 10101011
- Used to synchronize receiver, sender clock rates

# Ethernet Frame structure (more)

Addresses: 6 byte source, destination MAC addresses

- If adapter receives frame with matching destination address, or with broadcast address (e.g. ARP packet), it passes data in frame to network layer protocol
- Otherwise, adapter discards frame

Type: indicates higher layer protocol (mostly IP but others possible, e.g., Novell IPX, AppleTalk)

CRC: cyclic redundancy check at receiver

Error detected: frame is dropped

type								
preamble	dest. address	source address		data (payload)	CRC			



Connectionless: no handshaking between sending and receiving NICs Unreliable: receiving NIC doesn't send acks or nacks to sending NIC

 Data in dropped frames recovered only if initial sender uses higher layer rdt (e.g., TCP), otherwise dropped data lost

Ethernet's MAC protocol: unslotted CSMA/CD with binary backoff

## 802.3




**ENGINEERING** 

### **Ethernet standards**

#### Many different Ethernet standards

- Common MAC protocol and frame format
- Different speeds: 2 Mbps, 10 Mbps, 100 Mbps, 1Gbps, 10 Gbps, 40 Gbps
- Different physical layer media: fiber, cable





### **Ethernet switch**

Link-layer device: takes an active role

- Store, forward Ethernet frames
- Examine incoming frame's MAC address, selectively forward frame to one-or-more outgoing links when frame is to be forwarded on Segment, uses CSMA/CD to access segment

#### Transparent

- Hosts are unaware of presence of switches
   Plug-and-play, self-learning
- Switches do not need to be configured

# *Multiple*simultaneous




**ENGINEERING** 

## simultaneous transmissions

Hosts have dedicated, direct connection to switch
Switches buffer packets
Ethernet protocol used on each incoming link, but no collisions; full duplex

Each link is its own collision domain

Switching: A-to-A' and B-to-B' can transmit simultaneously, without collisions



switch with six interfaces (1,2,3,4,5,6)



### Switch forwarding table


<u>Q:</u> how does switch know A' reachable via interface 4, B' reachable via interface 5?

<u>A:</u> each switch has a switch table, each entry:

- (MAC address of host, interface to reach host, time stamp)
- Looks like a routing table!

Q: how are entries created, maintained in switch table?

Something like a routing protocol?



switch with six interfaces (1,2,3,4,5,6)




#### **ENGINEERING**

Switch: self-learning

Source: A Dest: A'

Switch *learns* which hosts can be reached through which interfaces

- When frame received, switch "learns" location of sender: incoming LAN segment
- Records sender/location pair in switch table



MAC addr	interface	TTL	
Α	1	60	

Switch table (initially empty)

# Switch: frame filtering/forwarding

When frame received at switch:

- 1. Record incoming link, MAC address of sending host
- 2. Index switch table using MAC destination address

```
3. if entry found for destination then {
  if destination on segment from which frame arrived then drop frame
    else forward frame on interface indicated by entry
  }
  else flood /* forward on all interfaces except arriving interface */
```


# Self-learning, AUCKLAND ENVISOR OF THE UNIVERSITY OF OF THE UNIVE

**ENGINEERING** 

√Source: A √Dest: A'

Frame destination, A', location unknown: *flood* 

Destination A location known: selectively send on just one link




MAC addr	interface	TTL
Α	1	60
A'	4	60

switch table (initially empty)

## Interconnecting switches

Self-learning switches can be connected together:




 $\underline{Q}$ : sending from A to G - how does S<sub>1</sub> know to forward frame destined to G via S<sub>4</sub> and S<sub>3</sub>?

A: self learning! (works exactly the same as in single-switch case!)



### Institutional network




Switches vs. Routers

#### Both are store-and-forward:

- Routers: network-layer devices (examine network-layer headers)
- Switches: link-layer devices (examine link-layer headers)

#### Both have forwarding tables:

- Routers: compute tables using routing algorithms, IP addresses
- Switches: learn forwarding table using flooding, learning, MAC addresses





### Data center networks

10's to 100's of thousands of hosts, often closely coupled, in close proximity:

- e-business (e.g. Amazon)
- Content-servers (e.g., YouTube, Akamai, Apple, Microsoft)
- Search engines, data mining (e.g., Google)

#### Challenges:

- Multiple applications, each serving massive numbers of clients
- Managing/Balancing load, avoiding processing, networking, data bottlenecks




Inside a 40-ft Microsoft container, Chicago data center

## Data center networks

#### load balancer: application-layer routing

- receives external client requests
- directs workload within data center
- returns results to external client (hiding data center internals from client)






### Data center networks

Rich interconnection among switches, racks:

- Increased throughput between racks (multiple routing paths possible)
- Increased reliability via redundancy




# Synthesis: a day in the life of a web request

Journey down protocol stack complete!

- Application, transport, network, link Putting-it-all-together: synthesis!
- Goal: identify, review, understand protocols (at all layers) involved in seemingly simple scenario: requesting www page
- Scenario: student attaches laptop to campus network, requests/receives www.google.com


## A day in the life: scenario





## Connecting to the Internet






- Connecting laptop needs to get its own IP address, addr of first-hop router, addr of DNS server: use DHCP
- DHCP request encapsulated in UDP, encapsulated in IP, encapsulated in 802.3 Ethernet
- Ethernet frame broadcast (dest: FFFFFFFFFFFF) on LAN, received at router running DHCP server
- Ethernet demuxed to IP demuxed, UDP demuxed to DHCP

## Connecting to the Internet






- DHCP server formulates DHCP ACK containing client's IP address, IP address of first-hop router for client, name & IP address of DNS server
- Encapsulation at DHCP server, frame forwarded (switch learning) through LAN, demultiplexing at client
- DHCP client receives DHCP ACK reply

## ARP (before



#### **ENGINEERING**

## DNS, before HTTP)




- Before sending HTTP request, need IP address of www.google.com: DNS
- DNS query created, encapsulated in UDP, encapsulated in IP, encapsulated in Ethernet. To send frame to router, need MAC address of router interface: ARP
- ARP query broadcast, received by router, which replies with ARP reply giving MAC address of router interface
- Client now knows MAC address of first hop router, so can now send frame containing DNS query




#### **ENGINEERING**

## **Using DNS**




 IP datagram containing DNS query forwarded via LAN switch from client to 1<sup>st</sup> hop router




- IP datagram forwarded from campus network into Vodafone network, routed (tables created by RIP, OSPF, IS-IS and/or BGP routing protocols) to DNS server
- Demuxed to DNS server
- DNS server replies to client with IP address of www.google.com

## TCP connection carrying



## HTTP request/reply





## Summary

- Described the link layer and its purpose
- Described the services the link layer provides
- Introduced some ways of detecting and correcting errors: Parity bits, Internet checksums and Cyclic Redundancy Checks
- Channel partitioning, by time, frequency or code
- Random access (dynamic),
- ALOHA, S-ALOHA, CSMA, CSMA/CD
- Carrier sensing: easy in some technologies (wire), hard in others (wireless)

- CSMA/CD used in Ethernet
- CSMA/CA used in 802.11

#### Taking turns:

- Polling from central site, token passing
- Bluetooth, FDDI, token ring
- Learnt how LANs work, including: MAC Addresses, Address
  - Resolution Protocol, Ethernet protocols and Switches
- Learnt how switches are selflearning
- Introduced data centres and their unique challenges
- Synthesized our knowledge on how a web request is served

