Chapter 13: I/O Systems

Sections: 13.1-13.3.1 & 13.5

Chapter 13: I/O Systems

- Overview
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Transforming I/O Requests to Hardware Operations
- STREAMS
- Performance

Objectives

 Explore the structure of an operating system's I/O subsystem

 Discuss the principles of I/O hardware and its complexity

 Provide details of the performance aspects of I/O hardware and software

Overview

- I/O management is a major component of operating system design and operation
 - Important aspect of computer operation
 - I/O devices vary greatly
 - Various methods to control them.
 - Performance management
 - New types of devices frequent
- Ports, busses, device controllers connect to various devices
- **Device drivers** encapsulate device details
 - Present uniform device-access interface to I/O subsystem

Functionality:

Read Write

Open


Configure

etc....

I/O Hardware

- Incredible variety of I/O devices
 - Storage
 - Transmission
 - Human-interface
- Common concepts signals from I/O devices interface with computer
 - Port connection point for device
 - Bus daisy chain or shared direct access
 - PCI bus common in PCs and servers, PCI Express (PCIe)
 - expansion bus connects relatively slow devices
 - Controller (host adapter) electronics that operate port, bus, device
 - Sometimes integrated
 - Sometimes separate circuit board (host adapter)
 - Contains processor, microcode, private memory, bus controller, etc
 - Some talk to per-device controller with bus controller, microcode, memory, etc

A Typical PC Bus Structure



I/O Hardware (Cont.)


- I/O instructions control devices
- Devices usually have registers where device driver places commands, addresses, and data to write, or read data from registers after command execution
 - Data-in register, data-out register, status register, control register
 - Typically 1-4 bytes, or FIFO buffer
- Devices have addresses, used by
 - Direct I/O instructions
 - Memory-mapped I/O
 - Device data and command registers mapped to processor address space
 - Especially for large address spaces (graphics)

Device I/O Port Locations on PCs (partial)

FYI

I/O address range (hexadecimal)	device
000-00F	DMA controller
020–021	interrupt controller
040–043	timer
200–20F	game controller
2F8–2FF	serial port (secondary)
320-32F	hard-disk controller
378–37F	parallel port
3D0-3DF	graphics controller
3F0-3F7	diskette-drive controller
3F8-3FF	serial port (primary)

A Kernel I/O Structure




Polling

- For each byte of I/O
 - 1. Read busy bit from status register until 0
 - 2. Host sets read or write bit and if write copies data into dataout register
 - 3. Host sets command-ready bit
 - 4. Controller sets busy bit, executes transfer
 - Controller clears busy bit, error bit, command-ready bit when transfer done
- Step 1 is busy-wait cycle to wait for I/O from device
 - Reasonable if device is fast
 - But inefficient if device slow
 - CPU switches to other tasks?
 - But if miss a cycle data overwritten / lost

Interrupts


- Polling can happen in 3 instruction cycles
 - Read status, logical-and to extract status bit, branch if not zero
 - How to be more efficient if non-zero infrequently?
- CPU Interrupt-request line triggered by I/O device
 - Checked by processor after each instruction
- Interrupt handler receives interrupts
 - Maskable to ignore or delay some interrupts
- Interrupt vector to dispatch interrupt to correct handler
 - Context switch at start and end
 - Based on priority
 - Some nonmaskable
 - Interrupt chaining if more than one device at same interrupt number

Interrupt-Driven I/O Cycle






Interrupt-driven I/O Operation



Life Cycle of An I/O Request



Intel Pentium Processor Event-Vector Table

FYI

vector number	description
0	divide error
1	debug exception
2	null interrupt
3	breakpoint
4	INTO-detected overflow
5	bound range exception
6	invalid opcode
7	device not available
8	double fault
9	coprocessor segment overrun (reserved)
10	invalid task state segment
11	segment not present
12	stack fault
13	general protection
14	page fault
15	(Intel reserved, do not use)
16	floating-point error
17	alignment check
18	machine check
19–31	(Intel reserved, do not use)
32–255	maskable interrupts


Interrupts (Cont.)

- Interrupt mechanism also used for exceptions
 - Terminate process, crash system due to hardware error
- Page fault executes when memory access error
- System call executes via trap to trigger kernel to execute request
- Multi-CPU systems can process interrupts concurrently
 - If operating system designed to handle it
- Used for time-sensitive processing, frequent, must be fast

Direct Memory Access

- Used to avoid programmed I/O (one byte at a time) for large data movement
- Requires DMA controller
- Bypasses CPU to transfer data directly between I/O device and memory
- OS writes DMA command block into memory
 - Source and destination addresses
 - Read or write mode
 - Count of bytes
 - Writes location of command block to DMA controller
 - Bus mastering of DMA controller grabs bus from CPU
 - Cycle stealing from CPU but still much more efficient
 - When done, interrupts to signal completion
- Version that is aware of virtual addresses can be even more efficient - DVMA

Six Step Process to Perform DMA Transfer



Application I/O Interface

- I/O system calls encapsulate device behaviors in generic classes
- Device-driver layer hides differences among I/O controllers from kernel
- New devices talking already-implemented protocols need no extra work
- Each OS has its own I/O subsystem structures and device driver frameworks
- Devices vary in many dimensions
 - Character-stream or block
 - Sequential or random-access
 - Synchronous or asynchronous (or both)
 - Sharable or dedicated
 - Speed of operation
 - read-write, read only, or write only


Characteristics of I/O Devices

- Subtleties of devices handled by device drivers
- Broadly I/O devices can be grouped by the OS into
 - Block I/O
 - Character I/O (Stream)
 - Memory-mapped file access
 - Network sockets
- For direct manipulation of I/O device specific characteristics, usually an escape / back door
 - Unix ioctl() call to send arbitrary bits to a device control register and data to device data register

Block and Character Devices

- Block devices include disk drives
 - Commands include read, write, seek
 - Raw I/O, direct I/O, or file-system access
 - Memory-mapped file access possible
 - File mapped to virtual memory and clusters brought via demand paging
 - DMA
- Character devices include keyboards, mice, serial ports
 - Commands include get(), put()
 - Libraries layered on top allow line editing

Device-status Table



Kernel I/O Subsystem

- Caching faster device holding copy of data
 - Always just a copy
 - Key to performance
 - Sometimes combined with buffering
- Spooling hold output for a device
 - If device can serve only one request at a time
 - i.e., Printing
- Device reservation provides exclusive access to a device
 - System calls for allocation and de-allocation
 - Watch out for deadlock


Error Handling

- OS can recover from disk read, device unavailable, transient write failures
 - Retry a read or write, for example
 - Some systems more advanced Solaris FMA, AIX
 - Track error frequencies, stop using device with increasing frequency of retry-able errors
- Most return an error number or code when I/O request fails
- System error logs hold problem reports


I/O Protection

- User process may accidentally or purposefully attempt to disrupt normal operation via illegal I/O instructions
 - All I/O instructions defined to be privileged
 - I/O must be performed via system calls
 - Memory-mapped and I/O port memory locations must be protected too


Use of a System Call to Perform I/O



UNIX I/O Kernel Structure



Intercomputer Communications



Improving Performance

- Reduce number of context switches
- Reduce data copying
- Reduce interrupts by using large transfers, smart controllers, polling
- Use DMA
- Use smarter hardware devices
- Balance CPU, memory, bus, and I/O performance for highest throughput
- Move user-mode processes / daemons to kernel threads

End of Chapter 13