Enough x86 assembler to be dangerous

Charles Bailey

Bloomberg LP

Developer Experience Engineering London

Enough x86 assembler to be very dangerous

Charles Bailey

Bloomberg LP

Developer Experience Engineering London

Why dangerous?

- Assembly language isn't object code
- Object code isn't directly executed by "silicon"
- There is not substitute for measuring

What about writing assembly code?

- There are many pitfalls...
- ... in summary, don't.

So why learn an assembly language?

- Understand the next abstraction down
- Observe the impact of your code choices
- It's fun

Just enough "Architecture" to get by

Architecture summary

- Registers
- Virtual address space
- Stack

Registers

- Fast to access
- Local to each CPU core

General purpose registers

eax ebx ecx edx esi edi esp ebp

Special purpose registers

```
eip / rip
eflags / rflags
```

Virtual address space

- Data mapped in from the executable
- Dynamically allocated data
- The stack

Stack


- Specific to each thread
- Combined call stack and data stack
- Grows downward from higher memory addresses

Show me assembly code!

- objdump -d -Mintel <object-file>
- -S -masm=intel to gcc or clang
- disassemble in gdb (after set disassembly-flavor intel)
- Open the Debug > Windows > Disassembly window in Visual Studio

A simple example

```
long add(long a, long b) { return a + b; }
g++ -m32 -00 -masm=intel -fno-exceptions\
 -fno-asynchronous-unwind-tables -fno-pic
Z3addll:
   push
            ebp
           ebp, esp
    mov
           edx, DWORD PTR [ebp+8]
   mov
            eax, DWORD PTR [ebp+12]
    mov
    add
            eax, edx
            ebp
    pop
    ret
```



Demonstration class

```
struct Foo {
    int data;
    Foo();
    Foo(const Foo&);
    Foo(Foo&&);
    ~Foo();

Foo& operator+=(const Foo&);
};
```

Candidates for operator+

```
Foo op_plus1(const Foo& a, const Foo& b) {
    Foo r(a);
    r += b;
    return r;
}

Foo op_plus2(const Foo& a, const Foo& b) {
    return Foo(a) += b;
}
```

operator+ (candidate one)

```
_Z8op_plus1RK3FooS1 :
   push ebx
   sub esp, 16
   mov ebx, DWORD PTR [esp+24]
   push DWORD PTR [esp+28]
   push ebx
   call _ZN3FooC1ERKS_ ; copy constructor
   pop
         eax
         edx
   pop
   push DWORD PTR [esp+32]
   push ebx
   call ZN3FoopLERKS_
                        ; operator+=
   add
         esp, 24
         eax, ebx
   mov
         ebx
   pop
   ret 4
```

operator+ (candidate two)

Questions?

References

Stackoverflows x86 tag wiki https://stackoverflow.com/tags/x86/info

Intel developer's manual http://www.intel.com/content/www/us/en/processors/a software-developer-manuals.html

x86-* ABI documentation https://github.com/hjltools/x86-psABI