SHABBY HEFE

EXTRACT: 6.6 lb. Bavarian Wheat Liquid Malt Extract

1.0 lb. Pilsen Light Dry Malt Extract

SPECIALTY GRAINS: 0.5 lb. Wheat Malt

0.5 lb. Pilsner Malt

HOPS: 1.0 oz. Mt Hood 60 min

YEAST: Imperial – G01 Stefon

White Labs – WLP300 Hefeweizen Ale

Wyeast – Weihenstephan 3068

(or) Dry Yeast - Fermentis Safale WB-06

OTHER: 4oz. Corn Sugar (to carbonate at bottling time)

INSTRUCTIONS:

- Bring 2 ½ 3 gallons of water to 160 170 degrees. Take pot off burner.
- 2. Steep (soak) specialty grains in bag for 30 40 min.
- 3. Rinse grains with 2 cups of 160 170 degree water and discard spent grains. (keep bag)
- 4. Pour malt extract into mixture. Stir until dissolved.
- 5. Return pot to heat and bring to boil. (DO NOT BOIL OVER)
- 6. Boil for 60 minutes, while adding the hops at the recipe intervals.
- 7. Sanitize all equipment that the wort will come into contact with after the boil.
- 8. Put 1 gallon cold water into 6 61/2 gallon fermentation vessel.
- 9. Add contents of boil pot, fill to 5 gallon mark with cold water.
- 10. When wort has cooled to about 70 degrees pitch yeast and place lid on tight.
- 11. Install and fill airlock to the proper level with sanitizer or water. Store in area that will remain 65 70 degrees.

- 12. After fermentation has stopped (14 17 days) transfer to a bottling bucket, add corn sugar (4 oz.) dissolved in 1 cup water.
- 13. Fill leaving 1" to 1 1/4" space in neck of bottle and seal with caps.
- 14. Age beer for two three weeks at 68 72 degrees, chill and enjoy.

ALL GRAIN: 5.5 lb. Pilsner Malt

5.5 lb. Wheat Malt

HOPS: 1.0 oz. Mt Hood 60 min

YEAST: Imperial – G01 Stefon

White Labs – WLP300 Hefeweizen Ale

Wyeast – Weihenstephan 3068

(or) Dry Yeast - Fermentis Safale WB-06

Mash at 150 degrees for 60 minutes. Boil for 90 minutes. Estimated OG 1.054, FG 1.012. Estimated IBU 19, Estimated SRM 4 Estimated ABV 5.5 %



1430 East Main Ave #1430-C, Puyallup WA ● 253-286-7607