Step 14 — Troubleshooting

No sound in game

1. Did you open the world **after** installing? The world's resource pack is loaded when the world opens.
2. Watch for a pack error message when the world opens. Run **Check** (step 11) again: it must say *Check passed*.
3. Check the game's **Jukebox/Note Blocks** volume slider (*Options* → *Music & Sounds*).
4. Try `/function music:<name>/volume {v:150}`.
5. In the log of Minecraft (`.minecraft\logs\latest.log`), a line *"Unable to play unknown soundEvent"* means the resource pack is not loaded: generate and install again.

The structure is not built

- Commands must be allowed (operator / cheats).
- Choose the place first: `/function music:<name>/wand`, then right-click a block with the wand.
- If the area could not be loaded in 30 s, nothing is changed: try again.

The wand does nothing

- Hold it in your **main hand** and aim at a block less than 64 blocks away (the sky or water alone do not count).
- A right-click on a block that opens (chest, door, lever…) uses that block instead of the wand: aim at an ordinary block.
- Each song has its own wand: take the one of the right song (`/function music:<name>/wand`).
- A structure already built does not move: `/function music:<name>/remove` first.

"Official Minecraft sounds not downloaded"

The first download (about 41 MB from Mojang's servers) could not be done, usually because there is no internet. Check the connection, then *Settings → Official Minecraft sounds → Download now*. An antivirus or a company firewall may also block `piston-meta.mojang.com` and `resources.download.minecraft.net`.

The license does not activate


- *"This key was bought for the Google account …"*: sign in with the Google account shown (its first letter and domain are displayed). If you paid with another address, ask the author for a key for your Google address.
- *"No license is stored in the Google account"*: use **Activate with Google** with the key received by e-mail (the first time); then **Get my license back** works on your other computers.
- Google's page does not come back to the software: keep the software open while signing in, and let your firewall accept the local connection (address `127.0.0.1`).
- *"This activation comes from another computer"*: normal after copying your settings; click **Get my license back with Google**.

A world does not appear in the list

- It appears by itself after a moment; **Refresh the list** forces a search.
- For an unusual game folder: **Add an instance folder…** (step 1) or *Settings → Added instances*.

The software shows an error

Open **Diagnostics**: it shows the detected environment, runs a **self-test** and shows the log. **Copy the report** or **Export the report…** to share it when you ask for help. Nothing is ever sent automatically.



Diagnostics

Undo everything in a world

- In game, for each song: `/function music:<name>/remove` (removes the structure), then `/function music:<name>/uninstall`.
- Then, in the software (step 10): **Remove a song from the world...**. Or by hand: delete `datapacks/music_<name>.zip`, the `mmstudio_packs` folder and the world's `resources.zip` (or `resourcepacks/resources.zip`).
- Or restore the ZIP backup made before the installation.