

Community



TUTORIAL

How To Configure Multi-Factor Authentication on Ubuntu 18.04

Ubuntu Security Ubuntu 18.04

By Daniel Pellarini

The author selected the <u>Electronic Frontier Foundation</u> to receive a donation as part of the Write for DOnations program.

Introduction

Two-factor authentication (2FA) is an authentication method that requires entering more than one piece of information to successfully log in to an account or device. In addition to entering a username and password combination, 2FA requires the user to enter an additional piece of information such as a *one-time password* (OTP), like a six-digit verification code.

In general, 2FA requires the user to enter information of different types:

- Something that the user knows, such as a password
- Something that the user has, such as the verification code generated from an authenticator application

2FA is a subset of *multi-factor authentication* (MFA), which, in addition to something that the user knows and something that they have, requires something that the user *is*. This is the case of biometrics, which use technologies such as fingerprint or voice recognition.

2FA helps strengthen the authentication process to a certain service or device: even if the password were compromised, an attacker would also need to have access to the user's device which holds the authenticator app used to generate the security codes. For this reason, many online services (including Digital Coops) offer the possibility to enable 2FA SCROLL TO TOP

for user accounts to increase account security when it comes to the authentication phase.

In this guide, you will configure 2FA for a non-root sudoer user on an Ubuntu 18.04 installation with the Google PAM module. Since you're configuring 2FA on the non-root user, you will still be able to access the machine from your **root** account in case of a lockout. The tutorial will be general enough to be applied both to server and to desktop installations, both local and remote.

Prerequisites

Before you begin this guide you'll need the following:

- One Ubuntu 18.04 server or desktop environment. If you are using an Ubuntu server, set it
 up by following the <u>Ubuntu 18.04 initial server setup</u> guide, including a non-root user
 with sudo privileges and a firewall.
- An authenticator application installed on your mobile device, with which you can scan
 2FA QR codes, such as Google Authenticator or Authy.

Step 1 – Installing the Google PAM Module

In order to configure 2FA on Ubuntu 18.04, you need to install <u>Google's PAM module</u> for Linux. The *Pluggable Authentication Module* (PAM) is the authentication mechanism Linux uses. You will use Google's PAM module to have your user authenticate over 2FA using Google-generated OTP codes.

First, log in as the non-root user that you configured in the prerequisites:

```
$ ssh sammy@your_server_ip
```

Update the Ubuntu repositories to download the latest version of the authenticator:

\$ sudo apt-get update

Now that your repositories are up to SCROLL TO TOP test version of the PAM module:

This is a very small package with no dependencies, so it will take a few seconds to install. In the next section, you will configure 2FA for the non-root user on the system.

Step 2 - Configuring 2FA for a User

Now that you've installed the PAM module, you will run it to generate a QR code for the logged in user. This will create the code, but the Ubuntu environment won't require 2FA until you've enabled it later in this tutorial.

Run the google-authenticator command to start and configure the PAM module:

\$ google-authenticator

The command will present a prompt that will ask you several configuration questions. The first question will ask if you want tokens to be time based. Time-based authentication tokens will expire after a set amount of time, which defaults to 30 seconds on most systems. Time-based tokens are more secure than tokens that are not time-based, and most 2FA implementations use them. You can choose either option here, but this tutorial will choose. Yes, to use time-based authentication tokens:

Output

Do you want authentication tokens to be time-based (y/n) y

After answering y to this question, you will see several lines output to your console:

- A QR code: This is the code you need to scan using your authenticator app. Once you
 have scanned it, it will immediately turn into a code-generating device that will create a
 new OTP every 30 seconds.
- Your secret key: This is an alternative method to configure your authenticator app. If you
 are using an app that does not support QR scanning, you can enter the secret key to
 configure your authentication app.
- Your verification code: This is the first six-digit verification code that this specific QR code generates.

 Your emergency scratch codes: Also known as backup codes, these one-use tokens will allow you to pass 2FA authentication if you lose your authenticator device. Keep these codes in a safe place to avoid being locked out of the account.

After you've configured your authenticator app and saved your backup codes in a safe place, the prompt will ask if you'd like to update the configuration file. If you choose n, you will need to run the configuration program again. You will enter y to save your changes and move forward:

```
Output  \label{eq:continuous}  \mbox{Do you want me to update your "~/.google_authenticator" file (y/n) y }
```

The next question will ask if you want to disallow authentication codes to be used more than once. By default, you can only use each code once, even if it remains valid for 30 seconds. This is the safest choice because it prevents replay attacks from an attacker who somehow managed to get a hold of your verification code after you have used it. For this reason, it's more secure to disallow codes to be used more than once. Answer y to disallow multiple uses of the same token:

```
Output
```

```
Do you want to disallow multiple uses of the same authentication token? This restricts you to one login about every 30s, but it increases your chances to notice or even prevent man-in-the-middle attacks (y/n) y
```

The next question asks if you want authentication tokens to be accepted a short time before or after their normal validity time. Verification codes are very time-sensitive, which means that your tokens can be refused if your devices are not synchronized. This option allows you to work around this issue by extending the default validity time of verification codes so that, even if your devices were temporarily out of sync, your authentication codes would be accepted anyway. Making sure that the time is the same on all your devices is the best option, as choosing yes will decrease the security of your system. Answer n to this question to not allow a grace period:

```
Output
```

```
By default, tokens are good for 30 seconds and in order to compensate for possible time-skew between the client and the server, we allow an extra token before and after the current time. If you experience problems with poor time synchronization, you can increase SCROLL TO TOP default size of 1:30min to about 4min. Do you want to do so (y/n) n
```

The last question asks if you want to enable rate limiting for log in attempts. This will not allow more than three failed log in attempts every 30 seconds, which is a good security strengthening technique. Enable it by answering y:

Output

If the computer that you are logging into isn't hardened against brute-force login attempts, you can enable rate-limiting for the authentication module. By default, this limits attackers to no more than 3 login attempts every 30s. Do you want to enable rate-limiting (y/n) y

You have now configured and generated 2FA codes for the non-root user with the PAM module. Now that your codes are generated, you need to enable 2FA in your environment.

Step 3 – Activating 2FA in Ubuntu

The Google PAM module is now generating 2FA codes your user, but Ubuntu doesn't yet know that it needs to use the codes as part of the user's authentication process. In this step, you will update Ubuntu's configuration to require 2FA tokens in addition to the regular method of authentication.

You have two different options at this point:

- You can require 2FA every time a user logs in to the system *and* every time a user requests sudo privileges.
- You can require 2FA only during log in, where subsequent sudo authentication attempts would only require the user password.

The first option will be ideal for a shared environment, where you may want to protect any actions that require sudo permissions. The second approach is more practical for a local desktop environment, where you are the only user on the system.

Note: If you are enabling 2FA on a remote machine that you access over SSH, like a DigitalOcean Droplet, you need to follow steps two and three from the How To Set Up Multi-Factor Authentication for SSH on Ubuntu 16.04 guide before proceeding with this tutorial. The remaining steps in this tutorial apply to SCROLL TO TOP Sions, but remote environments need additional updates to make the SSH service aware or ZFA.

If you are not using SSH to access your Ubuntu installation, you can immediately proceed with the remaining steps in the tutorial.

Requiring 2FA for Log In and sudo Requests

To be prompted for 2FA during log in and subsequent privilege escalation requests, you need to edit the /etc/pam.d/common-auth file by adding a line to the end of the existing file.

The common-auth file applies to all authentication mechanisms on the system, regardless of the desktop environment used. It also applies to authentication requests that happen after the user logs in to the system, such as during a sudo escalation request when installing a new package from the terminal.

Open this file with the following command:

```
$ sudo nano /etc/pam.d/common-auth
```

Add the highlighted line at the end of the file:

/etc/pam.d/common-auth

```
# and here are more per-package modules (the "Additional" block)
session required pam_unix.so
session optional pam_systemd.so
# end of pam-auth-update config
auth required pam_google_authenticator.so nullok
```

This line tells the Ubuntu authentication system to require 2FA upon log in through the Google PAM module. The nullok option allows existing users to log into the system even if they haven't configured 2FA authentication for their account. In other words, users who have configured 2FA will be required to enter an authentication code at the next log in, while users who haven't run the <code>google-authenticator</code> command will be able to log in with only their username and password until they configure 2FA.

Save and close the file after adding the line.

Requiring 2FA for Log In Only SCROLL TO TOP

If you want to only be prompted for 2FA when you first log in to the system on a desktop environment, you need to edit the configuration file for the desktop manager you are using. The name of the configuration file usually matches the name of the desktop environment. For example, the configuration file for gdm, the default Ubuntu desktop environment starting after Ubuntu 16.04, is /etc/pam.d/gdm.

In the case of a headless server, such as a DigitalOcean Droplet, you will edit the /etc/pam.d/common-session file instead. Open the relevant file based on your environment:

```
$ sudo nano /etc/pam.d/common-session
```

Add the highlighted line to the end of the file:

/etc/pam.d/common-session

```
#
# /etc/pam.d/common-session - session-related modules common to all services
#
...
# # and here are more per-package modules (the "Additional" block)
session required pam_unix.so
session optional pam_systemd.so
# end of pam-auth-update config
auth required pam google authenticator.so nullok
```

This will tell Ubuntu to require 2FA when a user connects to the system via the command line (either locally or remotely through SSH), but not during subsequent authentication attempts, such as sudo requests.

You have now successfully configured Ubuntu to prompt you for 2FA either just during log in, or for every authenticated action performed on the system. You're now ready to test the configuration and make sure that you are prompted for 2FA when you log in to your Ubuntu installation.

Step 4 – Testing 2FA

In the previous step, you've configured 2FA to generate codes every 30 seconds. In this step, you will test 2FA by logging in SCROLL TO TOP vironment.

First, log out and back in to your Ubuntu environment:

```
ssh sammy@your_server_ip
```

If you are using password-based authentication, you will be prompted for your user password:

Output

Password:

Note: If you are testing this on a DigitalOcean Droplet or another remote server protected by certificate authentication, you won't be prompted for a password, and your key will be passed and accepted automatically. You will therefore only be prompted for your verification code.

Enter your password and you will be prompted for the 2FA verification code:

Output

Verification code:

After entering your verification code, you will be logged in:

```
Output sammy@your_server_ip: ~#
```

If 2FA was only enabled for logins, you won't be prompted for your 2FA codes again until the session expires or you log out manually.

If you enabled 2FA through the common-auth file, you will be prompted for it on every login and request for sudo privileges:

```
Output

sammy@your_server_ip: ~# sudo -s

sudo password for sammy:

Verification code:

root@your_server_ip:

SCROLL TO TOP
```

In this step you have confirmed that your 2FA configuration is working as expected. If you were not prompted for your verification codes in this phase, return to step three of the tutorial and confirm that you have edited the correct Ubuntu authentication file.

Step 5 – Preventing a 2FA Lockout

In the event of a lost or wiped phone, it is important to have proper backup methods in place to recover access to your 2FA-enabled account. When you configure 2FA for the first time, you have a few options to ensure that you can recover from a lock out:

- Save a backup copy of your secret configuration codes in a safe place. You can do this manually, but some authentication apps like Authy provide backup code features.
- Save your recovery codes in a safe place that can be accessed outside of your 2FA enabled environment.

If for any reason you don't have access to your backup options, you can take additional steps to recover access to your 2FA enabled local environment or remote server.

Step 6 — Recovering from a 2FA Lockout on a Local Environment (Optional)

If you have physical access to the machine, you can boot into *rescue mode* to disable 2FA. Rescue mode is a *target* type (similar to a <u>runlevel</u>) in Linux that is used to preform administrative tasks. You will need to edit some settings in *GRUB*, which is the default boot loader in Ubuntu, to enter rescue mode.

To access GRUB, you will first reboot your machine:

\$ reboot

When the GRUB menu appears, make sure the **Ubuntu** entry is highlighted. This is the default name on a 18.04 installation, but may be different if you manually changed it after installation.

GNU GRUB version 2.02

```
*Ubuntu
Advanced options for Ubuntu
Memory test (memtest86+)
Memory test (memtest86+, serial console 115200)
```

Press enter to boot the selected OS, `e' to edit the commands before booting or `c' for a command-line.

Use the ↑ and ↓ keys to select which entry is highlighted.

Next, press the e key on your keyboard to edit the GRUB configuration before booting into your system.

```
GNU GRUB version 2.02
<u>s</u>etparams 'Ubuntu'
        recordfail
        load_video
        gfxmode $linux_gfx_mode
        insmod gzio
        if [ x$grub_platform = xxen ]; then insmod xzio; insmod lzopio; \
fi
        insmod part_msdos
        insmod ext2
        set root='hd0,msdos1'
        if [ x$feature_platform_search_hint = xy ]; then
          search --no-floppy --fs-uuid --set=root --hint-bios=hd0,msdos1\
 --hint-efi=hd0,msdos1 --hint-baremetal=ahci0,msdos1 36014b12-a5a4-43a9\
-8bd3-6ec5bf0aa055
    Minimum Emacs-like screen editing is supported. TAB lists
    completions. Press Ctrl-x or F10 to boot, Ctrl-c or F2 for a
    command-line or ESC to discard edits and return to the GRUB
    menu.
```

In the file that appears, scroll down until you see a line that starts with linux and ends with \$vt_handoff. Go to the end of this line and append systemd.unit=rescue.target, making sure that you leave a space between \$vt_handoff and systemd.unit=rescue.target. This will tell your Ubuntu machine to boot into rescue mode.

```
GNU GRUB version 2.02
        insmod part_msdos
        insmod ext2
        set root='hd0,msdos1'
        if [ x$feature_platform_search_hint = xy ]; then
          search --no-floppy --fs-uuid --set=root --hint-bios=hd0,msdos1\
 --hint-efi=hd0,msdos1 --hint-baremetal=ahci0,msdos1 36014b12-a5a4-43a9\
-8bd3-6ec5bf0aa055
          search --no-floppy --fs-uuid --set=root 36014b12-a5a4-43a9-8bd\
3-6ec5bf0aa055
        linux
                     /boot/vmlinuz-4.15.0-29-generic root=UUID=36014b12-\
a5a4-43a9-8bd3-6ec5bf0aa055 ro quiet splash $vt_handoff systemd.unit=re\
scue.target_
        initrd
                      /boot/initrd.img-4.15.0-29-generic
    Minimum Emacs-like screen editing is supported. TAB lists
    completions. Press Ctrl-x or F10 to boot, Ctrl-c or F2 for a
    command-line or ESC to discard edits and return to the GRUB
    menu.
```

Once you have made the changes, save the file with the Ctrl+X keyboard combination. Your machine will reboot and you will find yourself at a command line. Press Enter to go into rescue mode.

```
[ 2.099208] piix4_smbus 0000:00:07.3: SMBus Host Controller not enabled!
[ 2.738665] sd 32:0:0:0: [sda] Assuming drive cache: write through
/dev/sda1: recovering journal
/dev/sda1: clean, 129567/1638400 files, 1464516/6553088 blocks
You are in rescue mode. After logging in, type "journalctl –xb" to view
system logs, "systemctl reboot" to reboot, "systemctl default" or "exit"
to boot into default mode.
Press Enter for maintenance
(or press Control-D to continue): _
```

Once in rescue mode, open the Google Authenticator configuration file. This will be located inside the locked-out user's SCROLL TO TOP

The first line in this file is the user's secret key, which is used to configure an authenticator app.

You now have two choices:

- You can copy the secret key and configure your authenticator app.
- If you want to start from a clean slate, you can delete the ~/.google-authenticator file altogether to disable 2FA for this user. After logging in again as the non-root user, you can configure 2FA once again and get a brand new secret key.

With either choice, you are able to recover from a 2FA lockout on a local environment by using the GRUB boot loader. In the next step, you will recover from a 2FA lockout on a remote environment.

Step 7 — Recovering from a 2FA Lockout on a Remote Environment (Optional)

If your non-root sudoer account is locked out on a remote machine, you can use the **root** user to temporarily disable 2FA or reconfigure 2FA.

Start by logging in to your machine with the root user:

\$ ssh root@your_server_ip

Once logged in, open the Google Authenticator settings file that is located inside the locked-out user's home directory:

\$ sudo nano /home/sammy/.google_authenticator

The first line in this file is the user's secret key, which is what you need to configure an authenticator app.


You now have two choices:

- If you want to set up a new or wiped device, you can use the secret key to reconfigure your authenticator app.
- If you want to start from a clean slate, you can delete the /home/sammy/.google_authenticator file altogether to disable 2FA for this user. After logging in as the non-root user, you can configure 2FA once again and get a brand new secret key.

With either choice, you were able to recover from a 2FA lockout on a local environment by using the **root** user.

Conclusion

In this tutorial, you configured 2FA on an Ubuntu 18.04 machine. With 2FA configured on your environment, you have added an extra layer of protection to your account and you have made your system more secure. In addition to your traditional authentication method, you will also have to enter an additional verification code to log in. This makes it impossible for an attacker who managed to acquire your login credentials to be able to log in to your account without this additional verification code.




Report an issue

About the authors





Still looking for an answer?



Comments

8 Comments	8	Co	m	m	er	nts
------------	---	----	---	---	----	-----

Leave a comment		

Sign In to Comment

- nalnononno March 22, 2019
- Hi thx for the great article, can we use these same steps to add 2fa to a website rather than a machine?

Mal

Reply Report

- one danielpellarini March 22, 2019
- Hey Mal! By "adding 2FA to a website", do you mean from the point of view of the developer or the end user?

In other words: are you the developer of a website, and you would like to support 2FA, or do you have an account on a website which already offers 2FA, and you would just like to enable it for your user account?

Reply Report

SCROLL TO TOP

malnononno March 23, 2019

, Hi Daniel

Thx for getting back to me, it is the first option I am a developer of a site and I would like to add 2FA to it to make admin a little more secure.

Mal

Reply Report

malnononno March 23, 2019

, Hi Daniel

Just to add further clarification it runs on a lamp stack on a digitalocean droplet Ubuntu 18.04.

Mal

Reply Report

danielpellarini March 23, 2019

ັ Hi Mal

That would be a bit different then, and it would also depend on what platform is powering your website. For example, WordPress already has some plugins which can help you with this if you don't want to develop everything yourself.

Alternatively, if you need to code the 2FA feature from scratch, you can use the Google Authenticator tools there too, provided you find a library for your programming language of choice.

Reply Report

dcmorse July 14, 2019

Per man 8 pam_google_authenticator you also need to set

ChallengeResponseAuthentication yes in /etc/ssh/sshd_config then run
systemctl reload sshd.

Reply Report

danielpellarini July 28, 2019

That's correct, but that's only necessary if you want to use the PAM module with sshd as well (look at the note in Step 3 of this tutorial: it links to another tutorial where the author mentions to set the ChallengeResponseAuthentication option to yes if you need SSH support).

Reply Report

I get stuk on this step: Requiring 2FA for Log In and sudo Requests

When i add this line per the instructions i can no longer login through SSH. It keeps asking me for verification codes in a endless loop. If i remove the line again i can login.

I have followed the first steps from the 16.04 guide as i am logging in remotely.

I haven't managed to get the 2fa for sudo working on Ubuntu or debian.

Any suggestions?

Reply Report



This work is licensed under a Creative Commons Attribution-NonCommercial-ShareAlike 4.0 International License.



BECOME A CONTRIBUTOR

You get paid; we donate to tech nonprofits.





GET OUR BIWEEKLY NEWSLETTER

Sign up for Infrastructure as a Newsletter.



HUB FOR GOOD

Working on improving health and education, reducing inequality, and spurring economic growth? We'd like to help.

Featured on Community Kubernetes Course Learn Python 3 Machine Learning in Python Getting started with Go Intro to Kubernetes

DigitalOcean Products Droplets Managed Databases Managed Kubernetes Spaces Object Storage Marketplace

Welcome to the developer cloud

DigitalOcean makes it simple to launch in the cloud and scale up as you grow – whether you're running one virtual machine or ten thousand.

SCROLL TO TOP

Learn More



© 2020 DigitalOcean, LLC. All rights reserved.

Company

About

Leadership

Blog

Careers

Partners

Referral Program

Press

Legal

Security & Trust Center

Products	Community	Contact
Pricing	Tutorials	Get Support
Products Overview	Q&A	Trouble Signing In?
Droplets	Tools and Integrations	Sales
Kubernetes	Tags	Report Abuse
Managed Databases	Product Ideas	System Status
Spaces	Write for DigitalOcean	
Marketplace	Presentation Grants	
Load Balancers	Hatch Startup Program	
Block Storage	Shop Swag	
API Documentation	Research Program	
Documentation	Open Source	
Release Notes	Code of Conduct	