Install HBase on Ubuntu 20.04 LTS

You can choose to install HBase in Standalone Mode or Pseudo-Distributed Mode. The setup process is similar to our Hadoop installation.

Step 1: Download and Install HBase

Check <u>latest Stable release version</u> before you download. For production use, I recommend you go with Stable release.

```
VER="2.2.4" wget http://apache.mirror.gtcomm.net/hbase/stable/hbase-$VER-bin.tar.gz
```

Extract Hbase archive downloaded.

```
tar xvf hbase-$VER-bin.tar.gz
sudo mv hbase-$VER/ /usr/local/HBase/
```

Update your \$PATH values.

```
export HBASE_HOME=/usr/local/HBase
export PATH=\$PATH:\$JAVA_HOME/bin:\$HADOOP_HOME/bin:\$HADOOP_HOME/sbin:\
$HBASE_HOME/bin
FOF
```

Update your shell environment values.

```
$ source .bashrc
$ echo $HBASE_HOME
/usr/local/HBase
```

Edit JAVA HOME in shell script hbase-env.sh:

```
$ sudo vim /usr/local/HBase/conf/hbase-env.sh
# Set JAVA_HOME - Line 27
export HBASE_DISABLE_HADOOP_CLASSPATH_LOOKUP="true"
export JAVA_HOME=/usr/lib/jvm/java-8-openjdk-amd64/
```

Step 2: Configure HBase

We will do configurations like we did for Hadoop. All configuration files for HBase are located on /usr/local/HBase/conf/ directory.

hbase-site.xml

Set data directory to an appropriate location on this file.

Option 1: Install HBase in Standalone Mode (Not recommended)

In standalone mode all daemons (HMaster, HRegionServer, and ZooKeeper) ran in one jvm process/instance

Create HBase root directory.

```
sudo mkdir -p /hadoop/HBase/HFiles
sudo mkdir -p /hadoop/zookeeper
sudo chown -R hadoop:hadoop /hadoop/
```

Open the file for editing.

```
sudo vim /usr/local/HBase/conf/hbase-site.xml
```

Now add the following configurations between the *<configuration>* and *</configuration>* tags to look like below.

By default, unless you configure hbase.rootdir property, your data is still stored in /tmp/.

Now start HBase by using **start-hbase.sh** script in HBase bin directory.

```
$ sudo su - hadoop
$ start-hbase.sh
running master, logging to /usr/local/HBase/logs/hbase-hadoop-master-hbase.out
```

Option 2: Install HBase in Pseudo-Distributed Mode (Recommended)

Our value hbase.rootdir earlier will start in Standalone Mode. Pseudo-distributed mode means that HBase still runs completely on a single host, but each HBase daemon (HMaster, HRegionServer, and ZooKeeper) runs as a separate process.

To install HBase in Pseudo-Distributed Mode, set its values to:

In this setup, Data is stored your data in HDFS instead.

Ensure Zookeeper directory is created.

```
sudo mkdir -p /hadoop/zookeeper
sudo chown -R hadoop:hadoop /hadoop/
```

Now start HBase by using **start-hbase.sh** script in HBase bin directory.

```
$ sudo su - hadoop
$ start-hbase.sh
```

localhost: running zookeeper, logging to /usr/local/HBase/bin/../logs/hbase-hadoop-zookeeper-hbase.out

running master, logging to /usr/local/HBase/logs/hbase-hadoop-master-hbase.out : running regionserver, logging to /usr/local/HBase/logs/hbase-hadoop-regionserver-hbase.out

Check the HBase Directory in HDFS:

\$ hadoop fs -ls /hbase

```
Found 9 items

drwxr-xr-x - hadoop supergroup
drwxr-xr-x - hadoop supergroup
/hbase/MasterProcWALs

drwxr-xr-x - hadoop supergroup
-rw-r--r-- 1 hadoop supergroup
drwxr-xr-x - hadoop supergroup
dryxr-xr-x - hadoop supergroup
```

Step 3: Managing HMaster & HRegionServer

The HMaster server controls the HBase cluster. You can start up to 9 backup HMaster servers, which makes 10 total HMasters, counting the primary.

The HRegionServer manages the data in its StoreFiles as directed by the HMaster. Generally, one HRegionServer runs per node in the cluster. Running multiple HRegionServers on the same system can be useful for testing in pseudo-distributed mode.

Master and Region Servers can be started and stopped using the local-master-backup.sh local-regionservers.sh.

```
$ local-master-backup.sh start 2 # Start backup HMaster
$ local-regionservers.sh start 3 # Start multiple RegionServers
```

• Each HMaster uses two ports (16000 and 16010 by default). The port offset is added to these ports, so using an offset of **2**, the backup HMaster would use ports *16002* and *16012*

The following command starts 3 backup servers using ports 16002/16012, 16003/16013, and 16005/16015.

```
$ local-master-backup.sh start 2 3 5
```

• Each RegionServer requires two ports, and the default ports are 16020 and 16030

The following command starts four additional RegionServers, running on sequential ports starting at 16022/16032 (base ports 16020/16030 plus 2).

```
$ local-regionservers.sh start 2 3 4 5
```

To stop, replace **start** parameter **stop** each command followed by the offset of the server to stop. Example.

```
$ local-regionservers.sh stop 5
```

Starting HBase Shell

Hadoop and Hbase should be running before you can use HBase shell. Here the correct order of starting services.

```
$ start-all.sh
$ start-hbase.sh
```

Then use HBase shell.

```
hadoop@hbase:~$ hbase shell
2019-04-07 10:44:43,821 WARN [main] util.NativeCodeLoader: Unable to load
native-hadoop library for your platform... using builtin-java classes where
SLF4J: Class path contains multiple SLF4J bindings.
SLF4J: Found binding in [jar:file:/usr/local/HBase/lib/slf4j-log4j12-
1.7.10.jar!/org/slf4j/impl/StaticLoggerBinder.class]
SLF4J: Found binding in
[jar:file:/usr/local/hadoop/share/hadoop/common/lib/slf4j-log4j12-1.7.25.jar!/
org/slf4j/impl/StaticLoggerBinder.class]
SLF4J: See http://www.slf4j.org/codes.html#multiple_bindings for an explanation.
SLF4J: Actual binding is of type [org.slf4j.impl.Log4jLoggerFactory]
HBase Shell
Use "help" to get list of supported commands.
Use "exit" to quit this interactive shell.
Version 1.4.9, rd625b212e46d01cb17db9ac2e9e927fdb201afa1, Wed Dec 5 11:54:10
PST 2018
hbase(main):001:0>
```

Stopping HBase.

stop-hbase.sh

You have successfully installed Hadoop and HBase on Ubuntu 20.04.