


# **Lab12-02 – Configuring and Verifying Extended ACLs**

## **Member list:**

1	นาย ปูรณสิทธิ์ ปิยวัชรวิจิตร 5710503444
2	นาย ้ภารุจ สิงหพันธุ์ 5710503495

## **Topology**



## **Addressing Table**

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/1	192.168.10.1	255.255.255.0	N/A
	Lo0	192.168.20.1	255.255.255.0	N/A
	S0/0/0 (DCE)	10.1.1.1	255.255.255.252	N/A
ISP	S0/0/0	10.1.1.2	255.255.255.252	N/A
	S0/0/1 (DCE)	10.2.2.2	255.255.255.252	N/A
	Lo0	209.165.200.225	255.255.255.224	N/A
	Lo1	209.165.201.1	255.255.255.224	N/A
R3	G0/1	192.168.30.1	255.255.255.0	N/A
	Lo0	192.168.40.1	255.255.255.0	N/A
	S0/0/1	10.2.2.1	255.255.255.252	N/A
S1	VLAN 1	192.168.10.11	255.255.255.0	192.168.10.1
S3	VLAN 1	192.168.30.11	255.255.255.0	192.168.30.1
PC-A	NIC	192.168.10.3	255.255.255.0	192.168.10.1
PC-C	NIC	192.168.30.3	255.255.255.0	192.168.30.1

## **Objectives**

Part 1: Set Up the Topology and Initialize Devices

Part 2: Configure Devices and Verify Connectivity

- Configure basic settings on PCs, routers, and switches.
- Configure OSPF routing on R1, ISP, and R3.

## Part 3: Configure and Verify Extended Numbered and Named ACLs

- Configure, apply, and verify a numbered extended ACL.
- Configure, apply, and verify a named extended ACL.

#### Part 4: Modify and Verify Extended ACLs

## **Background / Scenario**

Extended access control lists (ACLs) are extremely powerful. They offer a much greater degree of control than standard ACLs as to the types of traffic that can be filtered, as well as where the traffic originated and where it is going.

In this lab, you will set up filtering rules for two offices represented by R1 and R3. Management has established some access policies between the LANs located at R1 and R3, which you must implement. The ISP router between R1 and R3 does not have any ACLs placed on it. You would not be allowed any administrative access to an ISP router as you can only control and manage your own equipment.

**Note**: The routers used with CCNA hands-on labs are Cisco 1941 Integrated Services Routers (ISRs) with Cisco IOS Release 15.2(4)M3 (universalk9 image). The switches used are Cisco Catalyst 2960s with Cisco IOS Release 15.0(2) (lanbasek9 image). Other routers, switches, and Cisco IOS versions can be used.

Depending on the model and Cisco IOS version, the commands available and output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of the lab for the correct interface identifiers.

**Note**: Make sure that the routers and switches have been erased and have no startup configurations. If you are unsure, contact your instructor.

## **Required Resources**

- 3 Routers (Cisco 1941 with Cisco IOS Release 15.2(4)M3 universal image or comparable)
- 2 Switches (Cisco 2960 with Cisco IOS Release 15.0(2) lanbasek9 image or comparable)
- 2 PCs (Windows 7, Vista, or XP with terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet and serial cables as shown in the topology

## Part 1: Set Up the Topology and Initialize Devices

In Part 1, you will set up the network topology and clear any configurations if necessary.

- Step 1: Cable the network as shown in the topology.
- Step 2: Initialize and reload the routers and switches.

## Part 2: Configure Devices and Verify Connectivity

In Part 2, you will configure basic settings on the routers, switches, and PCs. Refer to the Topology and Addressing Table for device names and address information.

## Step 1: Configure IP addresses on PC-A and PC-C.

#### Step 2: Configure basic settings on R1.

- a. Disable DNS lookup.
- b. Configure the device name as shown in the topology.
- c. Create a loopback interface on R1.
- d. Configure interface IP addresses as shown in the Topology and Addressing Table.
- e. Configure a privileged EXEC mode password of class.
- f. Assign a clock rate of **128000** to the S0/0/0 interface.
- g. Assign **cisco** as the console and vty password and enable Telnet access. Configure **logging synchronous** for both the console and vty lines.
- h. Enable web access on R1 to simulate a web server with local authentication for user admin.

```
R1(config)# ip http server
R1(config)# ip http authentication local
R1(config)# username admin privilege 15 secret class
```

#### Step 3: Configure basic settings on ISP.

a. Configure the device name as shown in the topology.

- b. Create the loopback interfaces on ISP.
- c. Configure interface IP addresses as shown in the Topology and Addressing Table.
- d. Disable DNS lookup.
- e. Assign **class** as the privileged EXEC mode password.
- f. Assign a clock rate of **128000** to the S0/0/1 interface.
- g. Assign **cisco** as the console and vty password and enable Telnet access. Configure **logging synchronous** for both console and vty lines.
- h. Enable web access on the ISP. Use the same parameters as in Step 2h.

## Step 4: Configure basic settings on R3.

- a. Configure the device name as shown in the topology.
- b. Create a loopback interface on R3.
- c. Configure interface IP addresses as shown in the Topology and Addressing Table.
- d. Disable DNS lookup.
- e. Assign **class** as the privileged EXEC mode password.
- f. Assign **cisco** as the console password and configure **logging synchronous** on the console line.
- g. Enable SSH on R3.

```
R3(config)# ip domain-name cisco.com
R3(config)# crypto key generate rsa modulus 1024
R3(config)# line vty 0 4
R3(config-line)# login local
R3(config-line)# transport input ssh
```

h. Enable web access on R3. Use the same parameters as in Step 2h.

## Step 5: (Optional) Configure basic settings on S1 and S3.

- a. Configure the hostnames as shown in the topology.
- b. Configure the management interface IP addresses as shown in the Topology and Addressing Table.
- c. Disable DNS lookup.
- d. Configure a privileged EXEC mode password of class.
- e. Configure a default gateway address.

## Step 6: Configure OSPF routing on R1, ISP, and R3.

 Assign 1 as the OSPF process ID and advertise all networks on R1, ISP, and R3. The OSPF configuration for R1 is included for reference.

```
R1(config)# router ospf 1
R1(config-router)# network 192.168.10.0 0.0.0.255 area 0
R1(config-router)# network 192.168.20.0 0.0.0.255 area 0
R1(config-router)# network 10.1.1.0 0.0.0.3 area 0
```

b. After configuring OSPF on R1, ISP, and R3, verify that all routers have complete routing tables listing all networks. Troubleshoot if this is not the case.

## Step 7: Verify connectivity between devices.

**Note**: It is very important to verify connectivity **before** you configure and apply ACLs! Ensure that your network is properly functioning before you start to filter out traffic.

a.	From PC-A, ping PC-C and the loopback and serial interfaces on R3.
	Were your pings successful?Yes
b.	From R1, ping PC-C and the loopback and serial interface on R3.
	Were your pings successful?Yes
C.	From PC-C, ping PC-A and the loopback and serial interface on R1.
	Were your pings successful?Yes
d.	From R3, ping PC-A and the loopback and serial interface on R1.
	Were your pings successful?Yes
e.	From PC-A, ping the loopback interfaces on the ISP router.
	Were your pings successful?Yes
f.	From PC-C, ping the loopback interfaces on the ISP router.
	Were your pings successful?Yes
g.	Open a web browser on PC-A and go to <a href="http://209.165.200.225">http://209.165.200.225</a> on ISP. You will be prompted for a username and password. Use <b>admin</b> for the username and <b>class</b> for the password. If you are prompted to accept a signature, accept it. The router will load the Cisco Configuration Professional (CCP) Express in a separate window. You may be prompted for a username and password. Use <b>admin</b> for the username and <b>class</b> for the password.
h.	Open a web browser on PC-C and go to <a href="http://10.1.1.1">http://10.1.1.1</a> on R1. You will be prompted for a username and password. Use <b>admin</b> for username and <b>class</b> for the password. If you are prompted to accept a signature, accept it. The router will load CCP Express in a separate window. You may be prompted for a username and password. Use <b>admin</b> for the username and <b>class</b> for the password.
Part	3: Configure and Verify Extended Numbered and Named ACLs
	tended ACLs can filter traffic in many different ways. Extended ACLs can filter on source IP addresses, urce ports, destination IP addresses, destination ports, as well as various protocols and services.
Se	curity policies are as follows:
1.	Allow web traffic originating from the 192.168.10.0/24 network to go to any network.
2.	Allow an SSH connection to the R3 serial interface from PC-A.
3.	Allow users on 192.168.10.0/24 network access to 192.168.20.0/24 network.
4.	Allow web traffic originating from the 192.168.30.0/24 network to access R1 via the web interface and the 209.165.200.224/27 network on ISP. The 192.168.30.0/24 network should NOT be allowed to access any other network via the web.
bes	ooking at the security policies listed above, you will need at least two ACLs to fulfill the security policies. A st practice is to place extended ACLs as close to the source as possible. We will follow this practice for ese policies.

Step 1: Configure a numbered extended ACL on R1 for security policy numbers 1 and 2.

You will use a numbered extended ACL on R1. What are the ranges for extended ACLs?	
100-199	

a. Configure the ACL on R1. Use 100 for the ACL number. R1(config)# access-list 100 remark Allow Web & SSH Access R1(config)# access-list 100 permit tcp host 192.168.10.3 host 10.2.2.1 eq 22 R1(config)# access-list 100 permit tcp any any eq 80 What does the 80 signify in the command output listed above? http port To what interface should ACL 100 be applied? R1 s0/0/0 In what direction should ACL 100 be applied? b. Apply ACL 100 to the S0/0/0 interface. R1(config)# interface s0/0/0 R1(config-if)# ip access-group 100 out c. Verify ACL 100. 1) Open up a web browser on PC-A, and access http://209.165.200.225 (the ISP router). It should be successful; troubleshoot, if not. 2) Establish an SSH connection from PC-A to R3 using 10.2.2.1 for the IP address. Log in with admin and **class** for your credentials. It should be successful; troubleshoot, if not. 3) From privileged EXEC mode prompt on R1, issue the **show access-lists** command. R1# show access-lists Extended IP access list 100 10 permit tcp host 192.168.10.3 host 10.2.2.1 eq 22 (22 matches) 20 permit tcp any any eq www (111 matches) 4) From the PC-A command prompt, issue a ping to 10.2.2.1. Explain your results. Unreachable เพราะ ping ไม่ใช่ tcp ไม่ใช่ Ip จึง ping ไม่ผ่าน Step 2: Configure a named extended ACL on R3 for security policy number 3.

a. Configure the policy on R3. Name the ACL WEB-POLICY.

```
R3(config)# ip access-list extended WEB-POLICY
R3(config-ext-nacl)# permit tcp 192.168.30.0 0.0.0.255 host 10.1.1.1 eq 80
R3(config-ext-nacl)# permit tcp 192.168.30.0 0.0.0.255 209.165.200.224
0.0.0.31 eq 80
```

b. Apply ACL WEB-POLICY to the S0/0/1 interface.

```
R3(config-ext-nacl)# interface S0/0/1
R3(config-if)# ip access-group WEB-POLICY out
```

c. Verify the ACL WEB-POLICY.

	1)	From R3 privileged EXEC mode command p	prompt, issue the <b>show ip interface s0/0/1</b> command.		
	-)		WEB-POLICY		
		In what direction is the ACL applied?			
	2)		s http://209.165.200.225 (the ISP router). It should be		
	3)	B) From PC-C, open a web session to <a href="http://10.1.1.1">http://10.1.1.1</a> (R1). It should be successful; troubleshoot, if no			
	4)	) From PC-C, open a web session to <a href="http://209.165.201.1">http://209.165.201.1</a> (ISP router). It should fail; troubleshoot, if not.			
	5)	From a PC-C command prompt, ping PC-A.	What was your result and why?		
		ไม่ได้เพราะถูก filt ออก			
Part	4:	Modify and Verify Extended A	CLs		
ne	twor	se of the ACLs applied on R1 and R3, no pings rks on R1 and R3. Management has decided th 68.30.0/24 networks should be allowed. You mu			
Step :	1: I	Modify ACL 100 on R1.			
a. From R1 privileged EXEC mode, issue the <b>show access-lists</b> command.			access-lists command.		
	How many lines are there in this access list?2				
b.	En	ACL on R1.			
	R1 <b>0</b> .	L(config)# ip access-list extended L(config-ext-nacl)# 30 permit ip 19 0.0.255 L(config-ext-nacl)# end			
C.		sue the <b>show access-lists</b> command.			
0.		here did the new line that you just added appea	ar in ACL 100?		
		o the last line			
Step 2		Modify ACL WEB-POLICY on R3.			
a.	Fro	om R3 privileged EXEC mode, issue the <b>show</b>	access-lists command.		
	Но	ow many lines are there in this access list?	2		
b.	En	nter global configuration mode and modify the A	ACL on R3.		
	R3	B(config)# <b>ip access-list extended</b> B(config-ext-nacl)# <b>30 permit ip 19 0.0.255</b>			
	R3	B(config-ext-nacl)# end			
C.	lss	sue the <b>show access-lists</b> command to verify	that the new line was added at the end of the ACL.		
Step :	3: \	Verify modified ACLs.			
a.	Fro	om PC-A, ping the IP address of PC-C. Were t	he pings successful?Yes		
h.	Fro	om PC-C, ping the IP address of PC-A. Were t	he pings successful? Yes		

	Why did the ACLs work immediately for the pings after you changed them? เพราะทำการpermit ipให้แล้ว
Re	eflection
L.	Why is careful planning and testing of ACLs required?
	เพราะหากเกิดการวางคำสั่งที่ผิดพลาดอาจทำให้ต้องลบแล้วต้องrunใหม่ทั้งหมด ทำให้เสียเวลามาก
2.	Which type of ACL is better: standard or extended?
	ขึ้นอยู่กับการใช้งานเพราะ standard ใช้เฉพาะsource แต่extendedใช้ได้ทั้ง source และ destination port อาจทำให้ต้องconfig เยอะกา
3.	Why are OSPF hello packets and routing updates not blocked by the implicit <b>deny any</b> access control entry (ACE) or ACL statement of the ACLs applied to R1 and R3?
	เพราะการส่ง hello packets ส่งมาจาก serial interface ของ R1 และ R3 ที่ไม่ได้อยู่ในวง LAN
	และที่ Router isp ไม่ได้ทำการสร้าง ACLไว้จึงทำให้มี packet hello ส่งผ่านมาได้
	และที่ Router isp ไม่ได้ทำการสร้าง ACLไว้จึงทำให้มี packet hello ส่งผ่านมาได้

## **Router Interface Summary Table**

Router Interface Summary				
Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)

**Note**: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.