
#### Overview of last class


#### TCP flow control

- receiver "advertises" free buffer space by including rwnd value in TCP header of receiver-to-sender segments
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust RcvBuffer
- sender limits amount of unacked ("in-flight") data to receiver's rwnd value
- guarantees receive buffer will not overflow





receiver-side buffering

#### TCP 3-way handshake




### TCP: closing a connection






# Idealization: known loss packets can be lost, dropped at router due to full buffers


 sender only resends if packet known to be lost






#### Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered








- four senders
- multihop paths
- timeout/retransmit

Q: what happens as  $\lambda_{in}$  and  $\lambda_{in}$  increase?

A: as red  $\lambda_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue throughput  $\rightarrow 0$ 







#### another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

## Class Today

#### Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## TCP congestion control: additive increase multiplicative decrease


- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
  - additive increase: increase cwnd by I MSS every RTT until loss detected
  - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth

cwnd: TCP sender



## TCP Congestion Control: details



sender limits transmission:

$$\begin{array}{ccc} \text{LastByteSent-} & \leq & \text{cwnd} \\ \text{LastByteAcked} & \end{array}$$


 cwnd is dynamic, function of perceived network congestion

#### TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes


rate 
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

#### Pipelining: increased utilization



#### TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
  - initially cwnd = I MSS
  - double cwnd every RTT
  - done by incrementing cwnd for every ACK received
- <u>summary:</u> initial rate is slow but ramps up exponentially fast



#### TCP: detecting, reacting to loss

- loss indicated by timeout:
  - cwnd set to I MSS;
  - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
  - dup ACKs indicate network capable of delivering some segments
  - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to I (timeout or 3 duplicate acks)


#### TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.




- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event



<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/


#### Summary: TCP Congestion Control (Reno)




## TCP throughput

- avg. TCP thruput as function of window size, RTT?
  - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
  - avg. window size (# in-flight bytes) is 3/4 W
  - avg. thruput is 3/4W per RTT

avg TCP thruput = 
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec





#### TCP Futures: TCP over "long, fat pipes"


- example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput = 
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- ⇒ to achieve 10 Gbps throughput, need a loss rate of L =  $2 \cdot 10^{-10}$  a very small loss rate!
- new versions of TCP for high-speed

#### **TCP Fairness**


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



## Why is TCP fair?

#### two competing sessions:

- additive increase gives slope of I, as throughout increases
- multiplicative decrease decreases throughput proportionally



## Fairness (more)

#### Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - send audio/video at constant rate, tolerate packet loss


## Fairness, parallel TCP connections


- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
  - new app asks for I TCP, gets rate R/I0
  - new app asks for 11 TCPs, gets R/2

#### Explicit Congestion Notification (ECN)

#### network-assisted congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
- congestion indication carried to receiving host
- receiver (seeing congestion indication in IP datagram) ) sets ECE bit on receiver-to-sender ACK segment to notify sender of congestion





## Chapter 3: summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- instantiation, implementation in the Internet
  - UDP
  - TCP

#### next:

- leaving the network "edge" (application, transport layers)
- into the network "core"
- two network layer chapters:
  - data plane
  - control plane