Data Encryption Standard (DES)

Alex Corner

Sheffield Hallam University

Mechanical ciphers like Enigma allowed much more complex algorithms to be used for encryption.

- Mechanical ciphers like Enigma allowed much more complex algorithms to be used for encryption.
- ► They still didn't necessarily ensure security.

- Mechanical ciphers like Enigma allowed much more complex algorithms to be used for encryption.
- They still didn't necessarily ensure security.
- ► The advent of the computer allowed even more complex algorithms to be used, using the XOR operation in conjunction with more familiar methods of substitution and transposition.

- Mechanical ciphers like Enigma allowed much more complex algorithms to be used for encryption.
- They still didn't necessarily ensure security.
- ► The advent of the computer allowed even more complex algorithms to be used, using the XOR operation in conjunction with more familiar methods of substitution and transposition.
- ▶ In the 1970s two very different breakthroughs changed the face of cryptography:

- Mechanical ciphers like Enigma allowed much more complex algorithms to be used for encryption.
- They still didn't necessarily ensure security.
- ► The advent of the computer allowed even more complex algorithms to be used, using the XOR operation in conjunction with more familiar methods of substitution and transposition.
- In the 1970s two very different breakthroughs changed the face of cryptography:
 - Public Key Cryptography

- Mechanical ciphers like Enigma allowed much more complex algorithms to be used for encryption.
- They still didn't necessarily ensure security.
- ► The advent of the computer allowed even more complex algorithms to be used, using the XOR operation in conjunction with more familiar methods of substitution and transposition.
- ▶ In the 1970s two very different breakthroughs changed the face of cryptography:
 - Public Key Cryptography
 - DES

XOR: Exclusive-OR

▶ There are various ways to write the exclusive-OR. We might write x XOR y, or in logical notation $x \oplus y$. (Even sometimes $\underline{\vee}$.)

XOR: Exclusive-OR

- ▶ There are various ways to write the exclusive-OR. We might write x XOR y, or in logical notation $x \oplus y$. (Even sometimes $\underline{\vee}$.)
- lt is described by the truth table below:

X	У	$x \oplus y$
0	0	0
0	1	1
1	0	1
1	1	0

XOR: Exclusive-OR

- ▶ There are various ways to write the exclusive-OR. We might write x XOR y, or in logical notation $x \oplus y$. (Even sometimes $\underline{\vee}$.)
- ▶ It is described by the truth table below:

X	У	$x \oplus y$
0	0	0
0	1	1
1	0	1
1	1	0

This is in fact the same as performing modular arithmetic using modulus 2: $0+0=0=1+1 \mod 2$ and $1+0=1=0+1 \mod 2$.

X	У	$x \oplus y$
0	0	0
0	1	1
1	0	1
1	1	0

X	У	$x \oplus y$
0	0	0
0	1	1
1	0	1
1	1	0

▶ We can apply this operator to whole strings of bits.

X	У	$x \oplus y$
0	0	0
0	1	1
1	0	1
1	1	0

- ▶ We can apply this operator to whole strings of bits.
- lacktriangleright For example, calculating $1010 \oplus 1011$ we perform XOR on the bits individually.

X	У	$x \oplus y$
0	0	0
0	1	1
1	0	1
1	1	0

- ▶ We can apply this operator to whole strings of bits.
- lacktriangleright For example, calculating $1010 \oplus 1011$ we perform XOR on the bits individually.
- ► So $1010 \oplus 1011 = 0001$.

X	У	$x \oplus y$
0	0	0
0	1	1
1	0	1
1	1	0

- We can apply this operator to whole strings of bits.
- lacktriangleright For example, calculating $1010 \oplus 1011$ we perform XOR on the bits individually.
- ► So $1010 \oplus 1011 = 0001$.
- ▶ Digital data is generally stored in binary or hex, using bits, so this type of operation is well-suited for implementation in a computer-aided cipher scheme.

ASCII: American Standard Code for Information Interchange

DEC	OCT	HEX	BIN	Symbol	Description
65	101	41	01000001	Α	Uppercase A
66	102	42	01000010	В	Uppercase B
67	103	43	01000011	C	Uppercase C
68	104	44	01000100	D	Uppercase D
69	105	45	01000101	Ε	Uppercase E
70	106	46	01000110	F	Uppercase F
71	107	47	01000111	G	Uppercase G

 A standard way to encode text and other characters. Each character is represented by a 7-bit binary string.

ASCII: American Standard Code for Information Interchange

DEC	OCT	HEX	BIN	Symbol	Description
65	101	41	01000001	Α	Uppercase A
66	102	42	01000010	В	Uppercase B
67	103	43	01000011	C	Uppercase C
68	104	44	01000100	D	Uppercase D
69	105	45	01000101	Е	Uppercase E
70	106	46	01000110	F	Uppercase F
71	107	47	01000111	G	Uppercase G

- ▶ A standard way to encode text and other characters. Each character is represented by a 7-bit binary string.
- ▶ Microsoft Excel uses 8-bit ANSI as above not *quite* the same mapping of characters to strings.

Edgar Allen Poe: "Human ingenuity cannot concoct a cipher which human ingenuity cannot resolve."

Edgar Allen Poe: "Human ingenuity cannot concoct a cipher which human ingenuity cannot resolve." Wrong.

- ► Edgar Allen Poe: "Human ingenuity cannot concoct a cipher which human ingenuity cannot resolve." Wrong.
- ► The original idea of a **one-time pad** was developed in 1918 by Vernam and Mauborgne, implemented mechanically.

- ► Edgar Allen Poe: "Human ingenuity cannot concoct a cipher which human ingenuity cannot resolve." Wrong.
- ► The original idea of a **one-time pad** was developed in 1918 by Vernam and Mauborgne, implemented mechanically.
- ▶ The idea is to write the plaintext in binary, e.g., using ASCII.

- ► Edgar Allen Poe: "Human ingenuity cannot concoct a cipher which human ingenuity cannot resolve." Wrong.
- ► The original idea of a **one-time pad** was developed in 1918 by Vernam and Mauborgne, implemented mechanically.
- ▶ The idea is to write the plaintext in binary, e.g., using ASCII.
- ▶ Then a random key of 0s and 1s is chosen which is the same length as the plaintext.

- ► Edgar Allen Poe: "Human ingenuity cannot concoct a cipher which human ingenuity cannot resolve." Wrong.
- ► The original idea of a **one-time pad** was developed in 1918 by Vernam and Mauborgne, implemented mechanically.
- ▶ The idea is to write the plaintext in binary, e.g., using ASCII.
- ▶ Then a random key of 0s and 1s is chosen which is the same length as the plaintext.
- Encryption is performed via the XOR operation and the key is then discarded.

- ► Edgar Allen Poe: "Human ingenuity cannot concoct a cipher which human ingenuity cannot resolve." Wrong.
- ► The original idea of a **one-time pad** was developed in 1918 by Vernam and Mauborgne, implemented mechanically.
- ▶ The idea is to write the plaintext in binary, e.g., using ASCII.
- ▶ Then a random key of 0s and 1s is chosen which is the same length as the plaintext.
- Encryption is performed via the XOR operation and the key is then discarded.
- Shannon and Kotelnikov had both showed that this encryption scheme is *theoretically* unbreakable.

▶ Theoretically unbreakable, but not really very practical.

- ► Theoretically unbreakable, but not really very practical.
 - 1. There is a problem generating a truly random sequence. Computers can never produce truly random numbers, only **pseudo-random** numbers, which are prone to attack.

- ▶ Theoretically unbreakable, but not really very practical.
 - 1. There is a problem generating a truly random sequence. Computers can never produce truly random numbers, only **pseudo-random** numbers, which are prone to attack.
 - 2. It requires a very long key which is computationally expensive to produce and difficult to distribute securely.

- ▶ Theoretically unbreakable, but not really very practical.
 - 1. There is a problem generating a truly random sequence. Computers can never produce truly random numbers, only **pseudo-random** numbers, which are prone to attack.
 - 2. It requires a very long key which is computationally expensive to produce and difficult to distribute securely.
 - 3. A new key is required each time.



▶ DES: Data Encryption Standard.



- ▶ DES: Data Encryption Standard.
- ▶ Developed by Horst Feistel at IBM.



- ▶ DES: Data Encryption Standard.
- Developed by Horst Feistel at IBM.
- ► The National Bureau of Standards held a competition in 1974: IBM submitted Lucifer.



- ▶ DES: Data Encryption Standard.
- Developed by Horst Feistel at IBM.
- The National Bureau of Standards held a competition in 1974: IBM submitted Lucifer.
- Dataseal



- ▶ DES: Data Encryption Standard.
- Developed by Horst Feistel at IBM.
- The National Bureau of Standards held a competition in 1974: IBM submitted Lucifer.
- ▶ Dataseal → Demonstration Cipher



- ▶ DES: Data Encryption Standard.
- Developed by Horst Feistel at IBM.
- The National Bureau of Standards held a competition in 1974: IBM submitted Lucifer.
- ▶ Dataseal → Demonstration Cipher → Demon



- ▶ DES: Data Encryption Standard.
- Developed by Horst Feistel at IBM.
- The National Bureau of Standards held a competition in 1974: IBM submitted Lucifer.
- ▶ Dataseal \rightarrow Demonstration Cipher \rightarrow Demon \rightarrow Lucifer



- ▶ DES: Data Encryption Standard.
- Developed by Horst Feistel at IBM.
- The National Bureau of Standards held a competition in 1974: IBM submitted Lucifer.
- ▶ Dataseal \rightarrow Demonstration Cipher \rightarrow Demon \rightarrow Lucifer \rightarrow DES.

Development of DES



- ▶ DES: Data Encryption Standard.
- Developed by Horst Feistel at IBM.
- The National Bureau of Standards held a competition in 1974: IBM submitted Lucifer.
- ▶ Dataseal \rightarrow Demonstration Cipher \rightarrow Demon \rightarrow Lucifer \rightarrow DES.
- ► Made the official worldwide standard in 1977.

▶ A large key size or length is an important part of a secure cryptographic system.

- ▶ A large key size or length is an important part of a secure cryptographic system.
- ➤ Some people, such as Whitfield Diffie and Martin Hellman, believed the DES key size to be too small to be secure.

- ▶ A large key size or length is an important part of a secure cryptographic system.
- ➤ Some people, such as Whitfield Diffie and Martin Hellman, believed the DES key size to be too small to be secure.
- ▶ It was 56 bits compared to IBM's original Lucifer key size of 128 bits.

- ▶ A large key size or length is an important part of a secure cryptographic system.
- ➤ Some people, such as Whitfield Diffie and Martin Hellman, believed the DES key size to be too small to be secure.
- ▶ It was 56 bits compared to IBM's original Lucifer key size of 128 bits.
- ▶ Others believed the National Security Agency (NSA) had included a **trapdoor**: a secret weakness which could be exploited by the security agencies.

- ▶ A large key size or length is an important part of a secure cryptographic system.
- ➤ Some people, such as Whitfield Diffie and Martin Hellman, believed the DES key size to be too small to be secure.
- ▶ It was 56 bits compared to IBM's original Lucifer key size of 128 bits.
- Others believed the National Security Agency (NSA) had included a trapdoor: a secret weakness which could be exploited by the security agencies.
- The most widely used cryptographic method ever designed largely used for secure financial transactions by banks.

- A large key size or length is an important part of a secure cryptographic system.
- ➤ Some people, such as Whitfield Diffie and Martin Hellman, believed the DES key size to be too small to be secure.
- ▶ It was 56 bits compared to IBM's original Lucifer key size of 128 bits.
- ▶ Others believed the National Security Agency (NSA) had included a **trapdoor**: a secret weakness which could be exploited by the security agencies.
- ► The most widely used cryptographic method ever designed largely used for secure financial transactions by banks.
- Expected to be used for 10 years from 1977.

- ▶ A large key size or length is an important part of a secure cryptographic system.
- ➤ Some people, such as Whitfield Diffie and Martin Hellman, believed the DES key size to be too small to be secure.
- ▶ It was 56 bits compared to IBM's original Lucifer key size of 128 bits.
- ▶ Others believed the National Security Agency (NSA) had included a **trapdoor**: a secret weakness which could be exploited by the security agencies.
- ► The most widely used cryptographic method ever designed largely used for secure financial transactions by banks.
- Expected to be used for 10 years from 1977. Triple-DES, or 3DES, developed in 1981 to be more secure, but is now also disallowed as of 2023.

► The ciphers we have seen so far have all been **stream ciphers**: each letter is encrypted separately.

- ► The ciphers we have seen so far have all been **stream ciphers**: each letter is encrypted separately.
- ▶ DES and many modern ciphers are a form of **block cipher**: how letters are encrypted depends on the letters around them.

- ► The ciphers we have seen so far have all been **stream ciphers**: each letter is encrypted separately.
- ▶ DES and many modern ciphers are a form of **block cipher**: how letters are encrypted depends on the letters around them.
- ► **Confusion:** Obscures the relationship between the key and the ciphertext typically achieved with substitution.

- ► The ciphers we have seen so far have all been **stream ciphers**: each letter is encrypted separately.
- ▶ DES and many modern ciphers are a form of **block cipher**: how letters are encrypted depends on the letters around them.
- ► **Confusion:** Obscures the relationship between the key and the ciphertext typically achieved with substitution.
- ▶ **Diffusion:** Spreads the influence of one plaintext bit over many ciphertext bits to hide statistical properties of the plaintext typically achieved with transposition.

- ► The ciphers we have seen so far have all been **stream ciphers**: each letter is encrypted separately.
- ▶ DES and many modern ciphers are a form of **block cipher**: how letters are encrypted depends on the letters around them.
- ► **Confusion:** Obscures the relationship between the key and the ciphertext typically achieved with substitution.
- ▶ **Diffusion:** Spreads the influence of one plaintext bit over many ciphertext bits to hide statistical properties of the plaintext typically achieved with transposition.
- ▶ Multiple Rounds: Intended to amplify the effect of confusion and diffusion.

▶ Keys in DES are of length 56, but are expanded by **parity bits** to be 64 bits.

▶ Keys in DES are of length 56, but are expanded by **parity bits** to be 64 bits.

▶ The first seven bits (on the left) are 0101100.

▶ Keys in DES are of length 56, but are expanded by **parity bits** to be 64 bits.

- ▶ The first seven bits (on the left) are 0101100.
- ▶ We put an extra bit on the *right* to make an *odd* number of 1s in each 8-bit byte:

0101100

▶ Keys in DES are of length 56, but are expanded by **parity bits** to be 64 bits.

- ▶ The first seven bits (on the left) are 0101100.
- ▶ We put an extra bit on the *right* to make an *odd* number of 1s in each 8-bit byte:

0101100<mark>0</mark>.

▶ Keys in DES are of length 56, but are expanded by **parity bits** to be 64 bits.

- ▶ The first seven bits (on the left) are 0101100.
- ► We put an extra bit on the *right* to make an *odd* number of 1s in each 8-bit byte: 01011000.

In hex this is $0101\,1000_2 = 58_{16}$.

▶ Keys in DES are of length 56, but are expanded by **parity bits** to be 64 bits.

- ▶ The first seven bits (on the left) are 0101100.
- ▶ We put an extra bit on the *right* to make an *odd* number of 1s in each 8-bit byte:


01011000.

- ▶ In hex this is $01011000_2 = 58_{16}$.
- ► This is done for all bytes, which eventually gives the key as:


$$K = 58$$
 1F BC 94 D3 A4 52 EA.

▶ DES consists of 16 **rounds**, each using a 48-bit **round key** K_i derived from the original 56-bit key K.


DES Scheme



DES Scheme: Single Round



DES Scheme: Mangler Function



DES Scheme: Right Expansion

A 32-bit right half is expanded to 48-bits in the following way, by repeating some of the bits.

32	1	2	3	4	5
4	5	6	7	8	9
8	9	10	11	12	13
12	13	14	15	16	17
16	17	18	19	20	21
20	21	22	23	24	25
24	25	26	27	28	29
28	29	30	31	32	1

DES Scheme: Right Expansion

A 32-bit right half is expanded to 48-bits in the following way, by repeating some of the bits.

```
32
   5 6 7 8 9
      10 11 12
               13
12
   13
      14 15
             16 17
16
  17
      18 19 20 21
20
   21 22 23 24 25
   25 26 27
             28 29
24
28
   29
      30 31
             32
                1
```

For example, if R = 000000010010001101000110100111, then

 $E(R) = 100000\,000010\,100100\,000110\,101000\,001010\,101100\,001110.$

DES Scheme: XOR with Round Key

After the right half is expanded, it is XORed with the current round key. E.g., the first 48-bit round key K_1 from our example key is

001001 111010 000101 101001 111001 011000 110111 011010.

When XORed with the expanded right half

 $100000\,000010\,100100\,000110\,101000\,001010\,101100\,001110$

we get

DES Scheme: S-Boxes

S_7							Co	lumr	ı Nu	mber						
Row No.	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15
0	4	11	2	14	15	0	8	13	3	12	9	7	5	10	6	1
1	13	0	11	7	4	9	1	10	14	3	5	12	2	15	8	6
2	1	4	11	13	12	3	7	14	10	15	6	8	0	5	9	2
3	6	11	13	8	1	4	10	7	9	5	0	15	14	2	3	12

► Each block passes through a separate S-box.

S ₇							Co	lumr	ı Nu	mber						
Row No.	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15
0	4	11	2	14	15	0	8	13	3	12	9	7	5	10	6	1
1	13	0	11	7	4	9	1	10	14	3	5	12	2	15	8	6
2	1	4	11	13	12	3	7	14	10	15	6	8	0	5	9	2
3	6	11	13	8	1	4	10	7	9	5	0	15	14	2	3	12

- ► Each block passes through a separate S-box.
- ▶ A block $b_1b_2b_3b_4b_5b_6$ is split into a pair $(b_1b_6, b_2b_3b_4b_5)$.

S ₇							Co	lumr	ı Nu	mber	•					
Row No.	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15
0	4	11	2	14	15	0	8	13	3	12	9	7	5	10	6	1
1	13	0	11	7	4	9	1	10	14	3	5	12	2	15	8	6
2	1	4	11	13	12	3	7	14	10	15	6	8	0	5	9	2
3	6	11	13	8	1	4	10	7	9	5	0	15	14	2	3	12

- Each block passes through a separate S-box.
- ► A block $b_1b_2b_3b_4b_5b_6$ is split into a pair $(b_1b_6, b_2b_3b_4b_5)$.
- ► The left part is a 2-bit binary number (decimal 0-3), the right part is a 4-bit binary number (decimal 0-15).


<i>S</i> ₇							Co	lumr	ı Nu	mber	•					
Row No.	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15
0	4	11	2	14	15	0	8	13	3	12	9	7	5	10	6	1
1	13	0	11	7	4	9	1	10	14	3	5	12	2	15	8	6
2	1	4	11	13	12	3	7	14	10	15	6	8	0	5	9	2
3	6	11	13	8	1	4	10	7	9	5	0	15	14	2	3	12

- Each block passes through a separate S-box.
- ► A block $b_1b_2b_3b_4b_5b_6$ is split into a pair $(b_1b_6, b_2b_3b_4b_5)$.
- ► The left part is a 2-bit binary number (decimal 0-3), the right part is a 4-bit binary number (decimal 0-15).
- ▶ These give the row and column to look up in the S-box.

S ₇		Column Number														
Row No.	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15
0	4	11	2	14	15	0	8	13	3	12	9	7	5	10	6	1
1	13	0	11	7	4	9	1	10	14	3	5	12	2	15	8	6
2	1	4	11	13	12	3	7	14	10	15	6	8	0	5	9	2
3	6	11	13	8	1	4	10	7	9	5	0	15	14	2	3	12

- Each block passes through a separate S-box.
- ► A block $b_1b_2b_3b_4b_5b_6$ is split into a pair $(b_1b_6, b_2b_3b_4b_5)$.
- ► The left part is a 2-bit binary number (decimal 0-3), the right part is a 4-bit binary number (decimal 0-15).
- ▶ These give the row and column to look up in the S-box.
- ▶ Block seven (011110) becomes (00, 1111) = (0, 15), giving 1 = 0001.

DES Scheme



Feistel System and Decryption

- ► The DES scheme is an example of a **Feistel system**:
 - Ladder structure;
 - Input split into left and right halves;
 - ▶ A round function of one half is computed and combined with the other half using bitwise XOR;
 - The halves are swapped over.

Feistel System and Decryption


- ► The DES scheme is an example of a **Feistel system**:
 - Ladder structure:
 - Input split into left and right halves;
 - ▶ A round function of one half is computed and combined with the other half using bitwise XOR;
 - ► The halves are swapped over.
- ▶ To decrypt the ciphertext: retrace all the steps in the 16 rounds using the same key K, but with the round keys used in the opposite order.

Modes of Operation

Five standard ways of implementing DES:


- ► Mode 1: Electronic Code Book
- Mode 2: Cipher Block Chaining
- Mode 3: Cipher Feedback Mode
- ► Mode 4: Output Feedback Mode
- Mode 5: Counter Mode

Modes of Operation: Electronic Code Book



Electronic Codebook (ECB) mode encryption


Modes of Operation: Electronic Code Book



Electronic Codebook (ECB) mode encryption


ECB encrypts the blocks one after another, but is vulnerable to attack for long messages because of plaintext patterns.

Modes of Operation: Cipher Block Chaining



Cipher Block Chaining (CBC) mode encryption

Modes of Operation: Cipher Block Chaining



Cipher Block Chaining (CBC) mode encryption


CBC uses the previous ciphertext block XORed with the new plaintext block before proceeding with encryption. An Initialisation Vector (IV) is used to XOR the first plaintext block. ECB is better at hiding plaintext patterns than ECB.

Modes of Operation: ECB vs Other Modes




Modes of Operation: ECB vs Other Modes





Modes of Operation: ECB vs Other Modes



▶ DES was expected to be used for 10 years: 1977-1987.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- ▶ It remained the standard **secret key** encryption method until 1998.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- lt remained the standard **secret key** encryption method until 1998.
- Ongoing debates about security of DES focussed on the short key length.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- lt remained the standard **secret key** encryption method until 1998.
- Ongoing debates about security of DES focussed on the short key length.
- ▶ Brute force attacks were theoretically possible, but the hardware in the 1970s would take too long to make this an efficient attack.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- lt remained the standard **secret key** encryption method until 1998.
- Ongoing debates about security of DES focussed on the short key length.
- ▶ Brute force attacks were theoretically possible, but the hardware in the 1970s would take too long to make this an efficient attack.
- In the 1980s rumours circulated that intelligence agencies had already built machines to search for DES keys.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- lt remained the standard **secret key** encryption method until 1998.
- Ongoing debates about security of DES focussed on the short key length.
- ▶ Brute force attacks were theoretically possible, but the hardware in the 1970s would take too long to make this an efficient attack.
- ▶ In the 1980s rumours circulated that intelligence agencies had already built machines to search for DES keys.
- By the 2000s, computers were 100,000 times more powerful making brute force attacks quite straightforward.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- lt remained the standard **secret key** encryption method until 1998.
- Ongoing debates about security of DES focussed on the short key length.
- ▶ Brute force attacks were theoretically possible, but the hardware in the 1970s would take too long to make this an efficient attack.
- ▶ In the 1980s rumours circulated that intelligence agencies had already built machines to search for DES keys.
- By the 2000s, computers were 100,000 times more powerful making brute force attacks quite straightforward.
- ightharpoonup A (second) challenge was issued in 1998 by the RSA Laboratory, with a \$10,000USD prize:
 - Electronic Frontier Foundation's DES Cracker, working as a botnet, took only 3 days to crack DES.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- lt remained the standard **secret key** encryption method until 1998.
- Ongoing debates about security of DES focussed on the short key length.
- ▶ Brute force attacks were theoretically possible, but the hardware in the 1970s would take too long to make this an efficient attack.
- ▶ In the 1980s rumours circulated that intelligence agencies had already built machines to search for DES keys.
- By the 2000s, computers were 100,000 times more powerful making brute force attacks quite straightforward.
- ightharpoonup A (second) challenge was issued in 1998 by the RSA Laboratory, with a \$10,000USD prize:
 - ▶ Electronic Frontier Foundation's DES Cracker, working as a botnet, took only 3 days to crack DES.
 - The previous record was 39 days.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- lt remained the standard **secret key** encryption method until 1998.
- Ongoing debates about security of DES focussed on the short key length.
- ▶ Brute force attacks were theoretically possible, but the hardware in the 1970s would take too long to make this an efficient attack.
- ▶ In the 1980s rumours circulated that intelligence agencies had already built machines to search for DES keys.
- By the 2000s, computers were 100,000 times more powerful making brute force attacks quite straightforward.
- ▶ A (second) challenge was issued in 1998 by the RSA Laboratory, with a \$10,000USD prize:
 - ▶ Electronic Frontier Foundation's DES Cracker, working as a botnet, took only 3 days to crack DES.
 - ► The previous record was 39 days.
 - ▶ In 1999, a network of 100,000 PCs on the Internet cracked DES in 22 hours and 15 minutes.

- ▶ DES was expected to be used for 10 years: 1977-1987.
- lt remained the standard **secret key** encryption method until 1998.
- Ongoing debates about security of DES focussed on the short key length.
- ▶ Brute force attacks were theoretically possible, but the hardware in the 1970s would take too long to make this an efficient attack.
- ▶ In the 1980s rumours circulated that intelligence agencies had already built machines to search for DES keys.
- ▶ By the 2000s, computers were 100,000 times more powerful making brute force attacks quite straightforward.
- ▶ A (second) challenge was issued in 1998 by the RSA Laboratory, with a \$10,000USD prize:
 - ▶ Electronic Frontier Foundation's DES Cracker, working as a botnet, took only 3 days to crack DES.
 - ► The previous record was 39 days.
 - ▶ In 1999, a network of 100,000 PCs on the Internet cracked DES in 22 hours and 15 minutes.
 - DES needed to be replaced.

► How do we make DES more secure?

▶ How do we make DES more secure? Run it twice: Double DES.

- ▶ How do we make DES more secure? Run it twice: Double DES.
- ightharpoonup The idea here is that this would double the keyspace from 2^{56} options to 2^{112} .

- ▶ How do we make DES more secure? Run it twice: Double DES.
- \triangleright The idea here is that this would double the keyspace from 2^{56} options to 2^{112} .
- ► Unfortunately, due to **meet-in-the-middle attacks**, this actually only increased the number of keys to 2⁵⁷.

► How do we make DES more secure?

▶ How do we make DES more secure? Run it *three* times.

- ▶ How do we make DES more secure? Run it *three* times.
- Uses three independent keys: K_1 , K_2 , K_3 .

- ▶ How do we make DES more secure? Run it *three* times.
- ▶ Uses three independent keys: K_1 , K_2 , K_3 .
- $\longrightarrow \mathsf{DES}(\mathsf{m},\mathsf{K}_1) \mapsto \mathsf{DES}^{-1}(\mathsf{DES}(\mathsf{m},\mathsf{K}_1),\mathsf{K}_2) \mapsto \mathsf{DES}(\mathsf{DES}^{-1}(\mathsf{DES}(\mathsf{m},\mathsf{K}_1),\mathsf{K}_2,\mathsf{K}_3))$

- ▶ How do we make DES more secure? Run it *three* times.
- ▶ Uses three independent keys: K_1 , K_2 , K_3 .
- $\blacktriangleright \ m \mapsto DES(m, K_1) \mapsto DES^{-1}(DES(m, K_1), K_2) \mapsto DES(DES^{-1}(DES(m, K_1), K_2, K_3))$
- ▶ If $K_1 = K_2 = K_3$, this is the same as single DES (good for backwards compatibility).

- ▶ How do we make DES more secure? Run it *three* times.
- ▶ Uses three independent keys: K_1 , K_2 , K_3 .
- $ightharpoonup m \mapsto DES(m, K_1) \mapsto DES^{-1}(DES(m, K_1), K_2) \mapsto DES(DES^{-1}(DES(m, K_1), K_2, K_3))$
- ▶ If $K_1 = K_2 = K_3$, this is the same as single DES (good for backwards compatibility).
- ▶ Often used with two keys, setting $K_1 = K_3$, but keeping K_2 independent.

- ▶ How do we make DES more secure? Run it *three* times.
- ▶ Uses three independent keys: K_1 , K_2 , K_3 .
- $ightharpoonup m\mapsto DES(m,K_1)\mapsto DES^{-1}(DES(m,K_1),K_2)\mapsto DES(DES^{-1}(DES(m,K_1),K_2,K_3))$
- ▶ If $K_1 = K_2 = K_3$, this is the same as single DES (good for backwards compatibility).
- ▶ Often used with two keys, setting $K_1 = K_3$, but keeping K_2 independent.
- ► Much stronger against meet-in-the-middle attacks.

▶ 3DES encryption was the standard for ATMs: all machines had to be compliant by 2005.

- ▶ 3DES encryption was the standard for ATMs: all machines had to be compliant by 2005.
- ► CVE-2016-2183 (Critical Vulnerabilities and Exposures) released in 2016 describes the 'Sweet32' attack (a type of **birthday attack**, which shows that even Triple DES was not sufficient any more.

- ▶ 3DES encryption was the standard for ATMs: all machines had to be compliant by 2005.
- ➤ CVE-2016-2183 (Critical Vulnerabilities and Exposures) released in 2016 describes the 'Sweet32' attack (a type of **birthday attack**, which shows that even Triple DES was not sufficient any more.
- All applications of 3DES were to cease by 2023.

- ▶ 3DES encryption was the standard for ATMs: all machines had to be compliant by 2005.
- ► CVE-2016-2183 (Critical Vulnerabilities and Exposures) released in 2016 describes the 'Sweet32' attack (a type of **birthday attack**, which shows that even Triple DES was not sufficient any more.
- All applications of 3DES were to cease by 2023.
- DES finally superseded by the Advanced Encryption Standard (AES).

Tutorials

In the tutorial this week we will:

- Create a spreadsheet to perform bitwise XOR encryption.
- Expand this to XOR whole words at a time.