

The Virtual Laboratory

LPFG Reference Manual

Last updated: December 11, 2022

Copyright © The Authors 1990-2022 (see Document Revision History, Section 12). This document is distributed under the terms of the Creative Commons Attribution-ShareAlike CC BY-SA 4.0 license (https://creativecommons.org/licenses/by-sa/4.0/), which permits reproduction, redistribution and adaptation of the material, provided the original work is properly cited, changes, if any are indicated, and the derivative material is distributed under the same license as the original.

Contents

1	Intr	oduction		4
	1.1	Running lpfg		4
		1.1.1 Command line options		4
		1.1.2 Input files		5
	1.2	User Interface		
		1.2.1 View manipulation		
		1.2.2 Main menu		
		1.2.3 Animate menu		
	1.3	File monitoring		
	1.0	I no monitoring	•	J
2	The	L-system file		10
	2.1	Derivation Length		10
	2.2	Axiom statement		10
	2.3	Module and type declarations		
		2.3.1 Modules		
		2.3.2 Types		
		219.12 1,pos	•	
3	Pro	luctions		12
	3.1	The predecessor		12
		3.1.1 The strict predecessor		12
		3.1.2 Left and right context		
		3.1.3 Left and right new context		
		3.1.4 Ring L-systems		
	3.2	Production body		
		3.2.1 The produce statement		
		3.2.2 The produce statement		
	3.3	Testing context within a production body		
	0.0	Tobbing context within a production body		10
4	Con	crol statements		18
	4.1	Start and End statements		18
	4.2	Ignore and Consider statements		18
	4.3	Decomposition and Interpretation Rules		
		4.3.1 Decomposition Rules		
		4.3.2 Interpretation rules		
		4.3.3 Rule blocks		
	4.4	Production groups		
		1 roduction 61 caps		
5	Pre	lefined modules		2 3
	5.1	Position and drawing		23
	5.2	Turtle rotations		24
	5.3	Display parameters		24
	5.4	Branching structures		
	5.5	Circles and spheres		
	5.6	Polygons, rhombi, and isosceles triangles		
	5.7	Surfaces and Meshes		
	5.8	Generalized cylinders		
	5.9	Textures		
		Labels		
		Tropism Control		21

	5.12	Query modules	28
		Environment communication	
	5.14	Dynamic view control	29
	5.15	Mouse interaction	29
6			30
	6.1	Controlling the simulation	
		6.1.1 Simulation progress	
		6.1.2 L-system derivation	
		6.1.3 Communication with the environment	31
	6.2	Accessing externally defined entities	31
		6.2.1 Parameters	31
		6.2.2 Graphically defined functions	
		6.2.3 Graphically defined curves	
		6.2.4 Graphically defined surfaces	
	6.3	Auxiliary math functions	
	0.0	6.3.1 Vector algebra	
		6.3.2 Random number generation	
	C 1		
	6.4	View-related functions	
	6.5	Mouse and menu functions	
	6.6	Input and output functions	35
7	۸ ۵.	annead tentes	36
1			
	7.1	Dynamic surfaces	
		7.1.1 Creating dynamic surfaces	
		7.1.2 Manipulating dynamic surfaces	
	7.2	Gillespie groups	
	7.3	Multi-view mode	38
	7.4	Mouse interactions	38
	7.5	User-Defined Menus	41
8		J - F	42
	8.1	View file	
		8.1.1 Setting the view	
		8.1.2 Rendering commands	43
		8.1.3 Geometry presentation	44
		8.1.4 Tropism commands	45
		8.1.5 External files	46
		8.1.6 Fonts	
		8.1.7 Postscript output control	
		8.1.8 Deprecated commands	
	8.2	•	41 48
	0.2	Allimation life	±0
9	App	pendix: Production Matching	49
10		1	52
	10.1	I control of the cont	52
		0 1	52
		10.1.2 Dynamic B-spline surfaces	52
	10.2	Tablet interaction	53
	10.3	Terrain	53
			54

11 Credits	56
12 Document revision history	56

1 Introduction

lpfg is a plant modeling program based on the formalism of L-systems but also has many other applications, such as the generation of fractals. Models are defined using the L+C language, which extends the syntax of C++ to include constructs inherent in L-systems. It is assumed that the reader is familiar with C/C++ and with the basic concepts of modeling with L-systems as introduced in [1] and the **CPFG Reference** manual. While simple L-system models may be created more compactly using cpfg, the powerful programming constructs in lpfg make it preferable for the development of complex models [2; 3].

This is a reference manual with limited examples. However, sample vlab objects are indicated in some sections to illustrate usage.

1.1 Running lpfg

lpfg is included with the vlab distribution, and is normally run from an object's menu within vlab. The command line below is defined in the object's specification file.

Command line options may appear in any order. In general, the only mandatory argument is the L-system file, *lsystem.*1, which contains the L+C code for the model. (See the -d11/-o options for an exception.)

1.1.1 Command line options

Option	Description
-a	Start <i>lpfg</i> in animate mode, using the information in <i>animationfile.a.</i> Only first frame steps are performed, as opposed to derivation length steps.
-b	Start <i>lpfg</i> in batch mode: no window is created. The simulation is performed and the final content of the string is stored in the file specified by the -out option. Only module names are stored in the file. This mode cannot be combined with the -a option.
-c	Compile the L-system into object code, and create a shared library file called lsys.so. This library can subsequently be used by <i>lpfg</i> to run the L-system model without recompiling (see the -dll and -o options). Do not run the simulation.
-cleanEA20	Zero the array of (20) return values from an environmental program before the next iteration. This is used to ensure the array is clear if an environmental program returns an arbitrary number of values. See the <i>vlab</i> Environmental Progams manual for more information.
-cn	Check for numerical errors in the arguments of turtle movement modules. When this option is included, <i>lpfg</i> checks that the arguments to modules such as F and Right are valid numbers. It is useful for finding division-by-zero errors in the model.
-d	Start $lpfg$ in debug mode. Information regarding the execution of the program is sent to the standard output. This mode is intended for $lpfg$ developers only.

1 INTRODUCTION 5

Option	Description
-dll filename.so -o filename.so	Use the precompiled library file <i>filename</i> .so (usually lsys.so unless explicitly renamed) instead of <i>lsystem</i> .l. See the -c option. This is useful when a simulation will be run many times but the L-system does not change (although other input files may). These two options are synonymous.
-ds	Output the current string to the console after each derivation step, before the interpretation: block.
-dtf	Output the final interpreted string to a file (i.e. after the interpretation: block). Uses the filename: Lsystemfile.str.
-dtfes	Output the interpreted string after each derivation step, to separate files. Uses the filename: Lsystemfile.str, but with an 8-digit suffix. For example the first string output would be in Lsystemfile00000001.str.
-out filename	In batch mode, use <i>filename</i> for the output string. This will be a text file. In regular (not batch) mode, run the model to the end and produce a single image in <i>filename</i> , based on the extension: bmp, jpg, pdf, png, tiff. The model window will close on completion. Also see the Save As menu item (Section 1.2.2).
-q	Start <i>lpfg</i> in quiet mode. All messages, including warnings and errors, are suppressed.
-rmode $mode$	Define the method for re-reading input files. The values of mode are: expl = explicit cont = continuous trig = triggered The refresh mode may also be set with the Refresh mode menu item (Section 1.2.2), and within a vlab object's specification file (see the vlab Framework manual).
-ν	Start $lpfg$ in verbose mode. Displays additional information/warning messages.
-w w h	Specify the width w and height h of the $lpfg$ output window in pixels. Use either this option or $-wr$, but not both.
-wnb	Create the $lpfg$ window without borders or title bar. This mode is useful for demonstration purposes.
-wp <i>x y</i>	Specify the $lpfg$ window's top left corner position (x,y) in pixels relative to the top left corner of the screen. Use either this option or $-wpr$ but not both.
-wpr x y	Specify the relative window position of the $lpfg$ window: x and y are numbers between 0 and 1, and represent the position of the top left corner of the window relative to the top left corner of the screen. Use either this option or $-$ wp but not both.
-wr w h	Specify the relative window size of the $lpfg$ window: w and h parameters are numbers between 0 and 1 and specify the relative size of the $lpfg$ output window with respect to the screen. Use either this option or $-w$ but not both.

1.1.2 Input files

Input files are recognized based on their extension. The L+C modeling language in lsystem.1 is described in this manual, as are the lpfg-specific input files, animation.a and view.v (Sections 8.2 and 8.1 respectively). Other file types can be found in the vlab Tools manual.

When the refresh mode is set to Triggered/Continuous, either from the command line (-rmode) or from the menu, lpfg turns on file monitoring to watch for changes in any of its input files. See Section 1.3 for more information on file monitoring.

1 INTRODUCTION 6

File	Description
lsystem.1	Defines the L+C model.
view.v	Defines the drawing and viewing parameters, including setting the view, rendering, surfaces, etc. See Section 8.1.
animation.a	Defines the parameters for controlling animation of the model. See Section 8.2.
colormap.map material.mat	Specifies 256 colors or 256 materials, respectively. A colormap is generally used to create schematic images, whereas material files are used to create realistic images. If no colormap file or material file is specified, the default colormap is used. See Section 5.3 for information on how to use the colors within $lpfg$, and the $palette$ and $medit$ tools in the $vlab$ Tools manual.
contourset.cset	Specifies contours defined as B-spline curves. There may be multiple <i>contour</i> .con files, each containing a single contour definition, but only one <i>contourset</i> .cset file containing multiple contour definitions. See Section 6.2.3 for information on how to access the contours within <i>lpfg</i> , and the <i>cuspy</i> and <i>gallery</i> tools in the <i>Vlab Tools</i> manual.
<pre>function.func functionset.fset timeline.tset</pre>	Specifies functions of one variable. The functions are defined as B-spline curves constrained in such a way that they assign exactly one y to every x in the normalized function domain $[0,1]$. There may be multiple $function.func$ files, each containing a single function definition, but only one $functionset.fset$ file containing multiple function definitions, and one $time-line.tset$ file containing functions constrained by a timeline rather than the normalized function domain. See Section 6.2.2 for information on how to access the functions within $lpfg$, and the $funcedit$, $gallery$, and $timeline$ tools in the $vlab$ Tools manual.
parameter.vset	Defines parameters that can be read from the L-system without recompiling. See Section 6.2.1 for the val function used to access the parameters within <i>lpfg</i> , as well as the file format.
environment.e	Specifies the environmental program and its parameters. See the <i>vlab</i> Environmental programs manual for more information.

1.2 User Interface

When lpfg is opened, it typically runs the L-system and graphically interprets the final string. (Some command line options, such as $\neg a$ and $\neg b$, produce different results.) Once the model is drawn it is possible to manipulate the view of the L-system, or make adjustments to it.

1.2.1 View manipulation

The view in the output window is manipulated using both the mouse buttons and the SHIFT and COMMAND keys within the lpfg window:

Action	Key & Mouse	Description
Rotation	Left mouse	Rotate around the Y axis by moving the mouse horizon- tally, and around the X axis by moving the mouse verti- cally.
Roll	SHIFT + middle mouse	Roll clockwise around the Z axis by moving the mouse to the right, and roll counter-clockwise by moving the mouse to the left.
Zoom	COMMAND + left or middle mouse	Zoom in by moving the mouse up, and zoom out by moving down.

Action	Key & Mouse	Description		
Pan	SHIFT + left mouse	Move model in all directions using the mouse.		
Change	COMMAND + middle	Increase the angle by moving the mouse up, and decrease		
frustrum	mouse	the angle by moving down. This operation has an effect		
angle		only in perspective projection mode.		

1.2.2 Main menu

A menu of options is displayed by clicking the right mouse button within the lpfg window. It includes the following menu items:

Menu item	Description
New model	Re-read all input files, recompile the L-system, reset the view, and run the simulation. This is equivalent to restarting the model from the object menu, but uses the existing $lpfg$ window rather than opening a new one.
New L-system	Re-read all input files, except the view and animation files, and re-run the simulation. The view is not reset.
New run	Re-run the simulation without re-reading (and recompiling) the L-system file, or re-reading the view and animation files. Other parameter files (colors, functions, etc.) are re-read.
New view	Re-read the view file, along with the materials/colormap, surfaces, and textures, and reset the view without re-running the simulation.
New rendering	Re-read the same files as New view, but reset the rendering parameters only, without changing the view or re-running the simulation.
Save	Save to the default file name and type. The initial file name is the same as the original L-system file, with a PNG extension. Use Save as to change the name and/or file type. The file used in the Save as window will then become the default file for this Save command.
Save as	Open a dialog window to save the current view with a different name and/or in a different format. (See below for a description of the dialog window).
String > Input	Input the binary form of an L-system string from the file, <i>lsystemfile.</i> strb. Generally, this is a file created earlier by String > Output.
String > Output	Output the current string to the file, lsystemfile.strb, in binary form.
Animate	Switch to animate mode and re-run the model, stopping and drawing the interpreted string at the first frame as defined in the animation file. Additional menu items are added to the menu (Section 1.2.3).
Refresh mode	Set the mode used to refresh the input files. The default is Explicit, where the menu options above must be used to re-read each file. Triggered/Continuous mode monitors all files for changes (see Section 1.3).
Exit	Quit $lpfg$.




Figure 1: An example of the Save as... dialog window.

In summary, the New commands include the following actions:

Menu item	Re-read (& recompile) L-system	Re-read view	Reset view	Reset rendering	Re-read colors, surfaces, textures	Re-read functions, contours, timeline, parameters
New model	X	X	X	X	x	X
New L-system	X				x	X
New run					X	X
New view		X	X	X	x	
New rendering		X		X	X	

The Save as menu item opens a dialog window such as the one in Figure 1. The fields in the window are:

Menu item	Description
Target Directory	The directory in which to save the file. The default is the <i>lab table</i> directory.
Name	The name of the file. The default is the same as the Save command. If this name is changed, it will become the default for subsequent Save and String commands. Note that the file extension cannot be edited; it is set based on the Type (and possibly the Format) field.
Numbering	Check this box to add a number to the file name. The number will be incremented automatically each time the file is saved. For example, if the file name in this dialog box is set to lsystem0000.png, subsequent Save commands will automatically save lsystem0001.png, lsystem0002.png, and so on. This can be used to save the frames of an animation.
Туре	The file type. This will set the extension in the Name field for all types except Image.
Format	Set the extension when Type is Image. This field is ignored for other types.
Alpha channel	Check this box to make the background transparent in the saved file.

1 INTRODUCTION 9

1.2.3 Animate menu

When Animate is selected from the menu, or the -a option is included on the command line (Section 1.1.1), the model is re-interpreted, stopping and drawing after the first frame defined in the animation file (Section 8.2), and the following menu items are added:

Menu item	Description	Keyboard shortcut
Step	Advance the simulation and redraw. This may correspond to more than one derivation step if the step parameter in the animation file is greater than 1.	Cmd+F
Run	Display consecutive animation frames after each step derivation steps until last frame is reached or passed.	Cmd+R
Forever	Start or resume the animation. After the last frame is reached the animation returns to the first frame and continues.	Cmd+V
Stop	Stop the animation.	Cmd+S
Rewind	Reset the animation to the first frame.	Cmd+W
Clear	Clear and redraw the latest frame. This is used if the clear between frames: parameter in the animation file is set to no.	
New animate	Re-read the animation file. Changes take effect when the simulation is re-run.	
Start recording	Record each frame of the animation as it is displayed, using the current file format specified in the Save option. To save each frame in a separate file, use the Save as option and set the Numbering checkbox.	
Don't animate	Stop the animation, and return to the original menu. Display the model at the first frame as defined in the animation file.	

Note that in lpfg the Rewind command returns to the axiom (whereas in cpfg it returns to the first derivation step), and the first frame defaults to 1, not 0.

1.3 FILE MONITORING

When Refresh mode is set to Triggered/Continuous, either from the command line (-rmode) or from the menu, *lpfg* turns on file monitoring to watch for changes in any of its input files. This allows changes to be made in the simulation as soon as a file is updated.

When a file change occurs, the following action is taken by lpfg:

File changed	Action
L-system	New L-system
View	New view
Animate	Rereads the animation file only.
Colormap	New rendering
Material	
Surface	New rendering
Texture	
Function	New run
Contour	
Timeline	
Parameters	

2 The L-system file

L-system files use the L+C modeling language [4; 5; 6]. It is a declarative language which combines L-system constructs (notably, modules and productions) within the general-purpose programming language C++. The principle advantage of this hybrid approach is that the expressive power of C++ can be used in L+C programs, making it easier to develop complex models.

A typical L+C program file has the following format:

```
#include <1pfgall.h>
// data structure declarations
// module declarations
// function declarations
derivation length: expression;
axiom: module list;
// productions
```

The three statements, #include, derivation length and axiom are mandatory, as well as declarations of all user-defined modules in the axiom and production(s).

Statements may appear in any order with the following restrictions:

- The #include statement should be the first line in the file. It contains embedded header files with declarations and definitions used by lpfg and the L2C translator, including predefined types. 2
- All elements referred to in a statement must be declared beforehand:
 - Types used as parameters of a module must be declared before the module is declared.
 - Modules must be declared before they appear in any statements.
- Productions are matched in the order in which they are listed in the L-system file. (The set of potentially applicable productions may change, however, from one derivation step to the next. See Section 4.4.)

2.1 Derivation Length

This statement specifies the number of derivation steps in the L-system, and has the format:

```
derivation length: expression
```

There are no restrictions on expression. Non-integer values are turncated to an integer. However, some care should be taken to ensure that expression is constant, as the behaviour of lpfg is undefined if the value changes during the simulation.

2.2 Axiom statement

The syntax of an axiom statement is:

```
axiom: module list;
```

where module list is a sequence of modules. Examples of valid axioms are:

¹Optional non-lpfg-specific header files should be included before lpfgall.h, since this file signals the start of the translation from L+C to C++.

 $^{^2}$ Most predefined types are described in this manual. For additional information see the lintrfc.h file.

```
axiom: A(1,2) B() A(0,0);
axiom: A(idx*2,(int)(sin(x*M_PI));
```

There are no commas between the modules in the list. If a module has no parameters, the parentheses may be omitted. For example, the first axiom above could be written as:

```
axiom: A(1,2) B A(0,0);
```

2.3 Module and type declarations

2.3.1 Modules

L+C requires that all modules be declared before they appear in any other statements. No module can be declared twice, even with a different number of parameters. Many standard modules are predefined (see Section 5) and, therefore, must not be redeclared. The syntax for declaring a new module is:

```
module name( ptypes );
```

where *name* is the module name, and *ptypes* is a list of the parameter types. If a module has no parameters, the parentheses can be omitted. For example:

```
module A(int, int);
module B;
module C(float, string);
```

Note that, unlike function arguments, module parameters have no names (they are identified by position). Thus the declaration module A(int id, int age) is illegal. However, comments may be used to note the parameter names to be used:

```
module A(int /*id*/, int /*age*/);
```

2.3.2 Types

All user-defined types (such as string above) must be defined before being used in a module declaration. In addition, each type must be a single identifier; compound types such as char* or unsigned int are not allowed. To use these types, include a typedef statement to define a single name:

```
typedef char* string;
typedef unsigned int uint;
```

3 Productions

Productions define the structure of the L-system string over time by specifying the fate of modules with each derivation step. A production has two parts: the *predecessor* defines the module(s) to be changed, as well as the context they must be found in for the production to apply; and the *production body* defines how the predecessor will be changed in the next derivation step if the production is applied. The syntax of a production is:

```
predecessor: { production body }
```

3.1 The predecessor

3.1.1 The strict predecessor

The predecessor of a production contains, at a minimum, the *strict predecessor*. This is the module or sequence of modules which, if the production is applied, will be replaced by new modules in the next derivation step. Examples of valid productions containing only a strict predecessor include:

```
F(x): { ... }
A(age, length) B(): { ... }
```

All module parameters in the predecessor must be listed and given unique names, even if they are not used in the production body. In addition, a module with no parameters must be followed by parentheses ().

3.1.2 Left and right context

In addition to the strict predecessor, a production may also list a context to its left or right, or both. These contexts must also be matched within the string for the production to be applied, although only the strict predecessor will be replaced. The syntax is:

left context < strict predecessor > right context:

For example, the production

```
F(x) > G(y): \{ F(x+1) \}
```

will replace F(x) with F(x+1) in the next derivation step only if G(y) is to the right of F(x) in the string. G(y) is not replaced by this production: it remains in the string unless it is replaced by another production in which it is the strict predecessor.

3.1.3 Left and right new context

In each derivation step, the right and left context constructs above are matched to modules in the current (or "old") string, in order to produce the next (or "new") string. Since matching is done sequentially from one end of the string to another, it is also possible to match to the newly created modules in the new string. Normally, the string is matched from left to right ("forward") which enables matching to the left new context using the << operator. For example:

```
B() << D(): { ... }
```

will replace D() in the next derivation step only if B() is the last module to be added to the new string so far.



See object: NewContext

The direction of the derivation can be controlled with the Backward() and Forward() statements (Section 6.1.2), usually called within a control statement (see Section 4.1). When the string is matched from right to left ("backward"), the right new context can be used with the operator >>. For example:

```
Start: { Backward(); }
E() >> F(): { ... }
```

Note that a production with a new context will never match if the derivation is going in the wrong direction: a new right context will not match if the direction is left to right ("forward"), and a new left context will not match if the direction is right to left ("backward").

Old' and new contexts can be combined in a single predecessor. For example, a production with the predecessor:

```
Age(age,length) << B() > B(): { ... }
```

will match the module B() in the current string if the derivation is proceeding in the forward direction, the last module in the new string is Age(age,length), and the current string has another B() to the right of the strict predecessor.

3.1.4 Ring L-systems

A ring L-system provides an alternate topology for context matching in the L-system string. Matching is performed as if the last module in the string and the first module in the string are adjacent, so that the string forms a ring.

For example:

```
Axiom: A B C;
C() < A() : { ... }
```

would match the A module in the axiom, because its left context is the C module at the end of the string.

To specify a ring L-system, include a statement before the Axiom:

```
{\tt ring} \ {\tt L-system} \colon value
```

where value is a non-zero number, or an expression returning a non-zero number.

3.2 Production body

If a production predecessor is matched successfully, lpfg executes the production body. This block may contain any valid C++ statement. The names given to module parameters in the predecessor act similar to function parameters in a C++ function.



See object: B-spline

3.2.1 The produce statement

The produce statement ends execution of the production body (like a return statement in a C++ function) and tells lpfg what the successor is. Its syntax is:

```
produce successor;
```

where successor is a sequence of modules. For example:

```
produce A(newAge,newLength);
produce B() A(x,length*12) B();
```

As with the axiom, there are no commas between modules and, if a module has no parameters, the parentheses may be omitted.

When the produce statement is reached, the successor is added to the new string and the production ends. However, a production may also end without reaching a produce statement: by reaching the end of the production block or by a return statement. In that case, the production is considered not applied, and lpfg will continue to look for a production that does apply to the predecessor. For example, the production:

```
A(age,length):
{
  if (age < 10)
     produce A(age+1,length+dl);
}</pre>
```

will only be applied if the first parameter of module A is less than 10. Otherwise lpfg will continue to look for a production that matches A(age,length). For instance, there may be another production such as:

```
A(age,length):
{
  if (age >=10)
     produce B(length);
}
```

A produce statement may be found anywhere in the production body where a C++ statement is valid, and there may be multiple produce statements, similar to C++ return statements. For example the two productions above could be written as:

```
A(age,length):
{
  if (age < 10)
     produce A(age+1,length+dl);
  else
     produce B(length);
}</pre>
```

A produce statement may also be issued without a successor:

```
produce;
```

In this case the strict predecessor is removed from the string and not replaced.

Note the difference between ending a production with an empty produce statement which removes the predecessor from the string, and ending with a return statement (or reaching the end of the production body without applying a produce statement), in which case *lpfg* continues to look for another production to match the predecessor.

3.2.2 The nproduce statement

It is sometimes useful to build a production's successor incrementally. The nproduce statement specifies part of a successor, but, critically, does not end the production. It syntax is like that of the produce statement:

```
nproduce module(s);
```

The nproduce statement adds the listed modules to the currently defined successor, but does not end execution of the production. A subsequence produce statement will add its own argument to the successor, then add the entire successor to the string. For example:

```
A(age,length):
{
  for (int i=0; i<age; i++)
          nproduce B;
  produce C(length);
}</pre>
```

will replace A(age,length) with a number of B modules equivalent to the value of the age parameter with a final C(length) module. If the predecessor is A(3,1), it will be replaced with:

```
B B B C(1)
```

If the production body ends without a **produce** statement, the production is not applied, and the partial successor is ignored.

3.3 Testing context within a production body

The context of the strict predecessor can also be tested within the production body, using one of the four InContext expressions:

```
InLeftContext ( module list )
InRightContext ( module list )
InNewLeftContext ( module list )
InNewRightContext ( module list )
```

The expressions are of type bool and are true if the context matches and false otherwise. For example, rather than defining the context in the predecessor of the production with:

```
F(x) < G(length) > H(y): { ... }
```

the context can be tested within the production body as follows:

This applies to InNewContext expressions as well where

```
F(x) << G(length): { ... }
```

is equivalent to:

Note the following:



See object: InNewContext

- Modules within the InContext constructs are not separated by commas (these are not function calls). They are listed in the same manner as in the predecessor.
- The order in which modules are listed should be the same as in the predecessor.
- Module parameters must be declared beforehand and their types must match the module's declaration. This is different from checking context in the predecessor where the parameters are declared implicitly.
- All the rules of context matching are the same as when matching context in a production's predecessor.

It is possible to combine InContext constructs with a context-sensitive predecessor. The InContext expression will begin matching with the module preceding the left context (InLeftContext) or following the right context (InRightContext) in the production. For example, the production

```
F(x) < G(length) > H(y): {
    float x;
    if InLeftContext(F(x))
        produce(G(x));
    else
        produce(G(length+1));
}
```

will match module G(3) in the string E(1) F(2) G(3) H(4). However, the InLeftContext expression will then try to match the E(1) module. Since it does not find the F(x) module, the else clause will apply and G(3) will be replaced with G(4).

Multiple InContext expressions that evaluate as true will continue to match modules further left (InLeftContext) or right (InRightContext). Consider the following example:

The intention of this code is to consider two cases that have the same left context but different right contexts. However, if the first InRightContext expression returns false after evaluating the first InLeftContext expression, the second InLeftContext expression (after the | | operator) will try to match the module to the left of the one matched by the first InLeftContext. To avoid this issue the production should be rewritten as:

Note that the two InRightContext expressions will be attempting to match the same module since only one of them will evaluate as true.

In general InContext expressions should be treated as operations that read from a stream: as each expression evaluates as true, the next module in the stream will be available for matching.

For details regarding context matching in branching structures see Section 9.

4 Control Statements

4.1 Start and End Statements

There are four statements used to specify C++ statements to be executed outside of productions at specific points during the L-system execution process:

- Start called before the first derivation step (i.e. before the output string is set to the axiom)
- StartEach called before each derivation step
- EndEach called after each derivation step
- End called after the final derivation step

Each of these statements has the syntax:

```
statement\ name: \{ C++\ statements \};
```

For example, to maintain a global variable steps equal to the current derivation step, the following statements can be used:

```
int steps;
Start: { steps = 0; }
EndEach:{ steps++; }
```

Note that the End statement is called after the final derivation step. Therefore, in Animate mode, if the animation is stopped or rewound before it reaches the final derivation step, the End statement is not called. If the End statement runs a vital command (for instance, to close an output file), ensure that the animation is run to the final frame.

4.2 Ignore and Consider Statements

By default, all modules are considered when matching contexts (more or less - see Section 9 for exceptions that may occur when modeling branching structures). It is often convenient, however, to consider only certain module types. There are two statements that can be used for this purpose:

```
ignore: module list;
or
consider: module list;
```

where *module list* is a sequence of module names separated by spaces. Use the **ignore** statement to list the modules that should be ignored when matching context, or the **consider** statement to list the only modules to be considered when matching context. For example, the code:

```
ignore: A B;
C(1) < D(2) > E(3): { ... }
```

would be matched to the string: C(1) A(10) D(2) B(5) E(3), since the A and B modules are ignored. The same effect can be achieved with a consider statement:

```
consider: C D E;
C(1) < D(2) > E(3): { ... }
```

In this case the same string would find a match because only the C, D and E modules are considered when matching.

Multiple ignore and consider statements are allowed within an L-system. Each statement applies to the subsequent productions until another ignore or consider statement is encountered. To cancel the effect of the last statement, use the empty ignore statement:

```
ignore: ;
```

The predefined modules SB and EB (Section 5.4) are always considered. Listing them in an ignore or consider statement has not effect.

4.3 Decomposition and Interpretation Rules

While productions are rules which define how the model advances over time, decomposition rules divide modules into simpler components, and interpretation rules specify how modules should be displayed.

4.3.1 Decomposition Rules

In complex L-systems, productions can be used to define modules at a higher level of abstraction with more details specified in decomposition rules. This provides a clear overview of the algorithm in the productions, with details to follow. Decomposition rules are applied to the L-system string in a decomposition step after the axiom and after each derivation step. The format is:

```
\begin{array}{c} \texttt{decomposition:} \\ predecessor : \left\{ \begin{array}{c} successor \\ \end{array} \right\} \\ predecessor : \left\{ \begin{array}{c} successor \\ \end{array} \right\} \end{array}
```

where each rule (predecessor/successor) has the same syntax as a production rule.

When the decomposition statement is present in an L-system it indicates that all the following rules are decomposition rules, until the end of the source file, or until a production or interpretation statement is encountered.

For example, a decomposition rule may replace a module by its constituent parts:

```
M(t) : {
    produce I(t)
        SB() Right(45) A(t) EB()
        SB() Left(45) A(t) EB()
        I(t);
}
```

The module M(t) is replaced in the L-system string by all the modules in the produce statement. This successor will then be used in the interpretation step, and in the next derivation.

Decomposition rules can be recursive: the module in the strict predecessor can appear in the successor. However, the default maximum decomposition depth is 1. Therefore, to actually recursively use a decomposition rule, a maximum depth statement must be used. It has the syntax:

```
maximum depth: n
```

where n is (truncated to) an integer. Decomposition is performed as long as the string does not contain any modules that can be further decomposed, or until maximum depth is reached. Only one instance of a maximum depth statement is allowed in an L-system. It is applied to all decomposition rules.

An example of a recursive decomposition rule is as follows:

```
decomposition:
maximum depth: 6;
   A(age):
   {
    if (age > 0)
        produce F(1) A(age-1);
}
```

This rule will produce a series of F(1) modules equal to age, to a maximum of 6, ending with module A.

4.3.2 Interpretation rules

Interpretation rules are executed only during the graphical interpretation of the string. Modules produced by interpretation rules are not inserted into the string for the next derivation step; they are only used as commands to the turtle when creating the visualization. This provides a useful separation between the functional aspects of a model and its graphical interpretation.

An interpretation step is performed in the following cases:

- When drawing the model in a window.
- When generating an output file (e.g. a rayshade file).
- When calculating the (axes-aligned) bounding box of the model.
- After the axiom and each derivation step, if any of the production predecessors contain query or communication modules (see Section 5.12).

Syntactically, interpretation rules have the same format as decomposition rules, including a maximum depth statement for recursive rules:

```
interpretation:
maximum depth: expression;
    predecessor : { successor }
    predecessor : { successor }
```

Generally, interpretation rules are replacing conceptual modules with predefined modules for turtle interpretation (see Section 5). For example:

```
interpretation:
   A(age,length): { produce Sphere(age); }
```

interprets each module A(age,length) in the string as a sphere of radius age.

4.3.3 Rule blocks

Generally, an L-system is written as an axiom followed by a block of productions, then decomposition rules, and finally interpretation rules:

```
axiom: module list;
predecessor : { successor }
predecessor : { successor }
...
decomposition:
...
interpretation:
...
```

However, in some cases it may be convenient to change this order, which will require a production statement to return to regular productions after rules of a different type have been listed.

For example, in the following code the L-system is organized into a block of rules pertinent to module A(), and then another block of rules pertinent to module X(), using a production statement to end the first set of interpretation rules.

```
A() : { ... B() ... }
decomposition:
B() : { ... C() D() ... }
interpretation:
C() : { ... }
D() : { ... }

production:
X() : { ... Y() ... }
decomposition:
Y() : { ... Z() ... }
interpretation:
Z() : { ... }
```

4.4 Production groups

In some models it is convenient to organize rule blocks into groups, such that only one specific group is considered in a given derivation step. By default, all productions, decompositions, and interpretation rules belong to the default group, numbered 0. The default group has a special property: if no production in the current group can be applied to a symbol, the productions in the default group will be tried, even if it is not the current group.

To specify an additional group, use the group statement:

```
group id:
```

where the group identifier, *id*, is an integer constant (not an expression or enumerated value) with a value greater than zero. A group ends with another group statement, or with an endgroup statement.

When lpfg is started, the default (group 0) rules are applied. To select another group for the subsequent derivation step, use the function:

```
UseGroup(id);
```

where *id* evaluates to an integer. It can be called at any time, but only takes effect at the beginning of the next derivation step. Consequently, it is often called in a **Start Each** statement. For example, productions can alternate between two groups using the following statements:



See object: B-spline

```
Start: {n=0;}
StartEach: { UseGroup(((n++ % 2) == 0) ? 1 : 2) }
group 1:
...
group 2:
...
interpretation:
group 0:
...
```

In this case, the value of the UseGroup parameter is defined by a conditional statement: if the remainder when n++ is divided by 2 is zero, then the group is 1, otherwise it is 2. Note that the interpretation block returns to group 0; therefore, the productions in this block will be used in each step.

There are also two specialized groups that are explained in greater detail later: Gillespie groups, ggroup (Section 7.2), and view groups, vgroup (Section 7.3).

5 Predefined modules

The following modules are predefined. The same names cannot be used for user-defined modules or global variables of any type. (The modules f and g cause name collisions particularly frequently.). See Section 6.3.1 for a description of the predefined vector data types, V2f, V2d, V3f, and V3d.

5.1 Position and drawing

Module	Description	Equiv. in $cpfg$
F(float d) G(float d)	Move forward a step of length d and draw a line segment from the original position to the new position. For F only: If the polygon flag is on (see Section 5.6), the final position is recorded as a vertex of the current polygon.	F(d) G(d)
<pre>f(float d) g(float d)</pre>	Move forward a step of length d. No line is drawn. For f only: If the polygon flag is on (see Section 5.6), the final position is recorded as a vertex of the current polygon.	f(d) g(d)
MoveTo(float x, float y, float z) MoveTo3f(V3f p)	Move the turtle to point (x,y,z) Move the turtle to point p.	@M(x,y,z)
MoveTo3d(V3d p) MoveTo2f(V2f p) MoveTo2d(V2d p)	, <u>,</u>	
MoveRel3f(V3f p) MoveRel3d(V3d p) MoveRel2f(V2f p) MoveRel2d(V2d p)	Move the turtle to the turtle's current position $+$ p. The heading, left and up vectors are not changed.	
LineTo(float x, float y, float z)	Draw a line from the turtle's current position to point (x,y,z) .	
LineTo3f(V3f p) LineTo3d(V3d p) LineTo2f(V2f p) LineTo2d(V2d p)	Draw a line from the turtle's current position to point p. The turtle will be positioned at point p.	
LineRel3f(V3f p) LineRel3d(V3d p) LineRel2f(V2f p) LineRel2d(V2d p)	Draw a line from the turtle's current position to its current position + p. The turtle will be positioned at point p.	
Line3f(V3f p1, V3f p2) Line3d(V3d p1, V3d p2) Line2f(V2f p1, V2f p2) Line2d(V2d p1, V2d p2)	Draw a line from point p1 to point p2. The turtle will be positioned at point p2.	
SetCoordinateSystem (float s)	Set the coordinate system affecting the above modules, using the turtle's current position and orientation and the global scaling factor s. The modules will be applied with respect to the modified coordinate system.	@D(s)

The turtle's heading, left and up vectors are not changed by these modules. If the distance between the two points is less than ϵ (a constant = 10^{-5}), these modules are ignored.

5.2 Turtle rotations

In the following modules, parameter a is an angle expressed in degrees.

Module	Description	$\begin{array}{c} \text{Equiv.} \\ \text{in} \\ \textit{cpfg} \end{array}$
Left(float a)	Turn left around the U axis by angle a	+(a)
Right(float a)	Turn right around the U axis by angle a	-(a)
Up(float a)	Pitch up around the ${\bf L}$ axis by angle ${\bf a}$	^(a)
Down(float a)	Pitch down around the ${\bf L}$ axis by angle ${\bf a}$	&(a)
RollL(float a)	Roll left around the ${\bf H}$ axis by angle ${\bf a}$	\(a)
RollR(float a)	Roll right around the H axis by angle a	/(a)
RollToVert()	Roll around the H axis so that H and U lie on a common vertical plane, with U closer to up than down.	@v
RotateXYZ	Rotate by angle around axis in global XYZ coordinates. The	
(V3f axis,	axis will be normalized. If its length is less than ϵ , no rotation	
float angle)	will occur.	
RotateHLU	Rotate by angle around axis in local turtle (HLU) coordi-	
(V3f axis,	nates. The axis will be normalized. If its length is less than	
float angle)	ϵ , no rotation will occur.	
SetHead	Set the heading vector of the turtle to hx, hy, hz, the up vector	@R(hx,
(float hx,	to ux,uy,uz, and the left vector to the cross product of the	hy,hz,
float hy, float hz,	new H and U . Normalized vectors do not need to be specified.	ux,uy,
float ux, float uy,	The module is ignored if any of the three settings is less than	uz)
float uz)	€.	
SetHead3f(V3f h)	Set the heading vector of the turtle to vector h. The turtle frame is rotated by the smallest rotation necessary to align the old and new heading vectors (i.e. parallel transport transformation).	

NOTE: There was a bug in the previous implementation of Up, Down, RollL and RollR, which caused the turtle to rotate in the opposite direction in some cases. This has been fixed; however, in order to keep compatibility with existing models, the view file command corrected rotation can be used to switch between the original and corrected behaviour (see Section 8.1.3).

5.3 Display parameters

Module	Description	Equiv. in $cpfg$
<pre>IncColor()</pre>	Increase the current colour index or material index by one.	;
DecColor()	Decrease the current colour index or material index by one.	,
SetColor(int n)	Set the current colour index or material index to n . If $n < 1$ or $>$;(n)
	255, the module is ignored.	,(n)
SetWidth(float v)	Set the line width to v. In pixel mode, the result is undefined if v	#(n)
	< 0 , and in other modes if $v \le 0$.	!(n)

5.4 Branching structures

Module	Description	Equiv.
		in
		cpfg
SB()	Start new branch by pushing the current state onto the turtle stack.	[
EB()	End branch by popping the state from the turtle stack.]
Cut()	Cut the remainder of the current branch, if the derivation direction is Forward	%
	(left to right). This module and all following modules are ignored up to the	
	closest unmatched EB module, or the end of the string if no EB module is found.	
	This module has no effect if the derivation direction is Backward.	

5.5 CIRCLES AND SPHERES

Module	Description	$\begin{array}{c} \text{Equiv.} \\ \text{in} \\ cpfq \end{array}$
CircleO()	Draw a circle, with diameter equal to the current line width, in the HL plane.	@ o
CircleFrontO()	Draw a circle, with diameter equal to the current line width, in the screen plane.	
Circle(float r)	Draw a circle of radius \mathbf{r} in the HL plane, centred at the current turtle position.	@o(d) where d is the diameter, not the radius.
CircleFront (float r)	Draw a circle, with radius r, in the screen plane.	
CircleB(float r)	Draw a circle outline in the HL plane, with inner radius = r - width/2 and outer radius = r + width/2, where width is the current line width.	@bc(r)
CircleFrontB (float r)	Draw a circle outline in the front plane, with inner radius $= r - width/2$ and outer radius $= r + width/2$, where width is the current line width. Note that it is always drawn in the front plane even when the object is rotated. This is different from $cpfg$ where it would keep its orientation in relationship to other elements in the scene.	@bo(r)
Sphere0()	Draw a sphere, with diameter equal to the current line width.	@0
Sphere(float r)	Draw a sphere of radius ${\tt r}$ at the current turtle position.	©O(d) where d is the diameter, not the radius.

The number of sides in the circle approximation is controlled by the ContourSides module (Section 5.8), or the contour sides command in the view file (Section 8.1.3). For spheres, there will be contour sides longitudinal sections and (contour sides+1)/2 transversal sections.

5.6 Polygons, rhombi, and isosceles triangles

Module	Description	Equiv.
		in
		cpfg
SP()	Start a polygon.	{
EP()	End a polygon.	}
PP()	Set a polygon vertex.	•
Rhombus(float length,	Draw a rhombus in the HL plane. The turtle is at the center	
float width)	of the bottom edge.	
Triangle(float width,	Draw an isosceles triangle in the HL plane. The turtle is at	
float height)	the center of the bottom edge.	

5.7 Surfaces and Meshes

Predefined surfaces and meshes are specified in the view file (Section 8.1.5), where the first surface in the file has id=0.

Module	Description	$\begin{array}{c} \text{Equiv.} \\ \text{in} \\ \textit{cpfg} \end{array}$
Surface(int id, float scale)	Draw the predefined Bézier surface id at the current location and orientation. The surface will be uniformly scaled by the factor scale.	~
Surface3(int id, float xscale, float yscale, float zscale)	Draw the predefined Bézier surface id at the current location and orientation. The surface will be scaled independently along the x , y and z axes by xscale, yscale, and zscale, respectively.	
Mesh(int id, float scale)	Draw the predefined mesh at the current location and orientation. The mesh will be uniformly scaled by the factor scale.	
Mesh3(int id, float xscale, float yscale, float zscale)	Draw the predefined mesh at the current location and orientation. The mesh will be scaled independently along the x , y and z axes by xscale, yscale, and zscale, respectively.	
SetUPrecision (float p)	Set the drawing precision of bicubic surfaces to p in the U direction. If set to zero, the U precision is reset to the surface default, defined in the view file.	
SetVPrecision (float p)	Set the drawing precision of bicubic surfaces to p in the V direction. If set to zero, the V precision is reset to the surface default, defined in the view file.	
<pre>InitSurface(int id)</pre>	Initialize an L-system-define surface. Currently there is only one surface allowed, so the parameter is ignored.	@PS
SurfacePoint (int id, int p, int q)	Set the (p,q) control point of the L-system-defined surface to the current turtle position. The id parameter is ignored.	@PC
DrawSurface(int id)	Draw the L-system-defined surface. The id parameter is ignored.	@PD
DSurface (SurfaceObj s)	Draw the dynamic Bézier surface s. See Section 7.1.	

5.8 Generalized cylinders

Generalized cylinders are specified as contours, which can be defined using the *cuspy* tool (see the *vlab* Tools manual), and listed on the command line (Section 1.1.2). Contours are referenced sequentially by an id in the order in which they are listed, starting with 1.

Module	Description	Equiv.
		$rac{{ m in}}{cpfg}$
StartGC()	Start a generalized cylinder at the current turtle position.	@Gs
PointGC()	Specify a control point on the central line of the generalized	Similar to
	cylinder.	@Gc(n)
EndGC()	End the current generalized cylinder.	@Ge
CurrentContour	Set contour id as the current contour for generalized cylin-	@#(id)
(int id)	ders. If id=0, the default contour (a circle) is used.	
BlendedContour	Interpolate the contour between id1 and id2 using the	
(int id1, ind id2,	interpolating coefficient blend. At blend=0 the contour	
float blend)	is id1; at blend=1 the contour is id2.	
ScaleContour	Scale the contour independently by p (left) and q (up).	
(float p, float q)		
ContourSides	Specify the number of sides all subsequent generalized	
(int sides)	cylinders will have. This module should be placed before	
	the StartGC module; it has no effect within a generalized	
	cylinder (i.e. between StartGC and EndGC).	

5.9 Textures

Cylinders and surfaces can be texture mapped using an image file specified in the view file (Section 8.1). Textures are referenced sequentially by an id in the order in which they are listed in the view file, starting with 0.

Module	Description
CurrentTexture	Use texture txtid to texture map a surface or cylinder. If txtid = -1,
(int texid)	texture mapping is turned off.
TextureVCoeff	Scale the texture mapped on cylinders in the v direction (along the cylinder
(float vscale)	axis). vscale is the portion of the texture that will be mapped to the cylinder
	as the turtle moves forward one unit. For example, to map the texture to a
	cylinder that is 10 units long, set vscale to 0.1. If the texture v coordinate
	is greater than 1, the texture wraps. This module only affects the texturing
	of cylinders; surfaces are not affected.

5.10 Labels

Module	Description	Equiv. in $cpfg$
Label(char* str)	Print the string, str, at the current turtle position.	@L(str)

Note that if the Label module is drawn before other objects when render mode is set to shadows, the shadows will not be rendered. For example:

will break shadow mapping, but the following will not:

5.11 Tropism Control

Tropisms are defined in the view file (Section 8.1.4). They are assigned consecutive integer id numbers, starting with 1, in the order in which they appear in the file.

Module	Description	Equiv.
		in
		cpfg
SetElasticity	Set the elasticity parameter of tropism or torque id to v. This	@Ts
(int id, float v)	is equivalent to the E: parameter of the tropism and torque	
	commands in the view file.	
IncElasticity	Increment the elasticity parameter of tropism or torque id by	@Ti
(int id)	the value defined by the S: parameter of the tropism and	
	torque commands in the view file.	
DecElasticity	Decrement the elasticity parameter of tropism or torque id by	@Td
(int id)	the value defined by S: parameter of the tropism and torque	
	commands in the view file.	
Elasticity	Set the elasticity or a "simple" tropism (command stropism	_
(float v)	in the view file) to v.	(under-
		score)

5.12 Query modules

If any of the following query modules are present in the predecessor of any production in the L-system, an interpretation step is performed after each derivation step even if no drawing occurs. The turtle is "moved" and all positions are calculated in case they are needed by the query modules.

If there are multiple views (Section 7.3), the interpretation rules in vgroup 0 will be used.³

Module	Description	$\begin{array}{c} \text{Equiv.} \\ \text{in} \\ \textit{cpfg} \end{array}$
<pre>GetPos(float x,</pre>	Query the x, y, and z coordinates of the current turtle po-	P(x,y,z)
float y, float z)	sition.	
<pre>GetHead(float x,</pre>	Query the x, y, and z coordinates of the current turtle head-	?H(x,y,z)
float y, float z)	ing vector.	
<pre>GetLeft(float x,</pre>	Query the x, y, and z coordinates of the current turtle left	?L(x,y,z)
float y, float z)	vector.	
<pre>GetUp(float x,</pre>	Query the x, y, and z coordinates of the current turtle up	?U(x,y,z)
float y, float z)	vector.	

³Vgroup 0 is a special group, distinct from the vgroups defined using the window command in the view file (Section 8.1.1).

5.13 Environment communication

Module	Description	Equiv.
		$rac{\mathrm{in}}{cpfg}$
E1(float v)	Send or receive environmental information, using the individual parameters, v, or v1 and v2, or the	?E(v)
E2 (float v1, float v2)	array a.	
EA20(EA20Array a)		

See the vlab Environmental Programs manual for more details, including the definition of the EA20Array data type.

5.14 Dynamic view control

Module	Description
Camera()	Change the view parameters such that the camera is located at the position of the
	turtle, with the same orientation. See also the new view between frames: parameter
	in the animation file (Section 8.2).

5.15 Mouse interaction

The following two modules are used to interactively identify a component of the model using the mouse and a combination of key strokes. The module is inserted into the string before the object identified by the mouse. If no object is identified (i.e. the mouse is clicked outside of the model components), no module is inserted.

Module	Description	$\begin{array}{c} \text{Equiv.} \\ \text{in} \\ \textit{cpfg} \end{array}$
MouseIns()	Inserted into the string when the user holds down the Shift and Command keys (or the 1 key) and clicks the left mouse button on a component of the model.	x
MouseInsPos (MouseStatus)	Inserted into the string when the user holds down the Alt and Command keys (or the 2 key) and clicks the left mouse button on a component of the model. A MouseStatus structure is included with the insertion of this module.	

See Section 7.4 for more details, including the definition of the MouseStatus data type.

6 Predefined functions

6.1 Controlling the simulation

6.1.1 Simulation progress

Function	Description
StepNo()	Return the current derivation step number.
void RunSimulation()	Run the simulation. Including this function in the Start block (Section 4.1) will start the animation as soon as $lpfg$ is called, without selecting the Run menu item (Section 1.2.3) or using the keyboard shortcut to start.
<pre>void PauseSimulation()</pre>	Pause the simulation after completing the current derivation step. The simulation can be resumed using the Step, Run or Forever menu options (Section 1.2.3). The End statement block (Section 4.1) is not executed.
<pre>void Stop()</pre>	Stop the simulation. The End statement block (Section 4.1) is executed after the current derivation step. The animation can be rewound, but cannot be advanced further using the Animate menu items (Section 1.2.3) or the keyboard shortcuts.
void DisplayFrame()	Display a frame of the animation at the current derivation step, if the display on request parameter is set to on in the animation file (Section 8.2). If it is off, this function has no effect.
void OutputFrame("filename.ext")	Output a frame of the animation at the end of the current derivation step, as an image, postscript, or OBJ file, depending on ext. If display on request = on in the animation file (Section 8.2), this call must be preceded by a DisplayFrame() function so that the frame buffer is updated. If this function is called outside of Animate mode, it is ignored. The actual saving is done at the end of the derivation step: if Stop() is called in the same step, the frame will not be output.

6.1.2 L-system derivation

L-system derivation can be affected by groups (Section 4.4) and Gillespie groups (Section 7.2) using the following functions:

Function	Description
<pre>void UseGroup(int)</pre>	Use the group from the specified group or ggroup in the next derivation step.
<pre>int CurrentGroup()</pre>	Return the number of the current group.
<pre>void SeedGillespie(long seed)</pre>	Seed the pseudo-random number generator used by Gillespie groups (see Section 7.2).

Derivation direction, used with new context functionality (Section 3.1.3), is determined by the following functions:

Function	Description	
<pre>void Forward()</pre>	Perform the next derivation step from left to right. This is the default.	
<pre>void Backward()</pre>	Perform the next derivation step from right to left.	
<pre>bool IsForward()</pre>	Return the last derivation direction. Note that this function returns the value	
	of the last Forward or Backward statement but may not reflect the current	
	derivation direction if it is changed during a derivation step.	

6.1.3 Communication with the environment

Function	Description
<pre>void Environment()</pre>	Specify whether the "interpretation for environment" step should be
void NoEnvironment()	performed after the current derivation step. This affects whether environmental information will be available in the next derivation step.
	Interpretation for environment is performed after the EndEach block, so
	these functions can be used in the StartEach or EndEach blocks with
	the same effect.

See the *vlab* Environmental Programs manual for more information.

6.2 Accessing externally defined entities

Parameters, functions, contours and surfaces accessed using functions listed in this section can be manipulated without modifying, re-reading and recompiling the L-system file. This facilitates and accelerates exploration of the models, using the tools in the vlab Tools manual. To see the results of changes, rerun the L-system using the New run menu item (Section 1.2.2). To see the results immediately, set lpfg and the tool to continuous refresh mode (see Section 1.3).

6.2.1 Parameters

Parameters may be defined in a .vset file (Section 1.1.2) which can be modified using the panel tool. Each parameter is identified by a name (pname) which *lpfg* maps to an integer number (using a #define statement invisibile to the user).

The following function is used to retrieve the value of a parameter from the file:

Function	Description
<pre>float val(int pname)</pre>	Return the value of parameter pname from the parameter.vset file.

The parameter.vset file contains #define statements, one per line, in the format:

#define $pname \ n$

where pname is the parameter name, and n is its value. For example, if parameter.vset contains the lines:

#define LENGTH 10
#define ANGLE 60

the L-system can retrieve the values of these parameters with the statements:

```
len = val(LENGTH);
a = val(ANGLE);
```

Note that the return variable cannot have the same name as the parameter. The variable must be declared, but the parameter is not.

6.2.2 Graphically defined functions

Graphically defined functions can be input into *lpfg* using three types of input files: *function*.func, *functionset*.fset, and *timeline*.tset (see Section 1.1.2). Each function is identified by a name, fname, which is mapped to a sequential integer number (using a #define statement invisible to the user).

The functions can be accessed within the L-system using the following calls:

Function	Description
<pre>float func(int fname, float x)</pre>	Return the value of function fname, specified in a .func
	or .fset file. The parameter x is clamped to the interval
	[0,1].
<pre>float pfunc(int fname,</pre>	Return the value of function fname, specified in a .func
<pre>float x, float min, float max)</pre>	or .fset file. The function is evaluated over the interval
	[min,max]. The parameter x is clamped to that interval.
<pre>float tfunc(int id, float x)</pre>	Return the value of function fname, specified in a .tset
	file. The function is evaluated over the interval specified
	in the file. The parameter x is clamped to that interval.
V2f funcTangent (int id, float x)	Return the tangent to function fname, specified in a
	.func or .fset file. The parameter x is clamped to
	the interval $[0,1]$.

6.2.3 Graphically defined curves

Similar to cpfg, lpfg supports B-spline curves, defined via their control points. Planar curves can be defined using the cuspy tool. See the vlab Tools manual for the file format, which can also be used to define 3-dimensional contours. Contour files are listed on the command line (Section 1.1.2). Each contour is assigned an id in the order in which it was listed, starting at 1.

See Section 5.8 for the use of contours to create generalized cylinders.

Function	Description
<pre>float curveX(int id, float s)</pre>	Return the coordinates of curve id defined in the con-
<pre>float curveY(int id, float s)</pre>	tour file. Parameter s is the normalized arc-length
<pre>float curveZ(int id, float s)</pre>	positin clamped to the interval [0,1]. The curveXY and curveXYZ functions return a structure type internal to
curveXY(int id, float s)	lpfg and may require explicit casting to V3f or V3d within
<pre>V2f curveXYf(int id, float s)</pre>	the L-system code.
V2d curveXYd(int id, float s)	
curveXYZ(int id, float s)	
V3f curveXYZf(int id, float s)	
V3d curveXYZd(int id, float s)	
V3f curveNormal(int id, float s)	Return the normal vector to the curve id at position t.
void curveScale (int id,	Scales curve id by the factors x , y , and z .
float x, float y, float z)	

Function	Description
<pre>void curveSetPoint(int id, int p,</pre>	Assign control point p in curve id to position
float x, float y, float z)	(x,y,z). The curve must be recalculated using curveRecalculate in order for the curve functions to return proper values.
<pre>void curveRecalculate(int id)</pre>	Recalculate curve id after assigning a control point with curveSetPoint.
<pre>void curveReset(int id)</pre>	Reset curve id to the state define in the contour file. The file is not re-read.

6.2.4 Graphically defined surfaces

Predefined surfaces can be created using either the *bezieredit* or *stedit* tool and are listed in the view file (Section 8.1.5). Surfaces are assigned an id in the order in which they were listed, starting at 1.

Function	Description
SurfaceObj GetSurface(int id)	Return the control points of the predefined Bézier surface specified in the view file as id. If the surface contains more
	than one patch, only the first patch is returned. Used to
	dynamically manipulate a surface (see Section 7.1).

6.3 Auxiliary math functions

6.3.1 Vector algebra

Vector functions are used with a set of pre-defined structures:

```
struct V2f { float x,y; };
struct V2d { double x,y; };
struct V3f { float x,y,z; };
struct V3d { double x,y,z; };
```

Most functionality associated with vectors are actually methods:

Method	Description
Length()	Return the vector's length as float or double, depending on the structure.
Normalize()	Normalize the vector.
Normalized()	Return a normalized form of the vector. The argument vector is not affected.
Set(x,y)	Set the components of a vector.
Set(x,y,z)	

Examples of these methods are:

However, there are also Normalize functions:

Function	Description
V2d Normalize(V2d v)	Normalize vector v, and return a copy of this vector.
V2f Normalize(V2f v)	
V3d Normalize(V3d v)	
V3f Normalize(V3f v)	

And, unless the preprocessor symbol NOAUTOOVERLOAD is specified before #include lpfgall.h, more operators are defined on vectors, including the addition and subtraction of two vectors of the same type, unary change of sign (direction), multiplication and division of a vector by a scalar, dot product, and the assignment operators +=, -=, *=, and /=. Moreover, the cross product is defined on V3f and V3d with operator %. Some usage examples are:

```
V2f a(1.5, 2,0), b(0, 0.5);

V2f c = a * 2.5 + b;

float x = a * b;

V3f d(1.2, 2.3, 0), e(0, 0,5, 0,1);

V3f f = d % e;
```

6.3.2 Random number generation

The random number functions, ran and sran, provide convenient access to simple random number generation, based on Unix drand48().

Function	Description
float ran(float range)	Generate a peseudo-random number uniformly distributed over [0, range].
<pre>void sran(long seed)</pre>	Seed the pseudo-random number generator used by ran. Use this function in the Start block to ensure every run is identical, even after rewinding.

6.4 View-related functions

Views are identified by name in the view file (Section 8.1.1), which *lpfg* maps to sequential integer numbers internally (using #define statements invisible to the user). Therefore, the following functions have an integer parameter which can be specified using the view name. See Section 7.3 for more information on multi-view mode, and the use of vname.

Function	Description
void UseView(int vname)	Activate the view, vname, specified in a window command in the view file.
<pre>float vvXmin(int vname)</pre>	Return the coordinate of the bounding box of view
<pre>float vvYmin(int vname)</pre>	vname.
<pre>float vvZmin(int vname)</pre>	
<pre>float vvXmax(int vname)</pre>	
<pre>float vvYmax(int vname)</pre>	
<pre>float vvZmax(int vname)</pre>	
float vvScale(int vname)	Return the current projection scaling factor of view
	vname.
CameraPosition GetCameraPosition(0)	Get the current position of the camera.

 ${\tt CameraPosition} \ is \ a \ predefined \ data \ type:$

```
struct CameraPosition {
   V3f position, lookat;
   V3f head, left, up;
   float scale;
};
```

6.5 Mouse and menu functions

Function	Description
struct MouseStatus	Return the state of the mouse. See Section 7.4 for examples of its
<pre>GetMouseStatus()</pre>	usage.
<pre>void UserMenuItem (char* label, int id)</pre>	Add a menu item, label, to a user-defined menu, with a numerical id to be returned when the item is selected. The menu is accessed by holding down the '4' key and clicking the left mouse button over
	the $lpfg$ window.
int UserMenuChoice()	Return the id defined by UserMenuItem() associated with the last selection made from the user-defined menu since the previous call to this function.
void UserMenuClear()	Clear the user-defined menu.

See Sections 7.4 and 7.5 for examples of mouse interactions and user-defined menus, respectively..

6.6 Input and output functions

Function	Description
<pre>void Printf(const char*,)</pre>	Print message to the lpfg.log file, and to the console if it
	is open. Recommended over the standard C function <i>printf</i>
	when $lpfg$ is not called from and connected to a console.
void OutputString	Write the current string to the specified file in binary format
(const char* filename)	(.strb), similar to the String > Output menu item. This
	function should be called in a control block, not within a
	production.
void LoadString	Overwrite the current string with the string in the specified
(const char* filename)	binary file (.strb), similar to the String > Input menu item.
	Normally this is a string created by the OutputString func-
	tion, or the String > Output menu item. This function should
	be called in a control block, not within a production.

7.1 Dynamic surfaces

Single-patch Bézier surfaces can be dynamically created and/or manipulated from within the L-system. This is useful, for example, when creating an animation with "keyframe" surfaces, or when building a family of similar surfaces that are modifications of a predefined set of base surfaces.

The manipulations that can be performed on a surface include:

- non-uniform scaling,
- linear interpolation between surfaces, and
- manipulation of individual control points,

7.1.1 Creating dynamic surfaces

A dynamic surface can be initialized for further manipulation by:

- Using the GetSurface function (Section 6.2.3) to get the control point coordinates of a predefined surface specified in the view file (Section 8.1)
- Initializing the coordinates of individual control points within the L-system

To explicitly initialize the coordinates of a control point use one of the Set methods:

```
void SurfaceObj::Set(int id, const float* arr)
void SurfaceObj::Set(int id, const V3f& v)
```

See Section 6.3.1 for a description of the predefined vector data type, V3f.

A similar method is available to get the coordinates of a control point:

```
V3f SurfaceObj::Get(int id) const
```

7.1.2 Manipulating dynamic surfaces

Scalar multiplication operators can be used to scale a surface object by a real number:

```
const SurfaceObj SurfaceObj::operator*(float r)
SurfaceObj operator*(float r, const SurfaceObj& obj)
```

To scale the surface non-uniformly (by a different factor in each direction), make the scaling factors coordinates of a V3f vector and use the method:

```
void SurfaceObj::Scale(const V3f& scale)
```

The addition operator combines two surfaces by pointwise adding their control points:

```
SurfaceObj operator+(const SurfaceObj& 1,const SurfaceObj& r)
```

The addition operator, along with the scalar multiplication operator, defines a vector space over patches. This can be used to interpolate between surfaces. Then use the predefined DSurface module (Section 5.7) to draw the resulting surface. For example:

```
interpretation:
Leaf(age):
{
    SurfaceObj young = GetSurface(L_YOUNG);
    SurfaceObj mature = GetSurface(L_MATURE);
    SurfaceObj leaf_surface = young*(1-age) + mature*age;
    produce DSurface(leaf_surface);
}
```

7.2 GILLESPIE GROUPS

Gillespie groups are a special type of production groups (Section 4.4), with a different derivation strategy. They are designed for modeling chemical reactions as stochastic processes. The specification of a Gillespie group begins with

```
ggroup number:
```

where *number* is an integer and part of a shared numbering system with regular production groups; therefore, a regular group and a Gillespie group cannot have the same number. Gillespie groups end with the standard endgroup statement, and are called using the standard UseGroup function.

Unlike a regular derivation step where every module in the string can produce a successor, a derivation step using a Gillespie group will have only *one* module in the entire string produce a successor, chosen using *Gillespie's method* [7; 8]. All other modules will remain the same.

Each module defined in a Gillespie group specifies the reactions that may occur within the module, and the propensity (likelihood) of each reaction. For example, if the Cell module implements reactions:

$$S+E \underset{c_1}{\rightarrow} ES, \quad ES \underset{c_2}{\rightarrow} S+E, \quad ES \underset{c_3}{\rightarrow} P+E$$

then the production for the Cell module in the Gillespie group will be:

```
Cell(S,E,ES,P):
{
   propensity c1*S*E produce Cell(S-1,E-1,ES+1, P);
   propensity c2*ES produce Cell(S+1,E+1,ES-1,P);
   propensity c3*ES produce Cell(S,E+1,ES-1,P+1);
}
```

In each derivation step, lpfg will randomly choose the next reaction to take place based on the propensities of all the modules in the Gillespie group such that the reaction with the greatest propensity is more likely to be chosen. For example, if there are ten Cell modules with the three reactions above, lpfg will pick one reaction out of 30. It will also calculate the time τ to the next reaction as $\tau = ln(1-\chi)/p$, where χ is a uniform random number in [0,1] and p is the sum of the propensities of all modules. To access τ , call the function:

```
float GillespieTime();
```

There are two restrictions when using Gillespie groups:

- ring L-system statements are ignored, and
- new context is not supported.

7.3 Multi-view mode

lpfg allows multiple views to be displayed simultaneously. The location of each view within the main window is defined in the view file (Section 8.1.1) using the window command. For example, to create three views, one at the top and two beneath it, the commands would be:

```
window: View1 0.0 0.0 1.0 0.5
window: View2 0.0 0.5 0.5 0.5
window: View3 0.5 0.5 0.5 0.5
```

where View1, View2, and View3 are mapped to integer numbers and used in UseView and vgroup statements, and the four numbers are:

- the x coordinate of the top left corner,
- the y coordinate of the top left corner,
- the width, relative to the main window, and
- the height, relative to the main window.

The default border between the views is a black line, one pixel wide. This can be altered with the window border command (Section 8.1.1). Note that the view area is reduced by the size of the border. This is especially noticeable if a wide border is used.



See object: Multiview

To display these views, they must be activated with the UseView function (Section 6.4). The function is normally called within the Start statement (Section 4.1). For example:

```
Start: {
    UseView(View1);
    UseView(View2);
    UseView(View3);
}
```

If a UseView function is added or changed within the L-system file, *lpfg* must be restarted or New model selected from the pop-up menu. (Selecting New L-system does not suffice.)

The actual content of each view is defined in the interpretation section of the L-system using the vgroup command. For example, View1 above would be defined as follows:

```
interpretation:
vgroup View1:
    ...
    produce ...;
```

7.4 Mouse interactions

The status of the mouse can be obtained using the GetMouseStatus() function, which returns a MouseStatus structure defined as:

```
V3d atFront,atRear,atMiddle;

// Intersection of the cursor ray with
// front plane, back plane, and halfway between them.
// Not affected by any keys.

bool lbDown;

// Left button currently down

bool lbPushed;

// Left button pressed
// since last call to GetMouseStatus

bool lbReleased;

// Left button released
// since last call to GetMouseStatus

};
```

The cursor ray is the line passing through the cursor location, perpendicular to the screen, mapped into world space.

The left button values, 1bDown and 1bPushed, are only set when the left button is pushed with a combination of keys. These key combinations are also used to determine which mouse module is inserted when the left mouse button identifies a component of the model:

Key combination	Alternate key	Module inserted
Shift+Command	1	MouseIns()
Shift+Alt+Command		
Alt+Command	2	MouseInsPos(MouseStatus)
Shift+Alt	3	No module inserted

Therefore, using any combination of the keys above, and the left mouse button, it is possible to draw a line:



See object: SimpleDraw

The following code draws a sphere when the left mouse button is pushed along with one of the key combinations for MouseIns(). Spheres can then be selected and moved.



See object: MoveBalls

```
derivation length: 1;
                     // generates new balls
module AddBall();
module Ball(V3d, int); // position, currencly selected?
MouseStatus ms;
int moving;
                      // Set to 1 after selecting a module
                      // and set to 0 after releasing the mouse button
Axiom: AddBall;
Start: { moving = 0; }
StartEach: { ms = GetMouseStatus(); }
/* Add sphere if mouse clicked outside any existing sphere. */
AddBall():
     if (!moving && ms.lbPushed) {
         moving = 1;
         produce Ball(ms.atMiddle, 1) AddBall();
/* An existing ball has been selected. Adjust its position to
  that of the mouse. Set flag "moving" to 1 to prevent the
   addition of another ball at the same location. */
MouseIns() Ball(pos, selected) :
    moving = 1;
    produce Ball(ms.atMiddle, 1);
/* Move the selected ball as long as the mouse button
   is not released. */
Ball(pos, selected):
     if (selected) {
         moving = !ms.lbReleased;
         produce Ball(ms.atMiddle, moving);
interpretation:
Ball(pos, selected) :
    produce MoveTo3d(pos) SetColor(1+selected) Sphere(1);
```

7.5 User-Defined Menus

In addition to the standard *lpfg* pop-up menu, a user-defined pop-up menu can be created and accessed by holding down the '4' key and using the left mouse button. The content of the menu is defined with multiple calls to UserMenuItem() functions, and each menu selection is identified using the UserMenuChoice() function.

Typically, the menu content is defined in the Start statement, and the menu item selected in the StartEach statement:



See object: UserMenu

```
int choice;

Start:
{
    UserMenuItem("First menu item",1);
    UserMenuItem("Second menu item",2);
    ...
}

StartEach:
{
    choice = UserMenuChoice();
}
```

8 Lpfg-specific input files

8.1 View file

Viewing and drawing parameters are stored in the view file, identified by its extension (filename.v)⁴. The view file is read by the C++ preprocessor; therefore, the use of comments (both C style /* ... */ and C++ style //), as well all other standard preprocessor directives such as #define and #if statements are allowed.

The commands in the file are interpreted in the order in which they appear in the file. If there are two or more commands that specify the same parameter, the last one takes precedence. This does not apply to commands that specify new set of parameters every time they appear (e.g. lights, tropisms). Every command must be contained on a single line.

8.1.1 Setting the view

Command	Description	Default	
projection: pvalue	Set the projection to parallel or perspective.	parallel	
scale: s	Set the size of the final image on the screen. For full		
scale factor: s	size, set $s = 1.0$. The two commands are equivalent.		
min zoom: zmin	Set the minimum value of the zooming factor.	0.05	
\max zoom: $zmax$	Set the maximum value of the zooming factor.	50	
generate on view change: $vchange$	Rerun the simulation. <i>Lpfg</i> rewinds to the axiom and performs the derivation again depending the value of <i>vchange</i> : on: rerun every time the view changes through rotation, zoom, or pan. triggered: rerun after the user releases the mouse button. off: never rerun.	off	
view: id dir: dx dy dz up: ux uy uz pan: px py pz fov: val shift: val scale: val	Define the view transformations to be used for view window <i>id</i> . In single view mode, set <i>id</i> to 0. All the transformation commands are optional. dir and up: the view direction and up direction. pan: the point that is the center of the view, relative to the center of the bounding box. fov: the angle of the field of view in the <i>y</i> direction. shift: the distance between the camera and the point being looked at. scale: the scale of objects. See Section 8.1.8 for a deprecated form of this command.	dir: 0 0 -1 up: 0 1 0 pan: 0 0 0 fov: 45 shift: 1 scale: 0.9	
box: id xmin xmax ymin	Define the default bounding box for view window id.		
ymax zmin zmax	In single view mode, set id to 0.		

 $^{^4}$ Some older models may use filename.dr

Command	Description	Default
window: vname left top width height	Define the location of view $vname$ within the $lpfg$ window. The parameters $left$, top , $right$ and $bottom$ are the relative position of the view within the main window, where $(0,0)$ is the upper left corner and $(1,1)$ is the bottom right. See Section 7.3 for a description of all components of multi-view mode.	
window border: $size$ $r g b$	Define the size and color of the border between multiple views, where $size$ is in pixels, and r , g , b are integers between 0 and 255. See Section 7.3 for a description of all components of multi-view.	size = 1 $r=g=b=0$
front distance: $d1$ back distance: $d2$	Set the distance to the front $(d1)$ and back $(d2)$ clipping planes, from the viewer in perspective projection, or from the position of the clipping plane with respect to the centre of the object's bounding box in parallel projection. Thus in parallel projection the front distance should be a negative number and the back distance should be positive. Both commands must be specified in order to have an effect.	See below

Default clipping planes are calculated on the basis of minimum and maximum distances to the bounding box in the view direction.

8.1.2 Rendering commands

Command	Description	Default
z buffer: on off	Turn Z buffer on and off.	off
render mode: rvalue	Set the rendering mode to filled, wireframe, shaded, or shadows. Note that when the render mode is shadows, the Z buffer is set to on regardless of the value of the z buffer command above.	filled
shadow map:	Define parameters for shadow mapping when the	n = 1024
$\mathtt{size} \colon n$	render mode command is set to shadows. ⁵ The	r = 0.2
color: r g b	shadow map will be generated using the first direc-	g = 0.2
offset: factor units	tional or spot light source specified with the light	b = 0.4
	parameter. The following parameters are optional:	factor = 5
	size: width and height of the shadow map $(n \times n)$,	units = 10
	where n must be an even number. Shadows may	
	not be displayed if values are too small $(n < 100)$	
	or too large (dependent on graphics card).	
	color: shadow color in rgb components.	
	offset: polygon offset for a generating depth	
	map used to reduce shadow acne (erroneous self-	
	shadowing). To reduce shadow acne, try increasing	
	these values.	

 $^{{}^5} For\ details\ see\ https://registry.khronos.org/OpenGL-Refpages/gl4/html/glPolygonOffset.xhtml.$

Command	Description	Default
light:	Define a light source. ⁶ Include either:	V: 0 0 1
V: x y z	V: vector of directional light source, or	(single light
0: x y z	O: origin of point light source, or	source in
P: x y z e c	both O and P where P: spotlight with direction	the default
A: r g b	(x,y,z), exponent e , and cutoff angle c .	view direction)
D: r g b	In addition, the following options may be specified:	
S: r g b	A: ambient color of light source.	A: 1 1 1
T: c l q	D: diffuse color of light source.	D: 1 1 1
	S: specular color of light source.	S: 1 1 1
	T: constant c , linear l , and quadratic q attenua-	T: 1 0 0
	tion factors (affecting point light sources and spot-	
	lights).	
	It is possible to define up to 8 light sources, one per	
	line.	
stationary lights:	Enable stationary light sources when on, keeping the	on
on off	position of all light sources fixed.	
concave polygons:	Enable the OpenGL tesselator when on, which di-	off
on off	vides polygons into triangles. This allows rendering	
	of concave polygons, but <i>lpfg</i> may run slower.	
auto normals: on off	Calculate normals to user-defined polygons generated	off
	with the SP/EP modules. When on, the normals are	
	calculated as the cross-product of the first and second	
	polygon edge. When off, the up vector of the turtle	
	is used as the normal to the polygon.	
antialiasing: n	Set the preferred number of samples per pixel in the	0 (no multi-
	anti-aliasing method. The parameter n is in the range	sampling)
	0 to 10. The final effect may depend on the hardware	
	used.	

8.1.3 Geometry presentation

Command	Description	Default
line style: $lstyle$	Set the line style to pixel, polygon or cylinder.	pixel
$ \begin{array}{c} \text{wireframe line width:} \\ width \end{array} $	Set the line width when the render mode command is set to wireframe. The value of <i>width</i> must be greater than zero.	
contour sides: n	Set the number of sides n of polygonal approximations of circles, cylinder cross-sections, and sphere sections rendered in the $lpfg$ window. This command can be overridden by either the ContourSides module (Section 5.8), or the samples parameter in the file created by the contour editor (see the $cuspy$ tool in the $vlab$ Tools manual). Values of $n < 3$ are clamped at 3.	16

⁶For details see https://www.glprogramming.com/red/chapter05.html.

Command	Description	Default
capped cylinders: on off	Cap generalized cylinders defined by a closed contour whenon, and generate a mesh consisting of one closed surface (a watertight mesh). If a concave contour is used to define the shape of the generalized cylinder, the command concave polygons: on should also be present. If an open contour is specified, this command should be set to off, otherwise an incorrect triangulation will be generated.	no
<pre>backface culling: on off</pre>	Specify that backward-facing polygons should not be drawn when on. This may speed up rendering or improve the rendering of transparent objects.	off
corrected rotation: on off	Use the corrected rotations when on. Old versions of <i>lpfg</i> had a bug which caused all rotations by the modules Up, Down, RollL, and RollR to be in the wrong direction. This was fixed, but in order to run old models without corrections, set corrected rotation to off.	on

8.1.4 Tropism commands

Command	Description	Default
tropism:	Set tropism parameters. The tropism vector (T) is required.	A: 0
T: x y z	The remaining parameters are optional:	I: 1
A: a	- A: angle (in degrees) that segments are trying to reach, with	E: 0
I: x	respect to the tropism vector	S: 0
E: <i>e</i>	- I: (global) intensity of the tropism	
S: de	- E: initial elasticity	
	- S: elasticity step	
torque:	Set parameters for rotating segments around their heading with-	I: 1
T: x y z	out modifying the heading orientation. The tropism vector (T)	E: 0
I: x	is required. The remaining parameters are optional, and are the	S: 0
E: <i>e</i>	same as for tropism, except that A is not required.	
s: de		
$\mathtt{stropism}\colon x\;y\;z,\;e$	Define a simple tropism, specifying the tropism vector (x,y,z)	
	and the elasticity e .	

There may be multiple tropisms in the view file. Tropisms can be manipulated using the modules in Section 5.11.

8.1.5 External files

Command	Description	Default
surface: filename.s scale sdiv tdiv txid	Declare the predefined Bezier surface in <i>filename</i> .s. The remaining parameters are optional: scale: a file-specific scaling parameter which is multiplied by the scaling parameter in the Surface module to produce the actual scaling factor. sdiv and tdiv: the number of subdivisions to draw along the s and t axes. These parameters must be used together. txid: the texture associated with the surface.	scale = 1
mesh: filename S: scale C: x y z	Declare a predefined mesh in <i>filename</i> with optional scaling (S:), and contact point coordinates (C:). The mesh file must be in OBJ format.	$scale = 1$ $x \ y \ z = 0 \ 0 \ 0$
texture: filename	Declare a texture in image file <i>filename</i> . Textures are assigned identifiers in the order given, starting at 0. Both the width and height of the image must be less than 4096. RGB and PNG files are supported.	

See Section 5.7 for surface and mesh modules.

8.1.6 Fonts

These commands define the font type to be used with the Label module (Section 5.10).

Command	Description	Default
font: Xfont	Define the font type using the Xfont specifica-	-*-courier-
	tion.	bold-r-*-*-
		12-*-*-*-
		--*
winfont: font size bi	Define the font in Windows format:	Ariel 12
	- font: the font name. Enclose in quotation	
	marks if multiple words (e.g. "Times New	
	Roman")	
	- size: the font size in pixels.	
	- bi: optional flags to specify bold and/or ital-	
	ics respectively.	

8.1.7 Postscript output control

Lpfg provides limited support for outputting models in postscript format. This feature is particularly useful when outputting 2D patterns. A key limitation in 3D is that hidden line/surface elimination is not implemented; graphical elements are output and painted (and overpainted) in the order in which they were generated and output to the postscript file.

Command	Description	Default
PS linecap: type	Define whether line caps should be applied when	0
	exporting to postscript. type=0: butt caps	
	01	
	type=1: round caps	
	type=2: projecting caps	
gradient:	Define whether gradient shading should be applied	
$direction \ magnitude$	to Beziér surfaces when exporting to postscript.	
	direction=0: gradient off	
	direction=1: gradient in the vertical (y) direction	
	direction=2: gradient in the horizontal (x) direction	
	magnitude: percentage change from near to far edge	
	(where 1.0 represents 100%). May be positive or	
	negative.	

8.1.8 Deprecated commands

The following commands have been replaced but may still exist in older models.

Command	Description	See new command
view: id px py pz scale	Define the view transformations to be	view: (Section 8.1.1)
$ux \ uy \ uz$	used for view window id:	
	- px py pz: The center of the view (pan)	
	relative to the center of the bounding	
	box.	
	- scale: The scale of objects.	
	- ux uy uz: The up direction.	

8.2 Animation file

The animation file is identified by its extension (filename.a), and may contain the following commands:

Command	Description	Default
first frame: n	Interpret derivation step n as the first frame of 0	
	an animation.	
last frame: n	Interpret derivation step n as the last frame of	Derivation
	an animation.	length
step: n	Set the number of derivation steps between frames to n .	1
$\verb swap interval: t \\$	Set the time interval between frames to t . In principle the units are one-hundredths of a second, but the actual interval may be affected by other factors (dependent on the operating system and the graphics card), especially at small t values.	0
double buffer: on off	Set double buffering on or off.	on
<pre>clear between frames: on off</pre>	Clear between frames when on.	on
hcenter between frames: on off	Horizontally center the model between frames when on.	off
<pre>scale between frames: on off</pre>	Scale the model to fit the view window between frames when on.	off
<pre>new view between frames: on off</pre>	Reset the view between frames when on. This command is most useful when using the Camera() module (Section 5.14) to dynamically position the camera.	off
<pre>display on request: on off</pre>	Display frames only on request. When on, only the first and last frame are displayed automatically. The DisplayFrame() function (Section 6.1.1) must be called to display intermediate frames. This makes it possible, for example, to skip frames that do not advance time but perform other calculations. When off, frames are displayed according to the step parameter.	off




Figure 2: Matching right context. Lateral branches are implicitly ignored.

9 APPENDIX: PRODUCTION MATCHING

When rewriting the string it is necessary to determine which production must be applied to each module in the string. The process of determining the applicable production is called *production matching*. For every module in the string, productions are checked for matching. The productions are checked in the order in which they are specified in the L-system. For a production to match, all three components of the predecessor (left context, strict predecessor and right context) must match. The rules for matching each of these components are different. This is because the L-system string is a means of representing branching structures and symmetric operations on the string do not (in general) correspond to symmetric operations on the branching structure.

This section contains a detailed explanation of rules that control the process of production matching. The notation used here utilizes symbols [and] to denote the beginning of a branch and the end of a branch (modules SB and EB in lpfg).

When the strict predecessor is compared with the module(s) at the current position in the string, they must match exactly.

When matching the right context, if a module in the context is not the same as the module in the string the following rules apply:

- If a module in the string is [and the module expected is not [then the entire branch (up to and including the corresponding] symbol) is skipped. This rule reflects the fact that modules may be topologically adjacent, even though in the string representation of the structure the two modules may be separated by modules representing a lateral branch (e.g. branch B in Figure 2).
- When a branch in the right context ends (with a right bracket) then the rest of the branch in the string is ignored by skipping to the first unmatched]. This rule also reflects the topology of the branching structure, not its string representation. For example in Figure 3, module C is closer to A than D.
- If multiple lateral branches start at a given branching point, then the predecessor in Figure 3 will only check the first branch. To skip a branch it is necessary to specify explicitly which branch at the branching point should be tested (see Figure 5). This notation is a simple consequence of the rule presented in Figure 3. In the current L-system notation there is no shortcut to specify




Figure 3: Matching right context. Remainder of lateral branch is implicitly ignored.




Figure 4: Problem with multiple lateral branches when matching the right context.

the second, third etc. lateral branch in a branching point without explicitly including pairs of [] in the production predecessor. There is also no way to specify "any of the lateral branches".

When matching the left context the following rules apply:

- Module [is always skipped, since the preceding module will be topologically adjacent (see Figure 6).
- If the module in the string indicates the end of a branch (i.e. it is a] module) then the entire branch (up to and including the corresponding [symbol) is skipped (Figure 7).

The rule illustrated in Figure 6 is a pronounced manifestation of the asymmetry in the left-context / right-context relationship: module $\tt C$ is the left context of both $\tt A$ and $\tt B$. But the right context of $\tt C$ is $\tt B$ (unless [] delimiters are used explicitly). The left context may be thought of as the parent module: the module before (below) the branching point. It is then natural to say that $\tt C$ is the parent module of both $\tt A$ and $\tt B$.




Figure 5: Explicit enumeration of lateral branches in the right context.




Figure 6: Matching left context. The beginning of the branch is implicitly ignored..




Figure 7: Matching left context. The lateral branches are implicitly ignored..

10 APPENDIX: DEPRECATED / UNDOCUMENTED FEATURES

The following features are no longer tested or supported, but may exist in older models.

10.1 B-SPLINE SURFACES

B-spline surfaces are not presently supported. All surfaces should be defined as Bézier patches (see the *bezieredit* and *stedit* tools in the vlab Tools manual). However, the constructs used to manipulate B-spline surfaces still exist within lpfg, in the expectation that an editor for them will be available at some point.

10.1.1 Defining and drawing B-spline surfaces

Predefined B-spline surfaces are specified in the view file using the command:

bsurface: filename.s scale sdiv tdiv txid

where the parameters are defined the same as for the **surface** command used to specify Bézier surfaces (see Section 8.1.5). The surface is drawn using the module:

BSurface(int id, float scale)

where id is the surface file number, and scale is a uniform scaling factor. The surface is drawn at the current location and orientation of the turtle.

10.1.2 Dynamic B-spline surfaces

B-spline surfaces can also be manipulated from within the L-system using constructs equivalent to their Bézier surface counterparts. See Section 7.1 for more details on dynamic surfaces.

The B-spline surface classes are:

BsurfaceObjS for surfaces with up to 10x10 control points BsurfaceObjM for surfaces with up to 32x32 control points

and the following methods are available for each class:

Method	Description
Set(int i, int j, const V3f& v)	Initialize the coordinates of a control point.
<pre>Get(int i, int j) const</pre>	Get the coordinates of a control point.
Scale(V3f scale)	Non-uniformly scale the surface by a different factor in
	each direction.

In addition, there are functions and modules to get and draw dynamic B-spline surfaces, similar to the Bézier surface function (Section 6.2.3) and module (Section 5.7):

Module	Description
BsurfaceObjS GetSurface(int id)	Return the control points of the predefined B-spline sur-
<pre>BsurfaceObjM GetSurface(int id)</pre>	face specified in the view file as id. If the surface con-
	tains more than one patch, only the first patch is re-
	turned.
<pre>DBSurfaceS(BsurfaceObjS s)</pre>	Draw the dynamic B-spline surface s.
<pre>DBSurfaceM(BsurfaceObjM s)</pre>	

10.2 Tablet interaction

Support for a tablet has not been tested with the newest versions of macOS or the newest tablet drivers. It consists of:

- a command line argument: -tablet
- the function: struct TabletStatus GetTabletStatus()

When -tablet is specified on the command line, tablet input is consider separately from mouse input, resulting in two separate input devices. With this option the tablet pointer is input using the GetTabletStatus() function, not the GetMouseStatus() function. However, the tablet cannot be used to change the view or insert MouseIns modules.

The GetTabletStatus() function returns the state of the tablet pointer, similar to GetMouseStatus(), including tablet pressure and pen angle if the tablet supports them. TabletStatus is a predefined data type:

```
struct TabletStatus {
  bool connected;

int viewX, viewY;
  float azimuth, altitude;
  double pressure;
  unsigned int cursorT, buttonState;

V3d atFront, atRear;
};
```

10.3 Terrain

An earlier version of *lpfg* supported a multi-resolution terrain object, with the terrain defined using a specialized editor. Unfortunately, detailed documentation of the terrain feature (including the .patch file format) is not available, and the editor has not been maintained. Nevertheless, the *lpfg* functionality related to terrain has been kept to provide backward compatibility with existing models, and as a stepping stone for reviving and supporting this functionality in the future.

Terrain functionality begins with the inclusion of a texture and a terrain in the view file using the commands:



See object: TerrainDemo

texture: filename.rgb terrain: filename.patch levels scale offset grid txid UTiling VTiling

The texture must be in RGB format. The parameters to the terrain: command are:

Parameter	Description	Default
$filename. { t patch}$	A predefined terrain file.	
levels	The number of levels to be used in the LOD system, where 1 is	
	the lowest level. Must not exceed the Number of Resolutions	
	to Export field in the Terrain Editor program at the time of	
	export. This parameter is required.	
scale	The value that should be multiplied to the position of every	1
	point in the terrain when the file is loaded.	
offset	The distance the camera must be to a patch of the terrain	1
	before it changes its level of detail. A value of 1 is conservative	
	and will work well on slower systems, while 50 will generally	
	display the highest level of resolution.	

Parameter	Description	Default
grid	Display the terrain LOD system on the screen as yellow rect-	off
	angles, when set to on.	
UTiling	The number of times the texture will be tiled in the u and v	UTiling = 1
VTiling	directions.	VTiling = 1

Parameters for drawing the terrain can be set with predefined functions:

Function	Description
bool terrainHeightAt	Project a ray along the Y axis, $(0,1,0)$, from the
(V3f pointInWorldSpace,	pointInWorldSpace, and return the pointOnTerrain at
V3f &pointOnTerrain)	which the ray intersects the terrain. If the ray intersects the
	terrain mesh, return true, otherwise return false.
void terrainVisibilityAll	Set the visibility of all terrain to Shaded, Hidden or
(VisibilityMode mode)	Wireframe
void terrainVisibilityPatch	Set the visibility of a single patch of terrain to to Shaded,
(VisibilityMode mode,	Hidden or Wireframe. The patch of terrain is selected by
int level, V3f point)	casting a ray along the Y axis at point, and choosing the
	visible patch that the ray intersects. All child patches are
	also set to this mode. The level parameter is no longer used.
void scaleTerrainBy	Multiplying the x , y and z components of each point of the
(float value)	Terrain by value.

See Section 6.3.1 for a description of the predefined data type, V3f.

The terrain mesh is drawn using the predefined module

Terrain(CameraPosition)

which draws the terrain using the current position and orientation of the turtle, and the current color. To ensure the most current camera position is used, it is generally defined just before the Terrain module:

```
CamerPosition cameraPos;
...
cameraPos = GetCameraPosition(0);
produce Terrain(cameraPos);
```

See Section 6.4 for a description of the GetCameraPosition() function.

10.4 String verification

A mechanism was developed for automatic testing the *lpfg* derivation process. It is activated by including the following statement in the L-system file (at the same level as the derivation length or consider statements, for example):

```
VerifyString: module list;
```

This statement has effect only in the batch mode (see command line option -b in Section 1.1.1). If the statement is present in the L-system after deriving the string, lpfg will compare the contents of the derived string with the strings listed in $module\ list$ (it compares only the module names, not parameter values). If the derived string matches, lpfg will print the message: Verify: Success. If the strings do not match, lpfg will print the message: Verify: Fail. It will also create two files containing the textual representation of the strings (module names only, no parameters) named:

$$\label{local_local_local} \begin{split} & \texttt{Verify}_\ lsystemfile_\texttt{expected.txt} \\ & \texttt{Verify}_\ lsystemfile_\texttt{actual.txt} \end{split}$$

where $\mathit{lsystemfile}$ is the name of the L-system file specified in the lpfg command line.

11 CREDITS

The original specification of the L+C language (then named L) was developed jointly by Przemyslaw Prusinkiewicz, Radoslaw Karwowski, Jari Pettunen, and Risto Sievanen. On this basis, *lpfg* was designed and implemented by Radoslaw Karwowski, employing his idea of translating L+C to C++ and using an existing C++ compiler, rather than developing an L+C compiler from scratch [4; 5]. Further extensions have been introduced by Brendan Lane [6], Adam Kromm, Thomas Burt, Jason Kraft, Steve Longay, Adam Runions, Cordell Bloor, Pascal Ferraro, and Mikolaj Cieslak.

12 DOCUMENT REVISION HISTORY

Date	Description	$\mathbf{B}\mathbf{y}$
2002	First version in Microsoft Word	Radoslaw Karwowski
2010 & 2014	Updates made to Microsoft Word version	Radoslaw Karwowski
		Brendan Lane
2022	Updated and re-formatted in LaTex	Lynn Mercer
		Przemyslaw Prusinkiewicz
		Pascal Ferraro
		Mikolaj Cieslak

REFERENCES

- [1] Przemyslaw Prusinkiewicz and Aristid Lindenmayer. *The Algorithmic Beauty of Plants*. With James S. Hanan, F. David Fracchia, Deborah R. Fowler, Martin J.M. de Boer, and Lynn Mercer. Springer-Verlag, 1990.
- [2] Przemyslaw Prusinkiewicz. Art and science for life: Designing and growing virtual plants with L-systems. *Acta Horticulturae*, 630:15–28, 2004.
- [3] Przemyslaw Prusinkiewicz, Mikolaj Cieslak, Pascal Ferraro, and Jim Hanan. Modeling plant development with L-systems. In RJ Morris, editor, *Mathematical Modelling in Plant Biology*, pages 139–169. Springer, 2018.
- [4] Radoslaw Karwowski. Improving the Process of Plant Modeling: The L+C Modeling Language. PhD thesis, University of Calgary, 2002.
- [5] Radoslaw Karwowski and Przemyslaw Prusinkiewicz. Design and implementation of the L+C modeling language. *Electronic Notes in Theoretical Computer Science*, 86(2):19pp, 2003.
- [6] Przemyslaw Prusinkiewicz, Radoslaw Karwowski, and Brendan Lane. The L+C plant modelling language. In J. Vos, L.F.M. Marcelis, P.H.B. de Visser, P.C. Struik, and J.B. Evers, editors, Functional-Structural Plant Modeling in Crop Production, pages 27–42. Springer, 2007.
- [7] D. Gillespie. A general method for numerically simulating the stochastic time evolution of coupled chemical reactions. *Journal of Computational Physics*, 22:403–434, 1976.
- [8] Mikolaj Cieslak and Przemyslaw Prusinkiewicz. Gillespie-Lindenmayer systems for stochastic simulation of morphogenesis. *in silico Plants*, 1(1):diz009, 2019.