

Computer Networks CS3001 (Section BDS-7A) Lecture 16

Instructor: Dr. Syed Mohammad Irteza
Assistant Professor, Department of Computer Science
17 October, 2023

2-way handshake scenarios



2-way handshake scenarios



accepted!

TCP 3-way handshake


Client state

serverSocket.listen(1) clientSocket = socket(AF_INET, SOCK_STREAM) LISTEN LISTEN clientSocket.connect((serverName, serverPort)) choose init seq num, x send TCP SYN msq **SYNSFNT** SYNbit=1, Seq=x choose init seq num, y send TCP SYNACK msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y) indicates client is live **ESTAB**

Server state

serverSocket = socket(AF INET, SOCK STREAM) serverSocket.bind(('', serverPort)) connectionSocket, addr = serverSocket.accept() SYN RCVD

A human 3-way handshake protocol



Closing a TCP connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



Principles of congestion control

Congestion:

• informally: "too many sources sending too much data too fast for network to handle"

- manifestations:
 - long delays (queueing in router buffers)
 - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




congestion control: too many senders, sending too fast

flow control: one sender too fast for one receiver

Approaches towards congestion control

End-end congestion control:


- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



TCP congestion control: AIMD

 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

Additive Increase <u>Multiplicative Decrease</u> increase sending rate by 1 cut sending rate in half at maximum segment size every each loss event RTT until loss detected Sending rate **AIMD** sawtooth behavior: probing TCP sender for bandwidth time Transport Laver: 3-12

TCP AIMD: more


Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD a distributed, asynchronous algorithm has been shown to:
 - optimize congested flow rates network wide!
 - have desirable stability properties

TCP congestion control: details



TCP sending behavior:


 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

TCP rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow, but ramps up exponentially fast




TCP: from slow start to congestion avoidance

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.

Implementation:

- variable ssthresh
- on loss event, ssthresh is set to
 1/2 of cwnd just before loss event



^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/