0.1 First-order phase transitions in Landau theory

As we have seen, Landau theory is based on the assumption that the order parameter is small near the critical point, and we have seen in the example of the Ising model how it can describe a continuous phase transition (in fact, for $t \to 0$ we have $\eta \to 0$). However, because of the symmetry properties of the Ising model we have excluded any possible cubic term; what we now want to do is to consider a more general form of \mathcal{L} which includes also a cubic term in η (in the case in which the symmetry is not violated), and see that this leads to the occurrence of a first-order phase transition. In fact, we want to generalize to include multicritical points, or phase transitions. Let us remember that in the Ising model we have phase transition derived by symmetry breaking, while now we have another type of phase transitions.

We have seen that since the order parameter is null for $T > \bar{T}$ the Landau free energy cannot contain any linear term in η . Let us therefore consider the simplest Landau free energy that depends on a particular field:

$$\mathcal{L}(\eta, t, h) = at\eta^2 - w\eta^3 + \frac{b}{4}\eta^4 - h\eta \tag{1}$$

where $t \equiv \frac{T-T^*}{2}$ and w is an additional parameter that we fix to be positive, w > 0; as in the previous case, we must have b > 0 so that η has finite values in the equilibrium configurations. In addiction,

$$at = \frac{a}{2}(T - T^*)$$
 $\begin{cases} > 0 & \text{if } T > T^* \\ < 0 & \text{if } T < T^* \end{cases}$

Remark. For w < 0 the results are the same, but in the $\eta < 0$ diagram.

The temperature T^* is the one at which we have the continuous transition if w = 0, but as we will see it doesn't have great significance now. The equilibrium configurations of the system, will be given by:

$$\frac{\partial \mathcal{L}_G}{\partial \eta} = 0 \quad \Rightarrow h = 2at\eta - 3w\eta^2 + b\eta^3$$

In absence of external fields (h = 0), the equilibrium states becomes

$$h = 0 \Rightarrow \eta(2at - 3w\eta + b\eta^2) = 0$$

The solutions of this equation are

$$\begin{cases} \bar{\eta} = 0 & \text{disordered phase} \\ \bar{\eta}_{\pm} = \frac{1}{2b} \left(3w \pm \sqrt{9w^2 - 8abt} \right) & \text{ordered phases} \end{cases}$$
 (2)

Let us rewrite the ordered solutions as

$$\bar{\eta}_{\pm} = \frac{1}{2b} \left(3w \pm \sqrt{9w^2 - 8abt} \right) = c \pm \sqrt{c^2 - \frac{2at}{b}}$$
 (3)

with

$$c = \frac{3u}{2b}$$

However, these two last solutions are possible only if:

$$\bar{\eta}_{\pm} \in \mathbb{R} \iff c^2 - \frac{2at}{b} > 0 \iff t = \frac{T - T^*}{2} < \frac{c^2b}{2a} \equiv t^{**} \equiv \frac{T^{**} - T^*}{2}$$

Lecture 16. Friday 6th December, 2019. Compiled: Thursday 15th September, 2022. Hence, we have

$$T^{**} = T^* + \frac{c^2b}{a} = T^* + 2t^{**}$$

so, since t^{**} is positive, this will occur at temperatures higher than T^* . Let us consider different cases:

• If $t > t^{**}$ $(T > T^{**})$, then the system will be in the disordered phase and we have $\bar{\eta}_{\pm} \notin \mathbb{R}$. The only real solution is $\bar{\eta} = 0$ that is also the absolute minimum of \mathcal{L} . The plot is shown in Figure 1.




Figure 1: Landau free energy for $t > t^{**}$ $(T > T^{**})$. The point $\bar{\eta} = 0$ is the absolute minimum.

- If $t \leq t^{**}$ $(T \leq T^{**})$, we have $\bar{\eta}_{\pm} = c \pm \sqrt{c^2 \frac{at}{b}} \in \mathbb{R}$ are both possible solutions. One will be a local maximum and the other a local minimum.
 - At $T=T^{**}$, we have $\bar{\eta}_-=\bar{\eta}_+$ (flex point), as shown in Figure 2.




Figure 2: Landau free energy for $t \le t^{**}$ $(T = T^{**})$. The point $\bar{\eta}_- = \bar{\eta}_+$ is a flex one.

- For $T_t < T < T^{**}$, a new minimum appears at $\eta = \bar{\eta}_+$, but we will have $\mathcal{L}(\bar{\eta}_+) > 0$, so this is only a local minimum (since $\mathcal{L}(0) = 0$): in this range of temperatures the ordered phase is metastable. The plot is shown in Figure 3.
- If we further decrease the temperature T, we will reach a temperature $T = T_t$ for which $\mathcal{L}(\bar{\eta}_+) = 0 = \mathcal{L}(0)$: at this point the ordered and disordered phase coexist, so this is the temperature of a new transition! The plot is shown in Figure 4. T_t is given by the coexistence condition

$$\mathcal{L}(\bar{\eta}_{+}) = \mathcal{L}(0)$$




Figure 3: Landau free energy for $t \le t^{**}$ ($T_t < T \le T^{**}$). The point $\bar{\eta}_+$ is a local minimum.

that is the coexistence between the disordered and ordered phases. In fact, in the plot of Figure 4 we see that there are two minima in the same line, this is a first order transition.




Figure 4: Landau free energy for $t \leq t^{**}$ $(T = T_t)$. The point $\bar{\eta}_+$ is a minimum. The ordered and disordered phase coexist.

– Finally for $T^* < T < T_t$, $\bar{\eta}_+$ becomes negative and so now $\eta = \bar{\eta}_+$ is the global minimum of \mathcal{L} : the ordered phase becomes stable and the disordered phase metastable, indeed now $\eta = 0$ is only a local minimum (see Figure 5).






Figure 5: Landau free energy for $t \leq t^{**}$ $(T^* < T < T_t)$. The point $\bar{\eta}_+$ is the global minimum.

– If now $T < T^*$, \mathcal{L} develops a new minimum for $\eta < 0$, but it is only a local minimum (the asymmetry introduced by $-w\eta^3$ ensures that $\bar{\eta}_+$ is always the global minimum). This means that also for $T < T^*$ the ordered phase with $\bar{\eta}_+$ continues to be the stable one, and so no phase transition occurs at T^* any more; this is what we meant when we said that T^* is not a relevant temperature any more.





(b) Same transition for lower values of the temperature.

Figure 6: The notation in this plot is different from the one used previously. Here $\bar{T} \equiv T^*$, $T^* \equiv T^{**}$ and $T^{**} \equiv T_t$.

Therefore, we have seen that lowering the temperature of the system, the value of η for which \mathcal{L} has a global minimum changes discontinuously from $\eta = 0$ to $\bar{\eta}_+$: this is a first-order transition. All the results obtained are shown in Figure 6.

As we said, at $T = T_t$ the system undergoes a first order transition. It is defined by two conditions: it must be a minimum of \mathcal{L} and such that the value of \mathcal{L} in that minimum is zero. Thus we can determine T_t as follows:

$$\begin{cases} \frac{\partial \mathcal{L}}{\partial \eta} = 0 = \eta \left(2at - 3w\eta + b\eta^2 \right) & \text{extreme condition} \\ \mathcal{L}(0) = \mathcal{L}(\eta_+) = 0 = \eta^2 (at - w\eta + \frac{b}{4}\eta^2) & \text{coexistence condition} \end{cases}$$

Therefore, for $\eta \neq 0$:

$$\Rightarrow \begin{cases} 2at - 3w\eta + b\eta^2 = 0\\ at - w\eta + \frac{b}{4}\eta^2 = 0 \end{cases}$$

Solving with respect to η and t, we get

$$\begin{cases} \bar{\eta}_t = +\frac{2w}{b} > 0 \\ t_t = \frac{2w^2}{ab} \end{cases}$$

Since by the definition $t = (T - T^*)/2$, we have:

$$T_t = T^* + \frac{4w^2}{ab} \tag{4}$$

Remark. Let us note that $T_t > T^*$.

Since at $T = T_t$ there is a first order transition does the system display latent heat?

$$s = -\frac{\partial \mathcal{L}}{\partial T}\bigg|_{n_t} = -\frac{1}{2}a\bar{\eta}_t^2 = -\frac{a}{2}\left(\frac{2w}{b}\right)^2$$

Hence, there is an entropy jump. The latent heat absorbed to go from the ordered to the disordered phase is

$$q = -T_t s = \frac{a}{2} T_t \left(\frac{2w}{b}\right)^2 \tag{5}$$

0.1.1 Phase stability and behaviour of χ_T

Finally, we can also determine the susceptibility of the system:

$$\chi_T \equiv \frac{\partial \eta}{\partial h}$$

In the presence of an external field, let us derive the equation of state with respect to h:

$$\frac{\partial}{\partial h} \left(\frac{\partial \mathcal{L}_G}{\partial \eta} = 0 \right) = \frac{\partial}{\partial h} \left(2at\eta - 3w\eta^2 + b\eta^3 = h \right)$$

Hence, since $\chi_T \equiv \frac{\partial \eta}{\partial h}$,

$$\chi(2at - 6w\eta + 3b\eta^2) = 1$$

The result is

$$\chi_T = \frac{1}{2at - 6w\eta + 3b\eta^2} \tag{6}$$

We now make use of equation (6) to compute the limit of stability of the phases we have found.

0.1.2 Computation of T^{**}

As said, $T = T^{**}$ is the value below which the ordered phase becomes a metastable state (local minima). In particular, since for $T = T^{**}$ the point $\bar{\eta}_{-} = \bar{\eta}_{+}$ is a flex point, we have the condition

$$\frac{\partial^2 \mathcal{L}}{\partial \eta^2} = 0$$

thus:

$$\frac{\partial}{\partial n} \left(2at\eta - 6w\eta^2 + b\eta^3 = h \right) = 0 \quad \Rightarrow 2at - 6w\eta + 3b\eta^2 = \frac{\partial h}{\partial n} = \chi^{-1} = 0$$

Remember that at $T = T^{**}$ the two solutions $\bar{\eta}_{\pm}$ coincide, hence from Eq.(3) we have

$$c^2 - \frac{2at}{b} = 0 \quad \Rightarrow \bar{\eta}_{\pm} = \eta_2 = \frac{3w}{2b}$$

Inserting in the expression with $\chi^{-1} = 0$, we have

$$\chi^{-1} = 0 = 2at^{**} - 6w\bar{\eta}_2 + 3b\bar{\eta}_2^2$$

Hence,

$$\iff t^{**} = \frac{9w^2}{8ab} = \frac{1}{2}(T^{**} - T^*)$$
 (7)

Remind that for $T_t < T < T^{**}$ the ordered phase $\bar{\eta}_+$ is metastable.

0.1.3 Computation of T^*

The instability of the disordered phase $\eta=0$ is when \mathcal{L} presents a flex point at $\eta=0$. Therefore, from the condition

$$\left. \frac{\partial^2 \mathcal{L}}{\partial \eta^2} \right|_{\bar{\eta} = 0} = 0$$

we have

$$\chi^{-1} = 2at - 6w\eta + 3b\eta^2 = \frac{\partial h}{\partial \eta} = 0 \quad \Rightarrow 2at = 0 \Rightarrow t = 0$$

Hence, we have

$$\Rightarrow T = T^* \tag{8}$$

thus no phase transition occurs at T^* any more. The plot of the Landau free energy in the case $T = T^*$ is shown in Figure 7.




Figure 7: Landau free energy for $t \le t^{**}$ $(T = T^*)$. The point $\bar{\eta}_+$ is the global minimum, while the point $\bar{\eta} = 0$ is a flex point.

0.2 Multicritical points in Landau theory

It is possible for a system to have more "disarranging parameters" than the only temperature T; let us call one such field Δ . In this case the phase diagram of the system becomes richer, with coexistence and critical lines that intersect in points called multicritical points; one of the most common examples of a multicritical point is the tricritical point, which divides a first-order transition line from a second-order one. An example of a system of the type we are considering is the Blume-Emery-Griffiths model, which we have studied in Mean field theory for the Blume-Emery-Griffiths model. In that case the additional "disarranging field" was the concentration x of He^3 , and the tricritical point is the one we called (x_t, T_t) .

Such a phenomenology can be obtained within Landau theory also with terms different from a simple cubic one; in particular, we can have first order phase transitions even when the system is invariant under parity, like in the case of the Ising model. In fact in that situation we required the coefficient of η^4 to be always positive, but if this is not true then $\mathcal L$ will be:

$$\mathcal{L}(T,\Delta,\eta) = \frac{a(t,\Delta)}{2}\eta^2 + \frac{b(t,\Delta)}{4}\eta^4 + \frac{c}{6}\eta^6 - h\eta \tag{9}$$

where a, b and c are functions of two parameteres (T, Δ) and c > 0 positive for the stability of the system (otherwise, like in the case previously considered, the minimization of \mathcal{L} leads η to infinity); Δ is the disordered field (in the BEG model Δ was the % He³ atoms).

Remark. To allow the coefficient of η^4 to change sign, we need the η^6 term.

Let us study the phenomenology of Δ (Δ_c is a critical value):

• If $\Delta < \Delta_c$: as T decreases, $a(T, \Delta)$ decreases and, at $T = T_c(\Delta)$, becomes zero. In this region $b(T, \Delta) > 0$ and the system displays the standard (η^4) critical point. At $T = T_c$ we have:

$$T = T_c(\Delta) \Rightarrow \begin{cases} a(T_c, \Delta) = 0\\ b(T_c, \Delta) > 0 \end{cases}$$

If a changes sign and b is kept positive (which can be done varying the values of T and Δ in a way such that a goes to zero faster than b, depending of course

on their explicit expressions) then a critical transition occurs since in this case $\eta=0$ becomes a local maximum for \mathcal{L} , and it develops two new global minima. Therefore, the solution of the equation $a(T,\Delta)=0$ will give a line of critical points in (T,Δ) plane.

• If $\Delta > \Delta_c$: as T decreases, $b(T, \Delta)$ becomes zero before $a(T, \Delta)$. At $T = T_c$ we have

$$T = T_c(\Delta) \Rightarrow \begin{cases} a(T_c, \Delta) > 0 \\ b(T_c, \Delta) = 0 \end{cases}$$

Hence, if b becomes negative while a is still positive (which again can be done varying T and Δ so that b vanishes faster than a) then something rather different happens: in this case, one can show that as b approaches zero $\mathcal L$ develops two new symmetric local minima at $\bar{\eta}_{\pm}$ (similarly to the case analysed before, with the difference that now the situation is perfectly symmetric since $\mathcal L$ is even) and they will become the new global minima as $\mathcal L(\bar{\eta}_{\pm})=0$, which happens when b changes sign: this way the equilibrium value of the order parameter change discontinuously from zero to a non-zero quantity so a first-order transition has indeed happened.

In this case, we have

$$\mathcal{L} = a\eta^2 + c\eta^6, \quad a > 0$$

The equilibrium states are

$$\frac{\partial \mathcal{L}}{\partial \eta} = 2a\eta + 6c\eta^5 = 0$$

so, the solutions are

$$\begin{cases} \eta = 0 \\ \eta_{1,2,3,3} \end{cases}$$




Figure 8: Landau free energy for $\Delta > \Delta_c$. There is coexistence between three phases, in fact there are 3 global minima.

• Case $\Delta = \Delta_t$: the tricritical point is given by the values of $\Delta = \Delta_t$ and $T = T_c$ such that

$$a(\Delta_t, T_t) = b(\Delta_t, T_t) = 0$$

This means that when both a and b are null the system goes from exhibiting a continuous critical transition to a discontinuous first-order one; in other words, the tricritical point (T_c, Δ_c) can be determined from the solution of the equations $a(T, \Delta) = 0$ and $b(T, \Delta) = 0$.

At the tricritical point the system is described by the following Landau free-energy:

$$\mathcal{L}_t = c\eta^6 - h\eta$$

The equation of state is

$$\frac{\partial \mathcal{L}_t}{\partial \eta} = 0 \quad \Rightarrow h = 6c\eta^5$$

The first-order transition with an even \mathcal{L} are shown in Figure 9.




Figure 9: First-order transition with an even \mathcal{L} .

To conclude let us consider again a system with an Ising-like Landau free energy, where c > 0 and a, b are in general functions of the reduced temperature t (and also of the other "disarranging" parameter Δ , which we now neglect). The Landau free energy is again

$$\mathcal{L} = \frac{a}{2}\eta^2 + \frac{b}{4}\eta^4 + \frac{c}{6}\eta^6 - h\eta$$

We now want to show that we can understand how the phase diagram of the system is in (a, b) space, i.e. that we can draw where the phase transition lines are and so we are able to visually represents where the various phases of the system are in (a, b) plane.

First of all, we can note that when a, b > 0 the only minimum of \mathcal{L} is $\bar{\eta} = 0$, so the system is in the paramagnetic phase. Furthermore if a < 0 and b > 0 the system is in the magnetic phase, and a second order transition has occurred; therefore we can surely say that the half-line a = 0, b > 0 is a second order transition line.

We must thus determine where the first order transition line lies in (a, b) space. In order to do so, we first note that the extrema of \mathcal{L} are given by:

$$0 = \frac{\partial \mathcal{L}}{\partial \eta} = \eta (a + b\eta^2 + c\eta^4) \quad \Rightarrow \quad \bar{\eta}_{\pm}^2 = \frac{-b \pm \sqrt{b^2 - 4ac}}{2c}$$

(and of course they exist only when the temperature is such that $b^2 - 4ac > 0$) and since:

$$\frac{\partial^2 \mathcal{L}}{\partial \eta^2}_{|\overline{\eta}_{+}} = \pm \overline{\eta}_{\pm}^2 \cdot 2\sqrt{b^2 - 4ac}$$

we have that $\pm \bar{\eta}_+$ are maxima while $\pm \bar{\eta}_-$ are minima. The first order transition happens when $\mathcal{L}(\pm \bar{\eta}_{\pm}) = \mathcal{L}(0) = 0$, so:

$$\frac{a}{2}\bar{\eta}_{+}^{2} + \frac{b}{4}\bar{\eta}_{+}^{4} + \frac{c}{6}\bar{\eta}_{+}^{6} = 0 \quad \Rightarrow \quad \frac{a}{2} + \frac{b}{4}\bar{\eta}_{+}^{2} + \frac{c}{6}\bar{\eta}_{+}^{4} = 0$$

Now, from the condition $\partial \mathcal{L}/\partial \eta = 0$ we can express $\bar{\eta}_+^4$ as a function of $\bar{\eta}_+^2$, and we get $\bar{\eta}_+^4 = -(a+b\bar{\eta}_+^2)/c$. Substituting we get:

$$\bar{\eta}_+^2 = -4\frac{a}{b}$$

and substituting again in $\bar{\eta}_+^2 = (-b + \sqrt{b^2 - 4ac})/(2c)$ in the end we get:

$$b = -4\sqrt{\frac{ac}{3}}$$

so the first order transition line is a parabola in (a, b) plane (in particular it will lie in the fourth quadrant). In the end the situation is as in Figure 10. As we can see the tricritical point of the system, being the point that divides the first-order from the second-order transition line, is the origin (0,0) of the parameter space.




Figure 10: Phase diagram of the system in (a, b) space.

0.3 Liquid crystals

We now proceed to study a particular physical system, liquid crystals, to which we will apply Landau theory of phase transitions. As we will see the symmetries of the system will allow the Landau free energy to include a cubic term in the order parameter (which we will properly define), and so we will be able to describe the first-order transition from an isotropic to a nematic phase (which we are now going to introduce).

0.3.1 What are liquid crystals?

Liquid crystals phase (LC) can be seen as an intermediate phase between a liquid and a solid: they are liquid like any other conventional fluid, but also have internal orientetional order like solid crystals. This orientational order provides them particular anisotropic properties from an optical, electric and magnetic point of view. The most common structural characteristics of the molecules that constitute liquid crystals are the following:

- They have an elongated, anisotrpic shape.
- Their axes can be considered rigid with good approximation.
- They have strong electric dipoles or easily polarizable groups.

Furthermore, it seems that the groups located at the extremities of a molecule are not relevant for the formation of phases.

The vast majority of the interesting phenomenology of liquid crystals concerns the geometry and dynamics of the preferred axis of orientation $\overset{\leftrightarrow}{n}(\vec{\mathbf{r}})$, called *director*. This is a 'two arrow vector' that gives the local average alignment of the elementary constituents. In this description the amplitude of $\overset{\leftrightarrow}{n}(\vec{\mathbf{r}})$ is irrelevant and one takes $\overset{\leftrightarrow}{n}(\vec{\mathbf{r}})$ such that is unitary (i.e. $\begin{vmatrix} \dot{n}(\vec{\mathbf{r}}) \end{vmatrix} = 1$). Since there is no head-tail symmetry (apolar order), $\overset{\leftrightarrow}{n} = -\overset{\leftrightarrow}{n}$ (i.e. $+\overset{\leftrightarrow}{n}(\vec{\mathbf{r}})$ and $-\overset{\leftrightarrow}{n}(\vec{\mathbf{r}})$ are physically equivalent).




Figure 11: Graphical representation of the nematic, smectic and cholesteric phases of a liquid crystal.

There is a plethora of possible liquid crystal phases; the most common are:

- Nematic: this phase is characterized by a very strong long-ranged orientational order: the main axes of the molecules tend to orientate along a preferred direction (see Figure 12), determined by the director. There is no long-ranged translational order of the molecular centers of mass, even if a short-ranged one can exist.
 - From optical point of view the Nematic phase is birifrangent, i.e. they exhibit two different refractive indexes: one parallel to the director n (called ordinary refractive index) and one orthogonal to it (special refractive index). These optical properties of the nematic phase are used to build devices like LCDs.
- Smectic: also in this phase the molecules are aligned along a preferred direction, but contrarily to the nematic one this phase has also a spatial periodic order: the molecules are organised in layers. Furthermore, differently from nematic phases, smectic liquid crystals have non-uniform density and are generally more viscous.
- Cholesteric: It is similar to the nematic phase since it has a long-ranged orientational order, but the direction of \vec{n} changes regularly in space; the typical configuration of a cholesteric liquid crystal has a director $\vec{n}(\vec{r})$ that rotates when \vec{r} varies along a particular direction: for example, in a three-dimensional reference frame the molecules are orientated along the y direction in xy plane, but this direction roteates if z changes.

The structure of a cholesteric liquid crystal is characterised by the spatial distance along the torsion axis, called pitch, after which the director has rotated by an angle of 2π . The pitch of the most common cholesteric liquid crystals is of the order of several hundred nanometers, so comparable with the wavelength

of visible light; furthermore, it can also be very sensitive to changes in temperature, chemical composition, or external electromagnetic fields. Note also that a nematic liquid crystal can be seen as a cholesteric one with infinite pitch; these two phases in fact are not independent from each other, and there is no real phase transition between them.




Figure 12

0.3.2 Definition of an order parameter for nematic liquid crystals

What we now want to do is to apply Landau theory to liquid crystals in order to study the transition from an isotropic to a nematic phase (Figure 12); therefore, we must define an order parameter for such a system. This is absolutely not trivial, and there are two ways to do it a microscopic and a macroscopic one. We will use a macroscopic approach.

Macroscopic approach

From a macroscopic point of view we have already stated that an important difference between the disordered and nematic phases consists in the response functions when the liquid crystal is subjected to magnetic or electrical fields. Hence, a macroscopic definition of an order parameter for LC phase is based on the system response when subject to fields. For instance, supposing that we have a liquid crystal subject to an external magnetic field $\vec{\mathbf{H}}$, the diamagnetic response of the system will be measurable in terms of its magnetization $\vec{\mathbf{M}}$, and in particular:

$$\vec{\mathbf{M}} = \bar{\bar{\chi}}\vec{\mathbf{H}} \tag{10}$$

where $\bar{\chi}$ is the response function matrix, namely the magnetic susceptibility of the system. In components we have:

$$M_{\alpha} = \chi_{\alpha\beta} H_{\beta} \tag{11}$$

where the inexes α, β stands for x, y, z. If $\vec{\mathbf{H}}$ is static, then χ is symmetric, i.e.

$$\chi_{\alpha\beta} = \chi_{\beta\alpha}$$

In the isotropic phase χ will also be diagonal, namely

$$\chi_{\alpha\beta} = \chi \delta_{\alpha\beta}$$

while in the nematic phase For a LC in the neumatic one has

$$\chi_{\alpha\beta} = \begin{pmatrix} \chi_{\perp} & 0 & 0\\ 0 & \chi_{\perp} & 0\\ 0 & 0 & \chi_{\parallel} \end{pmatrix} \tag{12}$$

where, as before, we have supposed that the director $\stackrel{\leftrightarrow}{n}$ is parallel to the z direction.

Therefore we could build an order parameter in terms of the susceptibility χ , and this parameter will necessarily have a tensorial nature (since χ itself is in general a tensor), so it will not be a simple scalar like in the previous case. Since we want our order parameter to vanish in the disordered phase, we can define it "removing" from χ its isotropic component. In other words, in components we can define:

$$Q_{\alpha\beta} = A\left(\chi_{\alpha\beta} - \frac{1}{3}\delta_{\alpha\beta}\operatorname{Tr}\bar{\chi}\right)$$
 (13)

where A is a constant. In this way Q is a good tensorial order parameter. In particular, the order parameter is a second rank traceless tensor. Let us note that its definition is completely general, and in fact it is useful also to describe other kinds of phases, not only the uniaxial nematic one.

It is possible to show that $Q_{\alpha\beta}$ can be written in terms of the local average orientiational order of the elementary constituents, $\vec{n}(\vec{\mathbf{r}})$ and the degree of local order given by a scalar $S(\vec{\mathbf{r}})$. Hence, we can define

$$Q_{\alpha\beta}(\vec{\mathbf{r}}) = S(\vec{\mathbf{r}}) \left(n_{\alpha}(\vec{\mathbf{r}}) n_{\beta}(\vec{\mathbf{r}}) - \frac{1}{3} \delta_{\alpha\beta} \right)$$
(14)

The advantage of this definition of the order parameter (which is the one we will use in the following) is that it also takes into account the degree of orientation and the mean direction. By definition Q is symmetric and traceless¹, so in general way we can write it as:

$$Q = \begin{pmatrix} q_1 & q_2 & q_3 \\ q_2 & q_4 & q_5 \\ q_3 & q_5 & -q_1 - q_4 \end{pmatrix}$$
 (15)

0.3.3 Landau-de Gennes theory for nematic liquid crystals

Since we now have a proper order parameter, we can formulate the Landau theory for the phase transitions of nematic liquid crystals (also called Landau-de Gennes theory). In particular we want to study the transition between the isotropic and nematic phase, and we call T_{n-i} the temperature at which it occurs.

As we have already stated, the Landau free energy \mathcal{L} must be consistent with the symmetries of the system, so in this case it must be invariant under rotations. Now, since Q transforms as a tensor under rotations and \mathcal{L} must be a scalar, it will contain terms of the form $\operatorname{Tr} \bar{Q}^P$; to the fourth order we will have (the linear term is absent because by definition Q is traceless, i.e. $\operatorname{Tr}(Q) = 0$):

$$\mathcal{L} = \mathcal{L}_0 + \frac{1}{2}A(T)\operatorname{Tr}\bar{\bar{Q}}^2 + \frac{1}{3}B(T)\operatorname{Tr}\bar{\bar{Q}}^3 + \frac{1}{4}C(T)\left[\left(\operatorname{Tr}\bar{\bar{Q}}^2\right)^2 + \operatorname{Tr}\bar{\bar{Q}}^4\right]$$

In reality this expression, and in particular the quartic term, can be simplified: in fact it is a property (which we will not prove) of any $n \times n$ symmetric matrix that $\operatorname{Tr} \bar{Q}^s$ with s > n can be expressed as a polynomial of $\operatorname{Tr} \bar{Q}^p$ with p < n, so in our case any $\operatorname{Tr} \bar{Q}^s$ with $s \geq 4$ can be expressed in terms of $\operatorname{Tr} \bar{Q}^2$ and $\operatorname{Tr} \bar{Q}^3$ (we are

¹A matrix whose trace is zero is said to be traceless.

automatically neglecting $\operatorname{Tr} \bar{Q}$ since in our case it vanishes, but in general it must be considered). Therefore, we can write the Landau free energy as:

$$\mathcal{L} = \mathcal{L}_0 + \frac{1}{2}A(T)\operatorname{Tr}\bar{\bar{Q}}^2 + \frac{1}{3}B(T)\operatorname{Tr}\bar{\bar{Q}}^3 + \frac{1}{4}C(T)\left(\operatorname{Tr}\bar{\bar{Q}}^2\right)^2$$
 (16)

or, in components:

$$\mathcal{L} = \mathcal{L}_0 + \frac{1}{2}A(T)Q_{\alpha\beta}Q_{\beta\alpha} + \frac{1}{3}B(T)Q_{\alpha\beta}Q_{\beta\gamma}Q_{\gamma\alpha} + \frac{1}{4}C(T)(Q_{\alpha\beta}Q_{\beta\alpha})^2$$
 (17)

Remark. Since each 3×3 matrix satisfies the relation

$$\operatorname{Tr}\bar{\bar{Q}}^4 = \frac{1}{2} \left(\operatorname{Tr}\bar{\bar{Q}}^2\right)^2$$

the term proportional to C(T) can be written as $\frac{1}{2}C(T) \operatorname{Tr} \bar{Q}^4$.

Let us note that since our order parameter is a tensor its invariance under rotations does not exclude the possible existence of terms with odd powers of Q in \mathcal{L} , in particular the cubic one.

For the most general case of a biaxial nematic phase \bar{Q} can be diagonalized giving

$$Q_{\alpha\beta} = \begin{pmatrix} \frac{2}{3}S & 0 & 0\\ 0 & -\frac{1}{3}(S+\eta) & 0\\ 0 & 0 & -\frac{1}{3}(S-\eta) \end{pmatrix}$$
(18)

where we remind that S is the degree of local order. If $\eta = 0$ we have the standard uniaxial nematic phase and the order parameter becomes

$$Q_{\alpha\beta} = \begin{pmatrix} \frac{2}{3}S & 0 & 0\\ 0 & -\frac{1}{3}S & 0\\ 0 & 0 & -\frac{1}{3}S \end{pmatrix}$$
 (19)

Now, from the expression of Q in the case of a uniaxial nematic liquid crystal (Eq.(19)) we have:

$$\operatorname{Tr}\bar{\bar{Q}}^2 = \frac{2}{3}S^2, \quad \operatorname{Tr}\bar{\bar{Q}}^3 = \frac{2}{9}S^3, \quad \left(\operatorname{Tr}\bar{\bar{Q}}^2\right)^2 = \frac{4}{9}S^4$$

Hence, for uniaxial nematic liquid crystal the Landau free energy becomes

$$\mathcal{L} = \mathcal{L}_0 + \frac{A(T)}{3}S^2 + \frac{2}{27}B(T)S^3 + \frac{C(T)}{9}S^4$$
 (20)

so that, supposing that B and C do not depend on the temperature (i.e. B(T) = B and C(T) = C), while $A(T) \simeq A(T - T^*)$, we have:

$$\mathcal{L} = \mathcal{L}_0 + \frac{A}{3}(T - T^*)S^2 + \frac{2}{27}BS^3 + \frac{C}{9}S^4$$
 (21)

This Landau free energy has exactly the same form of the one we studied in first-order phase transitions in Landau theory (Eq.(1)), with the substitutions:

$$a = \frac{2}{3}A$$
, $w = -\frac{2}{27}B$, $b = \frac{4}{9}C$

Applying the results we have already found (Eq.(4)), we will have that the first-order transitions between the isotropic and nematic phases occurs at the temperature:

$$T_{n-i} = T^* + \frac{4w^2}{ba} = T^* + \frac{2B^2}{27AC}$$
 (22)

Chapter 1

Role of fluctuations in critical phenomena: Ginzburg criterium, Coarse-graining and Ginzburg-Landau theory of phase transitions

1.1 Importance of fluctuations: the Ginzburg criterium

As we have seen, the main assumption (and the most important problem) of mean field theories is that the fluctuations of the order parameter are completely neglected in the computation of the partition function Z; this approximation breaks down in the neighbourhoods of critical points, where as we have seen in long range correlations the correlation length becomes comparable with the size of the system:

$$\xi \stackrel{T \to T_c}{\sim} |T - T_c|^{-\nu}$$

What we would now like to do is to include these fluctuations in a mean field theoretical framework; this will lead to the so called Ginzburg-Landau theory.

Overall, mean field is not a very good approximation in proximity of the critical point, and the question is: how bad is the mean field approximation in proximity of it? As a first approach we can try to estimate how big is the error we make in mean field theories neglecting the fluctuations of the order parameter near a critical point, so that we can understand under which conditions mean field theories are actually a good approximations.

To make things explicit, let us use the Ising model as a base for our considerations. We have seen in Weiss mean field theory for the Ising model that the Weiss mean field theory for the Ising model is based on the assumption that

$$\langle S_i S_j \rangle \xrightarrow{MF} \langle S_i \rangle \langle S_j \rangle$$

i.e. that the spins are statistically independent; therefore, a possible estimate of the error dor each pair of spin (S_i, S_j) made with this assumption can be:

$$E_{ij} = \frac{|\langle S_i S_j \rangle - \langle S_i \rangle \langle S_j \rangle|}{\langle S_i \rangle \langle S_j \rangle}$$
(1.1)

The numerator of E_{ij} is, by definition, the two-point connected correlation function:

$$G_c(i,j) \equiv \langle S_i S_j \rangle - \langle S_i \rangle \langle S_j \rangle = \langle (S_i - \langle S_i \rangle)(S_j - \langle S_j \rangle) \rangle \tag{1.2}$$

Assuming translational invariance, we have

$$G_c(i,j) \to G_c(|\vec{\mathbf{r}}_i - \vec{\mathbf{r}}_j|) \to G_c(r)$$

In order to compute $G_c(r)$ we cannot assume omogeneity since $\langle S_i \rangle = \langle S_j \rangle = m$. It implies that $G_c = 0$ identically, and if we want to compute the error in the mean field, is always zero. Therefore, in order to have non-null correlation functions we need that the system exhibits some kind of inhomogeneity, not necessarily due to thermal fluctuations. In fact, the connected correlation function G_c describes not only the spatial extension of the fluctuations of the order parameter, but also, through the linear response theory, the way in which m varies in space in response to an external inhomogeneous magnetic field. Within a mean field theory this is the only way to compute G_c ! Let us see this explicitly. We know that from the partition function of the Ising model in an inhomogeneous external field $\vec{\mathbf{H}}_i$, i.e.:

$$Z[H_i] = \operatorname{Tr}_{\{S\}} \left(e^{-\beta \left(-J \sum_{\langle ij \rangle} S_i S_j - \sum_i H_i S_i \right)} \right)$$
 (1.3)

we have the definition of the thermal average

$$\langle S_i \rangle = \frac{\operatorname{Tr}_{\{S\}} \left(S_i e^{-\beta \left(-J \sum_{\langle ij \rangle} S_i S_j - \sum_i H_i S_i \right)} \right)}{Z[H_i]} = \frac{1}{\beta Z} \frac{\partial Z}{\partial H_i} = \beta^{-1} \frac{\partial \ln Z}{\partial H_i} = -\frac{\partial F}{\partial H_i} \quad (1.4)$$

Similarly, one can show that

$$\langle S_i S_j \rangle = \frac{\beta^{-2}}{Z} \frac{\partial^2 Z}{\partial H_i \partial H_j} \tag{1.5}$$

and thus:

$$G_{c}(i,j) = \frac{\beta^{-2}}{Z} \frac{\partial^{2} Z}{\partial H_{i} \partial H_{j}} - \left(\frac{\beta^{-1}}{Z} \frac{\partial Z}{\partial H_{i}}\right) \left(\frac{\beta^{-1}}{Z} \frac{\partial Z}{\partial H_{j}}\right)$$

$$= \beta^{-2} \frac{\partial^{2} \ln Z}{\partial H_{i} \partial H_{j}} = -\frac{\partial^{2} F(\{H_{i}\})}{\partial H_{i} \partial H_{j}}$$
(1.6)

Therefore, the response in i due to a variation of H in j is

$$\frac{\partial}{\partial H_j} \langle S_i \rangle = \frac{\partial}{\partial H_j} \left[\beta^{-1} \frac{\partial \ln Z}{\partial H_i} \right] = \frac{\partial}{\partial H_j} \left[-\frac{\partial F}{\partial H_i} \right] = \beta G_c(i,j)$$

so $G_c(i,j)$ can indeed be seen as a response function. The generating functions are:

- $Z[H_i]$: generating function of G(i, j).
- $\ln Z[H_i] = -\beta F$: generating function of $G_c(i,j)$.

If we now call:

$$M = \sum_{i} \langle S_i \rangle$$

we will have

$$\frac{\partial M}{\partial H_j} = \sum_{i} \frac{\partial \langle S_i \rangle}{\partial H_j} = \beta \sum_{i} G_c(i, j)$$

If our system is invariant under translations and subject to a uniform field, then:

$$\frac{\partial M}{\partial H} = \sum_{i} \frac{\partial M}{\partial H_{j}} \frac{\partial H_{j}}{\partial H} = \beta \sum_{i,j} G_{c}(i,j)$$

and since $\chi_T = \partial M/\partial H$ we get:

$$\chi_T = \beta \sum_{i,j} G_c(i,j) = \beta \sum_{i,j} \left(\langle S_i S_j \rangle - \langle S_i \rangle \langle S_j \rangle \right) \tag{1.7}$$

which is a version of the fluctuation-dissipation theorem.

1.1.1 Fluctuation-dissipation relation

The fluctuation–dissipation theorem (FDT), or fluctuation–dissipation relation (FDR), is a powerful tool in statistical physics for predicting the behavior of systems that obey detailed balance. It is a general result of statistical thermodynamics that quantifies the relation between the fluctuations in a system that obeys detailed balance and the response of the system to applied perturbations.

More specifically, the fluctuation—dissipation theorem says that when there is a process that dissipates energy, turning it into heat (e.g., friction), there is a reverse process related to thermal fluctuations.

For instance, let us consider the Brownian motion: if an object is moving through a fluid, it experiences drag (air resistance or fluid resistance). Drag dissipates kinetic energy, turning it into heat. The corresponding fluctuation is Brownian motion. An object in a fluid does not sit still, but rather moves around with a small and rapidly-changing velocity, as molecules in the fluid bump into it. Brownian motion converts heat energy into kinetic energy—the reverse of drag.

Now, let us consider the partition function with an homogeneous magnetic field $H_i = H$, $\forall i$:

$$Z_N = \operatorname{Tr}_{\{S\}} e^{\beta J \sum_{\langle ij \rangle} S_i S_j + H \sum_i S_i}$$

The magnetization is thus:

$$M = \sum_{i} \langle S_i \rangle = \frac{1}{Z} \operatorname{Tr}_{\{S\}} \sum_{i} S_i e^{\beta J \sum_{\langle ij \rangle} S_i S_j + H \sum_i S_i} = \frac{1}{\beta Z_N} \frac{\partial Z_N}{\partial H}$$

Similarly, we have

$$\sum_{ij} \langle S_i S_j \rangle = \frac{1}{\beta^2 Z_N} \frac{\partial^2 Z_N}{\partial H^2}$$

Recall that

$$\frac{1}{N}F = -\frac{1}{N}k_BT\ln Z$$

Hence, the magnetic supsceptibility is:

$$\chi_{T} = \frac{\partial m}{\partial H} = \frac{\partial}{\partial H} \left[-\frac{1}{N} \frac{\partial F}{\partial H} \right] = \frac{\partial}{\partial H} \left[\frac{1}{N} k_{B} T \frac{\partial \ln Z}{\partial H} \right]$$

$$= \frac{1}{N} k_{B} T \left[\frac{\partial^{2} \ln Z}{\partial H^{2}} \right] = \frac{1}{N} k_{B} T \left[\frac{1}{Z} \frac{\partial^{2} Z}{\partial H^{2}} - \frac{1}{Z^{2}} \left(\frac{\partial Z}{\partial H} \right)^{2} \right]$$

$$= \frac{1}{N\beta} \left[\beta^{2} \sum_{ij} \langle S_{i} S_{j} \rangle - \beta^{2} \left(\sum_{i} \langle S_{i} \rangle \right)^{2} \right]$$

$$= \frac{\beta}{N} \sum_{ij} G_{c}(i, j) = \frac{\beta}{N} \sum_{ij} G_{c}(\vec{\mathbf{r}}_{i} - \vec{\mathbf{r}}_{j})$$

$$= \beta \sum_{i} G_{c}(\vec{\mathbf{x}}_{i})$$

where we have defined $\vec{\mathbf{x}}_i \equiv \vec{\mathbf{r}}_i - \vec{\mathbf{r}}_j$. Therefore:

$$\Rightarrow \chi_T = (a^d k_B T)^{-1} \int_{\Omega} d^d \vec{\mathbf{r}} G_c(\vec{\mathbf{r}})$$
 (1.8)

this is the fluctuation dissipation relation.

1.1.2 Computation of E_{TOT}

Let us now try to understand when the error E_{ij} done in mean field theories is negligible. Now, in general terms if we formulate a mean field theory for a system we will make the error E_{ij} in the region where correlations are relevant, namely if $|\vec{\mathbf{r}}|$ is the distance between two points of the system the error is made for $|\vec{\mathbf{r}}| \leq \xi$, with ξ the correlation length. The total relative error is the $E_R(r)$ integrated over the region of radius $|\vec{\mathbf{r}}| \leq \xi$, i.e. where correlations are not negligible:

$$E_{TOT} = \frac{\int_{|\vec{\mathbf{r}}| \le \xi} G_c(r) \, \mathrm{d}^d \vec{\mathbf{r}}}{\int_{|\vec{\mathbf{r}}| \le \xi} \langle S_i \rangle \, \langle S_j \rangle \, \mathrm{d}^d \vec{\mathbf{r}}}$$
(1.9)

where we have called d the dimensionality of our system. Supposing $T < T_c$, so that the order parameter η is non null, i.e. $\eta(r) = \eta \neq 0$, we have:

$$\langle S_i \rangle \langle S_j \rangle \approx \eta^2$$

is uniform in the region $|\vec{\mathbf{r}}| < \xi$. Hence, our mean field theory will be a good approximation if $E_{TOT} \ll 1$:

$$E_{TOT} \sim \frac{\int_{|\vec{\mathbf{r}}| \le \xi} G_c(\vec{\mathbf{r}}) d^D \vec{\mathbf{r}}}{\int_{|\vec{\mathbf{r}}| < \xi} \eta^2 d^D \vec{\mathbf{r}}} \ll 1$$
(1.10)

known as Ginzburg criterion. If it is satisfied, then the mean field theory is a valid approximation.

1.1.3 Estimation of E_{TOT} as $t \to 0^-$

In order to express Eq.(1.10) in a useful fashion, let us write it in terms of critical exponents; using also the version we have just found of the fluctuation-dissipation theorem (Eq.(1.8)) we get (supposing our system is continuous) that the numerator of Eq.(1.10) can be approximated as

$$\int_{|\vec{r}| < \xi} G_c(r) d^d r \overset{\text{fluctuation}}{\sim} k_B T_c \chi_T \sim t^{-\gamma}$$

On the other hand, the denominator can be approximated as

$$\int_{|\vec{\mathbf{r}}|<\xi} \eta^2 \,\mathrm{d}^d r \sim \xi^d |t|^{2\beta} \sim t^{2\beta-\nu d}$$

Therefore, the Ginzburg criterion can be reformulated as:

$$E_{TOT} \stackrel{t \to 0^-}{\sim} t^{-\gamma + \nu d - 2\beta} \ll 1$$

and in the limit $t \to 0^-$ this is possible only if $-\gamma + \nu d - 2\beta > 0$, i.e.:

$$d > \frac{\gamma + 2\beta}{\nu} \equiv d_c \tag{1.11}$$

This means that Ginzburg criterion allows us to determine the *upper critical dimension* d_c of a system, namely the dimension above which mean field theories are good approximations. Let us consider three different cases:

- Case $d < d_c$: fluctuations are relevant and mean field is no a good approximation
- Case $d > d_c$: fluctuations are less important and mean field describes properly the critical point.

• Case $d = d_c$: mean field critical exponents ok but strong correction to the scaling expected. For a Ising-like systems (in the mean field) we have

$$\beta = \frac{1}{2}, \quad \gamma = 1 \quad \Rightarrow d_c = \frac{2}{\nu}$$

In order to compute d_c we need to compute ν withing the mean field approximation. Let us note that since it depends on the critical exponents, the upper critical dimension d_c ultimately depends on the universality class of the system considered; furthermore, in order to actually be able to compute d_c we must generalize Landau theory to systems with spatial inhomogeneities so that we are able to compute the critical exponent ν .

Remark. Remind that within the mean field theory the ν exponent it is not defined. In fact, the ν exponent define the divergence of the correlation length, but in the mean field we neglet correlation between fluctuations.

We have $\nu_{MF} = 1/2$, hence the upper critical dimension for the mean field is d > 4.