

porated by Ordinance No. XXIV of 2002 promulgated by Government of the Punjab)
FACULTY OF INFORMATION TECHNOLOGY

Computer Organization and Assembly Language

Lab 03				
Topic	1. Direct Addressing Mode with variations.			

PART 1

Types of Registers:-

The registers are grouped into three categories:-

1. General Purpose registers

- 1.1. Data registers
 - 1.1.1. AX is the primary accumulator.
 - 1.1.2. BX is known as the base register.
 - 1.1.3. *CX* is known as the count register.
 - 1.1.4. **DX** is known as the data register.
- 1.2. Pointer registers
 - 1.2.1. Instruction Pointer IP
 - 1.2.2. Stack Pointer SP
 - 1.2.3. Base Pointer BP
- 1.3. Index registers
 - 1.3.1. Source Index SI
 - 1.3.2. Destination Index DI

2. <u>Control registers</u>

2.1. Instruction Pointer and Flag register

3. <u>Segment registers</u>

- 3.1. Code Segment CS
- 3.2. Data Segment DS
- 3.3. Stack Segment SS
- 3.4. Extra Segment ES



porated by Ordinance No. XXIV of 2002 promulgated by Government of the Punjab)

FACULTY OF INFORMATION TECHNOLOGY

Types of variables

Туре		No. of bits	Example declaration:
Byte		8	Num1: db 43
Word=>	2 bytes	16	Num2: dw 0xABFF
double word=	> 2 words	32	Num3: dd 0xABCDEF56

Note: size of both operands must be same for any type of instruction.


For example:

Mov ax,dh ; is wrong because destination is 2 bytes and source is 1 byte.

Viewing memory in DOSBOX

Areas highlighted in red(memory 1) "m1" and blue (memory 2) "m2" are showing the memory contents. *Note:* Two copies of the same memory is displayed in the given windows.

Area highlighted with yellow is showing the ascii values of the contents displayed in the memory m2.






rporated by Ordinance No. XXIV of 2002 promulgated by Government of the Punjab FACULTY OF INFORMATION TECHNOLOGY

Viewing sample variable in memory.

- To view memory from window m2 run the command "m2 ds: <u>Addressofvariable</u>" example: m2 ds:011F
- A variable with name "num1" is initialized at memory location 11F with value 65 decimal.
 - 41 hex = 65 decimal is the ascii of "A".





proproper by Ordinance No. XXIV of 2002 promulgated by Government of the Punjab)
FACULTY OF INFORMATION TECHNOLOGY

Direct Addressing Mode

Direct

A fixed offset is given in brackets and the memory at that offset is accessed. For example "mov [1234], ax" stores the contents of the AX registers in two bytes starting at address 1234 in the current data segment. The instruction "mov [1234], al" stores the contents of the AL register in the byte at offset 1234.

- Mov ax,[num1] ;reading
- Mov [num2],ax ;writing

Execute every part of Question 1 in *Nasm with Dosbox* and observe the memory variables and register values.

Example 1.

```
; a program to add three numbers using memory variables by direct mode.
  [org 0x0100]
                           ; load first number in ax
 3 mov
        ax, [num1]
                           ; load second number in bx
        bx, [num2]
 4 mov
                           ; accumulate sum in ax
        ax, bx
   add
                           ; load third number in bx
        bx, [num3]
   mov
                           ; accumulate sum in ax
        ax, bx
   add
                           ; store sum in num4
        [num4], ax
   mov
10 mov ax, 0x4c00
                           ; terminate program
11 int 0x21
12
13 num1:dw 5
14 num2:dw 10
15 num3:dw 15
16 num4:dw 0
```



orporated by Ordinance No. XXIV of 2002 promulgated by Government of the Punjab)
FACULTY OF INFORMATION TECHNOLOGY

Example 2

```
1; a program to add three numbers accessed using a single label
2 [org 0x0100]
        ax, [num1]
                           ; load first number in ax
 3 mov
        bx, [num1+2]
                           ; load second number in bx
4 mov
   add ax, bx
                           ; accumulate sum in ax
 6 mov
        bx, [num1+4]
                           ; load third number in bx
7 add ax, bx
                           ; accumulate sum in ax
8 mov [num1+6], ax
                           ; store sum at num1+6
        ax, 0x4c00
                           ; terminate program
 9 mov
10 int 0x21
11
12 num1:dw
13
        dw
             10
14
        dw
            15
15
             0
        dw
```

Example 3

```
; a program to add three numbers using byte variables
 3 [org 0x0100]
 4 mov al, [num1]
                           ; load first number in al
 5 mov bl, [num1+1]
                           ; load second number in bl
   add al, bl
                           ; accumulate sum in al
   mov bl, [num1+2]
                           ; load third number in bl
   add al, bl
                           ; accumulate sum in al
   mov
       [num1+3], al
                           ; store sum at num1+3
10
11 mov ax, 0x4c00
                          ; terminate program
12
   int 0x21
13
                 db 5, 10, 15, 0
14 num1:
```



rporated by Ordinance No. XXIV of 2002 promulgated by Government of the Punjab)
FACULTY OF INFORMATION TECHNOLOGY

Practice Tasks

Write a program to solve the following:

Use Direct addressing mode to access memory variables and the objective of this lab is when we declare the variable of different types how they reserve space in memory:

Note: when we declare variables of same types space reserve in memory side by side therefore we can excess all variables using first one.

Question 1:

Let

Var1=10

Var2=20

Var3=2

Var4=50

Var5=90

Save the sum of these (using **Direct** addressing mode) Five variables (Var1+ Var2+ Var3+ Var4+Var5) in ax and try this question using different data types of variable i.e db,dw,dd.

Question 2:

Declare then variables v1, v2... v10 and add the even no variables v2, v4..v10 using direct Addressing mode using dw type.

Question 3:

Calculate the table of two and save final result in ax.