



Hostman > Tutorials > How to Install and Configure SSH on Ubuntu 22.04

How to Install and Configure SSH on Ubuntu 22.04

= 24.11.2023

(L) Reading time: 5 min

Share

Ubuntu



Hostman Team

Technical writer

SSH is a network protocol that provides a secure connection between a client and a server. All communication is encrypted, preventing theft



We use cookies to improve your browsing experience. By continuing, you agree to our

Privacy Policy®.

Accept cookies





The first thing you need to do before you start installing SSH on Ubuntu is to update all apt packages to the latest versions. To do this, use the following command:

sudo apt update && sudo apt upgrade



Step 2: Install SSH on Ubuntu

OpenSSH is not pre-installed on the system, so let's install it manually. To do this, type in the terminal:

sudo apt install openssh-server



The installation of all the necessary components will begin. Answer "Yes" to all the system prompts.

After the installation is complete, ao to the next step to start the



We use cookies to improve your browsing experience. By continuing, you agree to our Privacy Policy(k).

Accept cookies





On successful startup, you will see the following system message.

The --now key helps you launch the service and simultaneously set it to start when the system boots.

To verify that the service is enabled and running successfully, type:

sudo systemctl status ssh



The output should contain the Active: active (running) line, which indicates that the service is successfully running.

If you want to disable the service, execute:

sudo systemctl disable ssh





We use cookies to improve your browsing experience. By continuing, you agree to our

Privacy Policy(k).

Accept cookies

In our case, we have the UFW installed, so we will use the following



In the output, you should see that SSH traffic is allowed. If you don't have it listed, you need to allow incoming SSH connections. This command will help with this:


sudo ufw allow ssh

Step 5: Connect to the server


Once you complete all the previous steps, you can log into the server using the SSH protocol.

To do this, you will need the server's IP address or domain name and the name of a user created on the server.

In the terminal line, enter the command:







Important: To successfully connect to a remote server, SSH must be installed and configured on the remote server and the user's computer from which you make the connection.

Cloud Servers from 1\$

1 x 3.2 GHz CPU, 1 GB RAM, 25 GB SSD

Get Started

Step 6: Configure SSH

Having completed the previous five steps, you can already connect to the server remotely. However, you can further increase the connection's

coourity by changing the default connection part to another or



We use cookies to improve your browsing experience. By continuing, you agree to our Privacy Policy(k).

Accept cookies






If you get any errors after editing the configuration file, you can restore the original file without problems.

After creating the backup, you can proceed to edit the configuration file. To do this, open it using the nano editor:

sudo nano /etc/ssh/sshd_config



In the file, change the port to a more secure one. It is best to set values from the dynamic range of ports (49152 - 65535) and use different numbers for additional security. For example, let's change the port value to 49532. To do this, we uncomment the corresponding line in the file and change the port as shown in the screenshot below.







In addition to this setting, we recommend changing the password authentication mode to a more secure key authentication mode. To do this, uncomment the corresponding line and make sure the value is "Yes", as shown in the screenshot.

```
# Ciphers and keying
#RekeyLimit default none

# Logging
#SyslogFacility AUTH
#LogLevel INFO

# Authentication:


#LoginGraceTime 2m
#PermitRootLogin prohibit-password
#StrictModes yes
#MaxAuthTries 6
#MaxSessions 10

PubkeyAuthentication yes

# Expect .ssh/authorized_keys2 to be disregarded by default in future.
#AuthorizedKeysFile .ssh/authorized_keys .ssh/authorized_keys2

#AuthorizedPrincipalsFile none
```

Now, let's prohibit logging on to the server as a superuser by changing the corresponding line as shown in the picture below.







security:

- UseDNS checks if the hostname matches its IP address. The value
 "Yes" enables this parameter.
- PermitEmptyPasswords prohibits using empty passwords for authentication if the value is "No."
- MaxAuthTries limits the number of unsuccessful attempts to connect to the server within one communication session.
- AllowUsers and AllowGroups are responsible for the list of users and groups allowed to access the server:
 - # AllowUsers User1, User2, User3 # AllowGroups Group1, Group2, Group3



- Login GraceTime sets the time provided for successful authorization.
 We recommend reducing the value of this parameter by four times.
- ClientAliveInterval limits the time of user inactivity. After



We use cookies to improve your browsing experience. By continuing, you agree to our

Privacy Policy(k).

Accept cookies





If you have changed the port in the configuration file, you should connect using the new port:

ssh -p port_number username@IP_address



Or:

ssh -p port_number_port_username@domain



Conclusion

This article presents a step-by-step guide on installing and configuring SSH in Ubuntu 22.04 and describes how to edit the main configuration file to improve security. We hope this guide helps you to set up a



We use cookies to improve your browsing experience. By continuing, you agree to our

Privacy Policy(k).

Accept cookies

Upuntu



■ Log In Sign Up

firewall

Step 5: Connect to the server

Step 6: Configure SSH

Conclusion

Try Hostman for free

Sign up and get \$100 of credit to try our services for 7 days

Sign Up

Popular content



We use cookies to improve your browsing experience. By continuing, you agree to our Privacy Policy .

Accept cookies





Products Community Company

Sign Up

Cloud Servers Tutorials About

Databases Blog

App Platform Docs

DBaaS FAQ

Cloud Server Hosting

VPS For Rent

HOSTMAN LTD 28 Oktovriou, 367, Mediterranean Court, Floor 1, Office A5, 3107, Limassol, Cyprus Privacy Policy © Terms of Service Service Level Agreement ©



© Hostman 2019-2024. All rights reserved



We use cookies to improve your browsing experience. By continuing, you agree to our

Privacy Policy®.

Accept cookies