
CHAPTER-3

Faraday's Law: States that the induced emf, V_{emf} (volts), in any closed circuit is equal to the time rate of change of magnetic flux linkage by the circuit.

- $V_{emf} = -\frac{d\lambda}{dt} = -N\frac{d\psi}{dt}$ $\lambda = N\psi$ is the flux linkage
- The negative sign shows that the induced voltage acts in such a way as to oppose the flux producing it. This is known as *Lenz's* law
- $\mathbf{E} = \mathbf{E}_e + \mathbf{E}_f$
- \mathbf{E}_f is zero outside the battery and \mathbf{E}_f and \mathbf{E}_e have opposite directions inside the battery

$$\oint_{L} \mathbf{E} \cdot d\mathbf{l} = \oint_{L} \mathbf{E}_{f} \cdot d\mathbf{l} + \oint_{L} \mathbf{E}_{e} \cdot d\mathbf{l} = \int_{N}^{P} \mathbf{E}_{f} \cdot d\mathbf{l}$$

$$V_{emf} = \int_{N}^{P} \mathbf{E}_{f} \cdot d\mathbf{l} = -\int_{N}^{P} \mathbf{E}_{e} \cdot d\mathbf{l} = IR$$




- An electrostatic field cannot maintain a steady current in a closed circuit since $\oint_{I} \mathbf{E}_{e} \cdot d\mathbf{l} = 0 = IR$
- An emf-produced field \mathbf{E}_f is nonconservative.
- Except in electrostatics, voltage and potential difference are usually not equivalent.


Transformer and Motional EMFs

- $V_{emf} = -\frac{d\psi}{dt} = \oint_L \mathbf{E} . d\mathbf{l} = -\frac{d}{dt} \int_S \mathbf{B} . d\mathbf{S}$
- Stationary loop in time-varying B Field (transformer EMF)
- $V_{emf} = \oint_L \mathbf{E} . d\mathbf{l} = -\int_S \frac{\partial \mathbf{B}}{\partial t} . d\mathbf{S}$
- this emf induced by the time-varying current (producing the time-varying B filed) in a stationary loop is referred to as transformer emf.
- Applying Stoke's theorem


$$\oint_{L} \mathbf{E} . d\mathbf{l} = -\int_{S} (\mathbf{\nabla} \times \mathbf{E}) . d\mathbf{S} = -\int_{S} \frac{\partial \mathbf{B}}{\partial t} . d\mathbf{S}$$



- The time-varying E field is not conservative.
- Moving loop in Static B Field (Motional EMF)
- $\mathbf{F}_m = Q\mathbf{u} \times \mathbf{B}$
- Motional electric filed \mathbf{E}_m is $\mathbf{E}_m = \frac{\mathbf{F}_m}{o} = \mathbf{u} \times \mathbf{B}$
- $V_{emf} = \oint_L \mathbf{E} . d\mathbf{l} = \oint_L (\mathbf{u} \times \mathbf{B}) . d\mathbf{l}$



Increasing $\mathbf{B}(t)$



- This emf is said to be motional emf or self-cutting emf. This kind of emf found in electrical machines such as motors, generators, and alternators.
- $\mathbf{F}_m = Q\mathbf{u} \times \mathbf{B}$
- $I = \frac{Q}{t}$
- Q = It
- $\mathbf{F}_m = It(\mathbf{u} \times \mathbf{B}) = I\mathbf{l} \times \mathbf{B}$
- $F_m = IlB$
- $V_{emf} = uBl$
- $\int_{S} (\nabla \times \mathbf{E}_{m}) \cdot d\mathbf{S} = \int_{S} \nabla \times (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{S}$
- $\nabla \times \mathbf{E}_m = \nabla \times (\mathbf{u} \times \mathbf{B})$
- Moving loop in time-varying B Field
- In this case, both transformer and motional emf are present.


$$V_{emf} = \oint_{L} \mathbf{E} \cdot d\mathbf{l} = -\int_{S} \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{S} + \oint_{L} (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l}$$
$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t} + \nabla \times (\mathbf{u} \times \mathbf{B})$$

Displacement Current

- $\nabla \times \mathbf{H} = \mathbf{J}$
- $\nabla \cdot (\nabla \times \mathbf{H}) = \nabla \cdot \mathbf{J} = \mathbf{0}$
- From continuity eqn. $\nabla \cdot \mathbf{J} = -\frac{\partial \rho_v}{\partial t} \neq 0$
- $\nabla \times \mathbf{H} = \mathbf{J} + \mathbf{J}_d$
- $\nabla . J_d = -\nabla . J = \frac{\partial \rho_v}{\partial t} = \nabla . \frac{\partial D}{\partial t}$
- $J_d = \frac{\partial D}{\partial t}$ displacement current density
- $\nabla \times \mathbf{H} = \mathbf{J} + \frac{\partial \mathbf{D}}{\partial t}$ ------ Maxwell's eqn. for time-varying fields


Maxwell's Equations in Final Forms


Differential (Point Form)	Integral Form	Remarks
$\mathbf{\nabla}.\mathbf{D}= ho_v$	$\oint_{S} \mathbf{D}. d\mathbf{S} = \int_{V} \rho_{v} dv$	Gauss's Law
$\nabla \cdot \mathbf{B} = 0$	$\oint_{S} \mathbf{B} . d\mathbf{S} = 0$	Nonexistence of magnetic monopole
$\nabla \times \mathbf{E} = 0$	$\oint_{L} \mathbf{E} . d\mathbf{l} = -\frac{\partial}{\partial t} \int_{S} \mathbf{B} . d\mathbf{S}$	Faraday's Law
$\nabla \times \mathbf{H} = \mathbf{J}$	$\oint_{I} \mathbf{H} \cdot d\mathbf{l} = \int_{S} \left(\mathbf{J} + \frac{\partial \mathbf{D}}{\partial t} \right) \cdot d\mathbf{S}$	Ampere's circuit law




Electric Boundary Conditions:

• Used to determine the fields in a different medium Dielectric (ϵ_{r_1}) – Dielectric (ϵ_{r_2}) :





- $\mathbf{E} = \mathbf{E}_t + \mathbf{E}_n$
- $\mathbf{E}_1 = \mathbf{E}_{1t} + \mathbf{E}_{1n}$ and $\mathbf{E}_2 = \mathbf{E}_{2t} + \mathbf{E}_{2n}$
- $\oint_L \mathbf{E} \cdot d\mathbf{l} = 0$
- $\bullet \ E_{1t} = E_{2t}$
- The tangential components of **E** are the same on the two sides of the boundary.
- $\mathbf{D} = \epsilon \mathbf{E} = \mathbf{D}_t + \mathbf{D}_n$
- $\bullet \ \frac{D_{1t}}{\epsilon_1} = E_{1t} = E_{2t} = \frac{D_{2t}}{\epsilon_2}$
- $\bullet \ D_{1n} D_{2n} = \rho_S$
- If no free charge exists, $\rho_S = 0$, at the interface,
- $\bullet \ \ D_{1n}=D_{2n}$
- The normal components of **D** are continuous across the boundary.
- $\bullet \ \epsilon_1 E_{1n} = \epsilon_2 E_{2n}$
- Refractive index:
- Consider \mathbf{D}_1 or \mathbf{E}_1 and \mathbf{D}_2 or \mathbf{E}_2 making angles θ_1 and θ_2 with the normal to the interface




$$E_1 \sin \theta_1 = E_{1t} = E_{2t} = E_2 \sin \theta_2$$

 $\epsilon_1 E_1 \cos \theta_1 = D_{1n} = D_{2n} = \epsilon_2 E_2 \cos \theta_2$

- $(\tan \theta_1)/\epsilon_1 = (\tan \theta_2)/\epsilon_2$
- $\bullet \ \frac{\tan \theta_1}{\tan \theta_2} = \frac{\epsilon_{r1}}{\epsilon_{r2}}$
- This is the law of refraction of the electric field at a boundary free of charge ($\rho_S = 0$)

Conductor – Dielectric:

- The conductor is assumed to be perfect for which $(\sigma \rightarrow \infty, \rho_C \rightarrow 0)$
- $E_t = 0$ and $D_n = \rho_S$




- Under static conditions, below are the points about a perfect conductor
 - No electric field may exist within a conductor $(\rho_v = 0, \mathbf{E} = 0)$
 - Then can be no potential difference between any two points in the conductor, i.e., a conductor is an equipotential body
 - An electric field is external to the conductor and is normal to its surface

$$D_t = \epsilon_o \epsilon_r E_t = 0$$
, $D_n = \epsilon_o \epsilon_r E_n = \rho_S$

• This concept of $\mathbf{E} = 0$ inside a conductor is applied in electrostatic screening and shielding.


<u>Conductor – Free-space:</u>




• Boundary conditions are the same except that $\epsilon_r = 1$ $D_t = \epsilon_o E_t = 0$, $D_n = \epsilon_o E_n = \rho_S$

Magnetic Boundary Conditions:

- $\oint_{S} \mathbf{B} \cdot d\mathbf{S} = 0$
- $\oint_L \mathbf{H} \cdot d\mathbf{l} = I$





- $\bullet \quad B_{1n}\Delta S B_{2n}\Delta S = 0$
- $\mathbf{B}_{1n} = \mathbf{B}_{2n} \text{ or } \mu_1 \mathbf{H}_{1n} = \mu_2 \mathbf{H}_{2n}$
- The normal components of **D** are continuous whereas the normal components of **H** are discontinuous.
- $H_{1t} H_{2t} = K \frac{B_{1t}}{\mu_1} \frac{B_{2t}}{\mu_2} = K$
- $\mathbf{H}_{1t} = \mathbf{H}_{2t}$ and $\frac{B_{1t}}{\mu_1} = \frac{B_{2t}}{\mu_2}$ when the boundary current free (*K*=0)
- Refractive index:

• Consider \mathbf{B}_1 or \mathbf{H}_1 and \mathbf{B}_2 or \mathbf{H}_2 making angles θ_1 and θ_2 with the normal to the interface

$$B_1 \cos \theta_1 = B_{1n} = B_{2n} = B_2 \cos \theta_2$$

$$\frac{B_1}{\mu_1} \sin \theta_1 = H_{1t} = H_{2t} = \frac{B_2}{\mu_2} \sin \theta_2$$

- $(\tan \theta_1)/\mu_1 = (\tan \theta_2)/\mu_2$
- $\bullet \ \frac{\tan \theta_1}{\tan \theta_2} = \frac{\mu_1}{\mu_2}$
- This is the law of refraction of the electric field at a boundary free of charge (K = 0)