1、新建主服务器实例3308

```
docker run -p 3308:3306 --name mysql-master \
-v /data/docker/mysql-master/log:/var/log/mysql \
-v /data/docker/mysql-master/data:/var/lib/mysql \
-v /data/docker/mysql-master/conf:/etc/mysql \
-e MYSQL_ROOT_PASSWORD=root \
-d mysql:5.7
```

2、进入/data/docker/mysql-master/conf目录下新建my.cnf

```
vim my.cnf
# 主服节点配置
[client]
default_character_set=utf8
[mysqld]
collation_server = utf8_general_ci
character_set_server = utf8
# 设置server_id,同一局域网中需要唯一
server id=101
# 指定不需要同步的数据库名称
binlog-ignore-db=mysql
# 开启二进制日志功能
log-bin=mall-mysql-bin
# 设置二进制日志使用内存大小(事务)
binlog_cache_size=1M
# 设置使用的二进制日志格式 (mixed, statement, row)
binlog format=mixed
# 二进制日志过期清理时间。默认值为0,表示不自动清理。
expire_logs_days=7
# 跳过主从复制中遇到的所有错误或指定类型的错误,避免slave端复制中断。
# 如: 1062错误是指一些主键重复, 1032错误是因为主从数据库数据不一致
slave_skip_errors=1062
```

3、修改完配置后重启master实例

```
docker restart mysql-master
```

4、进入mysql-master容器

```
docker exec -it mysql-master /bin/bash
# 登录mysql
mysql -uroot -proot
```

5、master容器实例内创建数据同步用户

```
CREATE USER 'slave'@'%' IDENTIFIED BY '123456';
GRANT REPLICATION SLAVE, REPLICATION CLIENT ON *.* TO 'slave'@'%';
```

6、新建从服务器

```
docker run -p 3309:3306 --name mysql-slave \
-v /data/docker/mysql-slave/log:/var/log/mysql \
-v /data/docker/mysql-slave/data:/var/lib/mysql \
-v /data/docker/mysql-slave/conf:/etc/mysql \
-e MYSQL_ROOT_PASSWORD=root \
-d mysql:5.7
```

7、进入/data/docker/mysql-slave/conf目录下新建my.cnf

```
vim my.cnf
# 从节点配置
[client]
default_character_set=utf8
[mysqld]
collation_server = utf8_general_ci
character_set_server = utf8
# 设置server id, 同一局域网中需要唯一
server_id=102
# 指定不需要同步的数据库名称
binlog-ignore-db=mysql
# 开启二进制日志功能,以备Slave作为其它数据库实例的Master时使用
log-bin=mall-mysql-slave1-bin
# 设置二进制日志使用内存大小(事务)
binlog cache size=1M
# 设置使用的二进制日志格式 (mixed, statement, row)
binlog format=mixed
# 二进制日志过期清理时间。默认值为0,表示不自动清理。
expire logs days=7
# 跳过主从复制中遇到的所有错误或指定类型的错误,避免slave端复制中断。
# 如: 1062错误是指一些主键重复, 1032错误是因为主从数据库数据不一致
slave skip errors=1062
# relay_log配置中继日志
relay log=mall-mysql-relay-bin
# log_slave_updates表示slave将复制事件写进自己的二进制日志
log_slave_updates=1
# slave设置为只读(具有super权限的用户除外)
read_only=1
```

8、修改完配置后重启slave实例

9、在主数据库中查看主从同步状态

```
docker exec -it mysql-master /bin/bash
mysql -uroot -proot
# 查看主数据库状态以及从哪里开始同步
show master status \G;
```

10、进入mysql-slave容器

```
docker exec -it mysql-slave /bin/bash
mysql -uroot -proot
```

11、在从数据库中配置主从复制

```
# 主从复制配置语句
change master to master_host='宿主机ip', master_user='slave', master_password='123456',
master_port=3308, master_log_file='mall-mysql-bin.000001', master_log_pos=617,
master_connect_retry=30;
```

主从复制参数说明:

master host: 主数据库的IP地址;

master port: 主数据库的运行端口;

master user: 在主数据库创建的用于同步数据的用户账号;

master password: 在主数据库创建的用于同步数据的用户密码;

master log file: 指定从数据库要复制数据的日志文件,通过查看主数据的状态,获取File参数;

master_log_pos: 指定从数据库从哪个位置开始复制数据,通过查看主数据的状态,获取 Position参数:

master connect retry: 连接失败重试的时间间隔,单位为秒。

12、在从数据库中查看主从同步状态

```
show slave status \G;
```

```
mysql> show slave status \G;
                        *** 1. row
              Slave IO State:
                 Master Host: 192.168.0.102
                 Master User: slave
                 Master Port: 3308
               Connect Retry: 30
             Master Log File: mall-mysql-bin.000001
         Read Master Log Pos: 617
              Relay Log File: mall-mysql-relay-bin.000001
               Relay Log Pos: 4
       Relay Master Log File: mall-mysql-bin.000001
            Slave IO Running: No
                                                      没开始
           Slave SOL Running: No
             Replicate Do DB:
         Replicate Ignore DB:
          Replicate Do Table:
      Replicate Ignore Table:
     Replicate Wild Do Table:
 Replicate Wild Ignore Table:
                  Last Errno: 0
                  Last Error:
                Skip Counter: 0
         Exec Master Log Pos: 617
             Relay Log Space: 154
             Until Condition: None
              Until Log File:
               Until Log Pos: 0
```

13、在从数据库中开始主从同步

```
start slave;
```

```
mysql> start slave;
Query OK, 0 rows affected (0.02 sec)
```

14、查看从数据库状态发现已经同步

```
mysql> start slave;
Query OK, 0 rows affected (0.02 sec)
mysql> show slave status \G;
      Slave IO State: Waiting for master to send event
                Master Host: 192.168.0.102
                Master User: slave
                Master Port: 3308
              Connect Retry: 30
            Master Log File: mall-mysql-bin.000001
         Read Master Log Pos: 617
             Relay Log File: mall-mysql-relay-bin.000002
              Relay Log Pos: 325
       Relay Master Log File: mall-mysql-bin.000001
           Slave IO Running: Yes
           Slave SQL Running: Yes
            keplicate no na:
         Replicate Ignore DB:
          Replicate Do Table:
      Replicate Ignore Table:
     Replicate Wild Do Table:
 Replicate Wild Ignore Table:
                 Last Errno: 0
                 Last Error:
               Skip Counter: 0
         Exec Master Log Pos: 617
             Relay Log Space: 537
```

15、主从复制测试

主机新建库-使用库-新建表-插入数据, ok

从机使用库-查看记录, ok