


Dynamical sys.

- To study evolution of "something" in time
System
- Sys. is represented by state
 $X = (X_1, X_2, \dots, X_n) \in \mathcal{X}$
set of all possible values of X
- a) X is discrete e.g. $\{0, 1, 2, \dots\}$
- b) X is continuous e.g. \mathbb{R}^n
- State evolves according to an update law

Discrete-time:

$$X(k+1) = T(X(k))$$

iterated maps

Continuous-time:

$$\dot{X}(t) = f(X(t))$$

ODE

- $\dot{X} = f(X)$ is compact notation for

$$\frac{dX_i}{dt} \leftarrow \begin{bmatrix} \dot{X}_1 \\ \dot{X}_2 \\ \vdots \\ \dot{X}_n \end{bmatrix} = \begin{bmatrix} f_1(X_1, X_2, \dots, X_n) \\ f_2(X_1, X_2, \dots, X_n) \\ \vdots \\ f_n(X_1, X_2, \dots, X_n) \end{bmatrix}$$


we study this

- $f: \mathbb{R}^n \rightarrow \mathbb{R}^n$ is a vector field f (comes from physics / simulation)

- Vector field $f(\cdot)$

is tangent to


the trajectory $X(t)$



- Initial condition

$$\dot{x} = f(x) \quad x(0) = \underline{x_0}$$

- Black box view




- Underlying principle for dyn. sys. :

- Future of the sys. only depends on current state
- $x(t)$ for $t \geq T$ only depends on $x(T)$
- Therefore, state encapsulate memory of the sys.
- This is called Markov property for Stochastic sys.

- Example: Pendulum

Q: what is the state?

Q: what is the dyn?



Newton's law: $I\ddot{\theta} = \text{torque}$

(gravity)

Inertia: $I = mL^2$

torque from gravity: $-mgL\sin\theta$

torque from friction: $-\mu L^2\dot{\theta}$ ($v = L\dot{\theta}$)

$$\Rightarrow mL^2\ddot{\theta} = -mgL\sin\theta - \mu L^2\dot{\theta}$$

$$\Rightarrow \ddot{\theta} = -\frac{g}{L}\sin\theta - \underbrace{\frac{\mu}{m}}_{\gamma}\dot{\theta}$$


state $X = (X_1, X_2) = (\theta, \dot{\theta})$

$$\Rightarrow \dot{X}_1 = \dot{\theta} = X_2$$

$$\dot{X}_2 = \ddot{\theta} = -\frac{g}{L}\sin(X_1) - \gamma X_2$$

$$\Rightarrow \begin{bmatrix} \dot{x}_1 \\ \dot{x}_2 \end{bmatrix} = \begin{bmatrix} f_1(x_1, x_2) \\ f_2(x_1, x_2) \end{bmatrix} = \begin{bmatrix} x_2 \\ -\frac{g}{L} \sin(x_1) - \gamma x_2 \end{bmatrix}$$

- Equilibrium point.



- Example: Pendulum


$$f_1(x_1, x_2) = 0 \Rightarrow x_2 = 0$$

$$f_2(x_1, x_2) = 0 \Leftrightarrow \sin(x_1) = 0 \Rightarrow x_1 = n\pi$$

for integer n

there are only two physically
distinguishable solution

$$x_1 = 0 \text{ or } x_1 = \pi$$



Controlled Dynamical System:

- Dyn. sys. driven by control input



$$\dot{x} = f(x, u), \quad x(0) = x_0$$

- $u = (u_1, u_2, \dots, u_p) \in \mathbb{R}^P$ is the control input
- Output signal or observation

$$y = h(x, u)$$

e.g. IMU sensors

- Black-box or input-output viewpoint



Outline of the class

Part I: $\dot{x} = f(x)$
(up to midterm)

fundamental of ODE
stability, ...

Part II: $\dot{x} = f(x, u)$ control design
 $y = h(x, u)$

Main tools: Lyapunov function. method

- We do not study time-varying systems
- time varying sys. can be reduced to time invariant

$$\dot{x} = f(x, t)$$

define new state $x_{n+1} = t$, with dyn. $\dot{x}_{n+1} = 1$

Review of linear sys.

$$\dot{\mathbf{x}} = \mathbf{A}\mathbf{x}, \quad \mathbf{x}(0) = \mathbf{x}_0$$

- \mathbf{A} is a $n \times n$ matrix
- Solution is explicitly known

$$\mathbf{x}(t) = e^{t\mathbf{A}} \mathbf{x}_0$$

- \mathbf{x}^* is eq/b point.
- Behavior of linear sys. depends on spectrum of \mathbf{A} .
- Why are linear sys. called linear?

if

$$\mathbf{x}'(0) \rightarrow \boxed{\dot{\mathbf{x}} = \mathbf{A}\mathbf{x}} \rightarrow \mathbf{x}'(t)$$

$$\mathbf{x}^2(0) \rightarrow \boxed{\dot{\mathbf{x}} = \mathbf{A}\mathbf{x}} \rightarrow \mathbf{x}^2(t)$$

then

$$a \mathbf{x}'(0) + b \mathbf{x}^2(0) \rightarrow \boxed{\dot{\mathbf{x}} = \mathbf{A}\mathbf{x}} \rightarrow a \mathbf{x}'(t) + b \mathbf{x}^2(t)$$

superposition

- linear sys. with control input

$$\dot{\hat{X}} = \hat{A}\hat{X} + \hat{B}\hat{u}, \quad \hat{X}_0 = \underline{0}$$

$$\hat{Y} = \hat{C}\hat{X} + \hat{D}\hat{u}$$

usual
assumption

- Input-output relationship is characterized by transfer function

$$\text{Laplace-transform: } X(t) \rightarrow \hat{X}(s) = \int_0^{\infty} e^{-st} x(t) dt$$

$$\Rightarrow s\hat{X}(s) = \hat{A}\hat{X}(s) + \hat{B}\hat{u}(s)$$

$$\hat{Y}(s) = \hat{C}\hat{X}(s) + \hat{D}\hat{u}(s)$$

$$\Rightarrow \hat{X}(s) = (sI - A)^{-1} \hat{B}\hat{u}(s)$$



$$\Rightarrow \hat{Y}(s) = [C(sI - A)^{-1} \hat{B} + D] \hat{u}(s)$$

$$G(s)$$


transfer function

- Superposition holds

if



Then



- When superposition does not hold \rightarrow Non linear

- Results in interesting phenomena.

① Multiple eq/b. points




We saw this in Pendulum example

② Finite-time blow-up

a) linear sys. Can not go to ∞ in finite-time

e.g. $X \in \mathbb{R}$, $\dot{X} = aX$ for $a > 0$



It is always
finite even for
very large a

b) example of nonlinear sys.


Finite time
blow up?

$$\dot{X} = X^2 \Rightarrow \frac{dX}{dt} = X^2 \Rightarrow \frac{dX}{X^2} = dt$$

$$\Rightarrow \int_{X(0)}^{X(t)} \frac{dX}{X^2} = \int_0^T dt$$

$$\Rightarrow -\frac{1}{X(T)} + \frac{1}{X(0)} = T$$

$$\Rightarrow X(T) = \frac{X(0)}{1 - TX(0)}$$



(3)

Sub/super harmonic oscillations


- For linear sys. if input has freq. ω then the output has the same freq:

$$U(t) = \cos(\omega t) \implies Y(t) = A \cos(\omega t + \phi)$$

↓ ↗
 Bode plots

- Not true for nonlinear sys.
- Example: Pumping up a swing

Consider the Pendulum, but length
can be controlled.




$$L(t) = L_0 (1 + \sum u(t))$$


control input

$$\begin{bmatrix} \dot{x}_1 \\ \dot{x}_2 \end{bmatrix} = \begin{bmatrix} x_2 \\ \frac{\theta}{L_0(1 + \sum u(t))} \sin(x_1) - \gamma x_2 \end{bmatrix}$$

a) $U(t) \geq 0$



b) $U(t) = \cos(2\sqrt{\frac{g}{L_0}} t)$



Ref: Pumping a swing, by Piccoli & Kulkarni, CSM

Related to Mathieu eq.

Other nonlinear phenomena:

- limit cycles
- Bifurcation
- Chaos



important, but not in the scope of this class

Read Ch. 1