

PDF

Cluster Setup

- <u>Purpose</u>
- Prerequisites
- Installation
- Configuration
 - o Configuration Files
 - Site Configuration
 - Configuring the Environment of the Hadoop Daemons
 - Configuring the Hadoop Daemons
 - Memory monitoring
 - Slaves
 - Logging
- Cluster Restartability
 - MapReduce
- Hadoop Rack Awareness
- <u>Hadoop Startup</u>
- Hadoop Shutdown

Purpose

This document describes how to install, configure and manage non-trivial Hadoop clusters ranging from a few nodes to extremely large clusters with thousands of nodes.

To play with Hadoop, you may first want to install Hadoop on a single machine (see Single Node Setup).

Prerequisites

- 1. Make sure all required software is installed on all nodes in your cluster.
- 2. Download the Hadoop software.

Installation

Installing a Hadoop cluster typically involves unpacking the software on all the machines in the cluster.

Typically one machine in the cluster is designated as the NameNode and another machine the as JobTracker, exclusively. These are the *masters*. The rest of the machines in the cluster act as both DataNode *and* TaskTracker. These are the *slaves*.

The root of the distribution is referred to as HAD00P_HOME. All machines in the cluster usually have the same HAD00P_HOME path.

Configuration

The following sections describe how to configure a Hadoop cluster.

Configuration Files

Hadoop configuration is driven by two types of important configuration files:

- 1. Read-only default configuration src/hdfs/hdfs-default.xml and src/mapred/mapred-default.xml.
- 2. Site-specific configuration conf/core-site.xml, conf/hdfs-site.xml and conf/mapred-site.xml.

To learn more about how the Hadoop framework is controlled by these configuration files, look here.

Additionally, you can control the Hadoop scripts found in the bin/directory of the distribution, by setting site-specific values via the conf/hadoop-env.sh.

Site Configuration

To configure the Hadoop cluster you will need to configure the environment in which the Hadoop daemons execute as well as the configuration parameters for the Hadoop daemons.

The Hadoop daemons are NameNode/DataNode and JobTracker/TaskTracker.

Configuring the Environment of the Hadoop Daemons

Administrators should use the Conf/hadoop - env . Sh script to do site-specific customization of the Hadoop daemons' process environment.

At the very least you should specify the JAVA_HOME so that it is correctly defined on each remote node.

In most cases you should also specify HADOOP_PID_DIR to point a directory that can only be written to by the users that are going to run the hadoop daemons. Otherwise there is the potential for a symlink attack.

Administrators can configure individual daemons using the configuration options HAD00P_*_0PTS. Various options available are shown below in the table.

> **Configure Options** Daemon

NameNode HADOOP_NAMENODE_OPTS DataNode HADOOP_DATANODE_OPTS

HADOOP_SECONDARYNAMENODE_OPTS SecondaryNamenode

JobTracker HADOOP_JOBTRACKER_OPTS TaskTracker HADOOP TASKTRACKER OPTS

For example, To configure Namenode to use parallelGC, the following statement should be added in hadoop-env. Sh: export HADOOP_NAMENODE_OPTS="-XX:+UseParallelGC \${HADOOP_NAMENODE_OPTS}"

Other useful configuration parameters that you can customize include:

- HADOOP_LOG_DIR The directory where the daemons' log files are stored. They are automatically created if they don't exist.
- HADOOP_HEAPSIZE The maximum amount of heapsize to use, in MB e.g. 1000MB. This is used to configure the heap size for the hadoop daemon. By default, the value is 1000MB.

Configuring the Hadoop Daemons

This section deals with important parameters to be specified in the following: conf/core-site.xml:

Value Notes Parameter URI of NameNode.

conf/hdfs-site.xml:

fs.default.name

Parameter Value Notes

hdfs://hostname/

dfs.name.dirPath on the local filesystem where the NameNode stores If this is a comma-delimited list of directories then the name table

 $the \ name space \ and \ transactions \ logs \ persistently. \\ \hspace{2.5cm} is \ replicated \ in \ all \ of \ the \ directories, for \ redundancy.$

dfs.data.dir Comma separated list of paths on the local filesystem of a If this is a comma-delimited list of directories, then data will be DataNode where it should store its blocks. stored in all named directories, typically on different devices.

conf/mapred-site.xml:

Parameter	Value	Notes
mapred.job.tracker	Host or IP and port of JobTracker.	host:port pair.
mapred.system.dir	Path on the HDFS where where the MapReduce framework stores system files e.g. /hadoop/mapred /system/.	This is in the default filesystem (HDFS) and must be accessible from both the server and client machines.
mapred.local.dir	Comma-separated list of paths on the local filesystem where temporary MapReduce data is written.	Multiple paths help spread disk i/o.
mapred.tasktracker. {map reduce}.tasks.maximum	The maximum number of MapReduce tasks, which are run simultaneously on a given TaskTracker, individually.	Defaults to 2 (2 maps and 2 reduces), but vary it depending on your hardware.
dfs.hosts/dfs.hosts.exclude	List of permitted/excluded DataNodes.	If necessary, use these files to control the list of allowable datanodes.
mapred.hosts/mapred.hosts.exclude	List of permitted/excluded TaskTrackers.	If necessary, use these files to control the list of allowable TaskTrackers.
mapred.queue.names	Comma separated list of queues to which jobs can be submitted.	The MapReduce system always supports atleast one queue with the name as <code>default</code> . Hence, this parameter's value should always contain the string <code>default</code> . Some job schedulers supported in Hadoop, like the <code>Capacity Scheduler</code> , support multiple queues. If such a scheduler is being used, the list of configured queue names must be specified here. Once queues are defined, users can submit jobs to a queue using the property name <code>mapred.job.queue.name</code> in the job configuration. There could be a separate configuration file for configuring properties of these queues that is managed by the scheduler. Refer to the documentation of the scheduler for information on the same.
mapred.acls.enabled	Boolean, specifying whether checks for queue ACLs and job ACLs are to be done for authorizing users for doing queue operations and job operations.	If true, queue ACLs are checked while submitting and administering jobs and job ACLs are checked for authorizing view and modification of jobs. Queue ACLs are specified using the configuration parameters of the form mapred.queue.queue-name.acl-name, defined below under mapred-queue-acls.xml. Job ACLs are described at Job Authorization

conf/mapred-queue-acls.xml

Parameter	Value	Notes
mapred.queue.queue-	List of users and groups that can	The list of users and groups are both comma separated list of names. The
name.acl-submit-job	submit jobs to the specified	two lists are separated by a blank. Example: user1,user2 group1,group2. If you
	queue-name.	wish to define only a list of groups, provide a blank at the beginning of the
		value.
mapred.queue.queue-	List of users and groups that can	The list of users and groups are both comma separated list of names. The
name.acl-administer-jobs	view job details, change the	two lists are separated by a blank. Example: user1,user2 group1,group2. If you
	priority or kill jobs that have been	wish to define only a list of groups, provide a blank at the beginning of the
	submitted to the specified	value. Note that the owner of a job can always change the priority or kill

queue-name.

his/her own job, irrespective of the ACLs.

Typically all the above parameters are marked as final to ensure that they cannot be overriden by user-applications.

Real-World Cluster Configurations

This section lists some non-default configuration parameters which have been used to run the sort benchmark on very large clusters.

• Some non-default configuration values used to run sort900, that is 9TB of data sorted on a cluster with 900 nodes:

Configuration Parameter	Value	Notes	
File			
conf/hdfs-site.xml dfs.block.size	134217728	B HDFS blocksize of 128MB for large file-systems.	
conf/hdfs-site.xml dfs.namenode.handler.	count 40	More NameNode server threads to handle RPCs from large number of	
		DataNodes.	
conf/mapred- mapred.reduce.parallel	.copies 20	Higher number of parallel copies run by reduces to fetch outputs from	
site.xml		very large number of maps.	
conf/mapred- mapred.map.child.java	.opts -Xmx512l	MLarger heap-size for child jvms of maps.	
site.xml			
conf/mapred- mapred.reduce.child.java.opts-Xmx51		MLarger heap-size for child jvms of reduces.	
site.xml			
conf/core-site.xml fs.inmemory.size.mb	200	Larger amount of memory allocated for the in-memory file-system	
		used to merge map-outputs at the reduces.	
conf/core-site.xml io.sort.factor	100	More streams merged at once while sorting files.	
conf/core-site.xml io.sort.mb	200	Higher memory-limit while sorting data.	
conf/core-site.xml io.file.buffer.size	131072	Size of read/write buffer used in SequenceFiles.	

• Updates to some configuration values to run sort1400 and sort2000, that is 14TB of data sorted on 1400 nodes and 20TB of data sorted on 2000 nodes:

Configuration	Parameter	Value	Notes
File			
conf/mapred- site.xml	mapred.job.tracker.handler.coun	t60	$\label{thm:continuous} More\ Job Tracker\ server\ threads\ to\ handle\ RPCs\ from\ large\ number\ of\ Task Trackers.$
conf/mapred- site.xml	mapred.reduce.parallel.copies	50	
conf/mapred- site.xml	tasktracker.http.threads	50	More worker threads for the TaskTracker's http server. The http server is used by reduces to fetch intermediate map-outputs.
conf/mapred- site.xml	mapred.map.child.java.opts	-Xmx512M	Larger heap-size for child jvms of maps.
conf/mapred- site.xml	mapred.reduce.child.java.opts	-Xmx1024N	ILarger heap-size for child jvms of reduces.

Task Controllers

Task controllers are classes in the Hadoop MapReduce framework that define how user's map and reduce tasks are launched and controlled. They can be used in clusters that require some customization in the process of launching or controlling the user tasks. For example, in some clusters, there may be a requirement to run tasks as the user who submitted the job, instead of as the task tracker user, which is how tasks are launched by default. This section describes how to configure and use task controllers.

The following task controllers are the available in Hadoop.

Name	Class Name	Description
------	------------	-------------

DefaultTaskControllerorg.apache.hadoop.mapred.DefaultTaskControllerThe default task controller which Hadoop uses to manage task execution. The tasks run as the task tracker user.

LinuxTaskController org.apache.hadoop.mapred.LinuxTaskController This task controller, which is supported only on Linux, runs the tasks as the user who submitted the job. It requires these user accounts to be created on the cluster nodes where the tasks are launched. It uses a setuid executable that is included in the Hadoop distribution. The task tracker uses this executable to launch and kill tasks. The setuid executable switches to the user who has submitted the job and launches or kills the tasks. For

maximum security, this task controller sets up restricted permissions and user/group ownership of local files and directories used by the tasks such as the job jar files, intermediate files, task log files and distributed cache files. Particularly note that, because of this, except the job owner and tasktracker, no other user can access any of the local files/directories including those localized as part of the distributed cache.

Configuring Task Controllers

The task controller to be used can be configured by setting the value of the following key in mapred-site.xml

Property	Value	Notes
mapred.task.tracker.task-	Fully qualified class	Currently there are two implementations of task controller in the Hadoop system,
controller	name of the task	DefaultTaskController and LinuxTaskController. Refer to the class names mentioned
	controller class	above to determine the value to set for the class of choice.

Using the LinuxTaskController

This section of the document describes the steps required to use the LinuxTaskController.

In order to use the LinuxTaskController, a setuid executable should be built and deployed on the compute nodes. The executable is named task-controller. To build the executable, execute ant task-controller -Dhadoop.conf.dir=/path/to/conf/dir. The path passed in -Dhadoop.conf.dir should be the path on the cluster nodes where a configuration file for the setuid executable would be located. The executable would be built to build.dir/bin and should be installed to \$HADOOP_HOME/bin.

The executable must have specific permissions as follows. The executable should have 6050 or --Sr-s--- permissions user-owned by root(super-user) and group-owned by a special group of which the TaskTracker's user is the group member and no job submitter is. If any job submitter belongs to this special group, security will be compromised. This special group name should be specified for the configuration property "mapreduce.tasktracker.group" in both mapred-site.xml and task-controller.cfg. For example, let's say that the TaskTracker is run as user mapred who is part of the groups users and specialGroup any of them being the primary group. Let also be that users has both mapred and another user (job submitter) X as its members, and X does not belong to specialGroup. Going by the above description, the setuid/setgid executable should be set 6050 or --Sr-s--- with user-owner as mapred and group-owner as specialGroup which has mapred as its member(and not users which has X also as its member besides mapred).

The LinuxTaskController requires that paths including and leading up to the directories specified in *mapred.local.dir* and *hadoop.log.dir* to be set 755 permissions.

task-controller.cfg

The executable requires a configuration file called *taskcontroller.cfg* to be present in the configuration directory passed to the ant target mentioned above. If the binary was not built with a specific conf directory, the path defaults to */path-to-binary/../conf*. The configuration file must be owned by root, group-owned by anyone and should have the permissions *0400 or r------*.

The executable requires following configuration items to be present in the *taskcontroller.cfg* file. The items should be mentioned as simple *key=value* pairs.

Name	Description	
hadoop.log.dir	Path to hadoop log directory. Should be same as the value which the TaskTracker is started with. This is	
required to set proper permissions on the log files so that they can be written to by the user's tasl		
by the TaskTracker for serving on the web UI.		
mapreduce.tasktracker.groupGroup to which the TaskTracker belongs. The group owner of the taskcontroller binary should be this		

ice.tasktracker.group Group to which the TaskTracker belongs. The group owner of the taskcontroller binary should be this group. Should be same as the value with which the TaskTracker is configured. This configuration is required for validating the secure access of the task-controller binary.

Monitoring Health of TaskTracker Nodes

Hadoop MapReduce provides a mechanism by which administrators can configure the TaskTracker to run an administrator supplied script periodically to determine if a node is healthy or not. Administrators can determine if the node is in a healthy state by performing any checks of their choice in the script. If the script detects the node to be in an unhealthy state, it must print a line to standard output beginning with the string *ERROR*. The TaskTracker spawns the script periodically and checks its output. If the script's output contains the string *ERROR*, as described above, the node's status is reported as 'unhealthy' and the node is black-listed on the JobTracker. No further tasks will be assigned to this node. However, the TaskTracker continues to run the script, so that if the node becomes healthy again, it will be removed from the blacklisted nodes on the JobTracker automatically. The node's health along with the output of the script, if it is unhealthy, is available to the administrator in the JobTracker's web interface. The time since the node was healthy is also displayed on the web interface.

Configuring the Node Health Check Script

The following parameters can be used to control the node health monitoring script in mapred-site.xml.

Name	Description
mapred.healthChecker.script.path	Absolute path to the script which is periodically run by the TaskTracker to
	determine if the node is healthy or not. The file should be executable by the
	TaskTracker. If the value of this key is empty or the file does not exist or is not
	executable, node health monitoring is not started.
mapred.healthChecker.interval	Frequency at which the node health script is run, in milliseconds
mapred.healthChecker.script.timeou	[†] Time after which the node health script will be killed by the TaskTracker if
	unresponsive. The node is marked unhealthy. if node health script times out.
mapred.healthChecker.script.args	Extra arguments that can be passed to the node health script when launched. These
	should be comma separated list of arguments.

Memory monitoring

A TaskTracker(TT) can be configured to monitor memory usage of tasks it spawns, so that badly-behaved jobs do not bring down a machine due to excess memory consumption. With monitoring enabled, every task is assigned a task-limit for virtual memory (VMEM). In addition, every node is assigned a node-limit for VMEM usage. A TT ensures that a task is killed if it, and its descendants, use VMEM over the task's per-task limit. It also ensures that one or more tasks are killed if the sum total of VMEM usage by all tasks, and their descendants, cross the node-limit.

Users can, optionally, specify the VMEM task-limit per job. If no such limit is provided, a default limit is used. A node-limit can be set per node.

Currently the memory monitoring and management is only supported in Linux platform.

To enable monitoring for a TT, the following parameters all need to be set:

Name	Туре	Description
mapred.cluster.map.memory.mb,	long	The size, in terms of virtual memory, of a single map/reduce slot in the
mapred.cluster.reduce.memory.mb		Map-Reduce framework, used by the scheduler. A job can ask for multiple slots for a single task via
		mapred.job.map.memory.mb/mapred.job.reduce.memory.mb, up to the limit specified by
		mapred.cluster.max.map.memory.mb/mapred.cluster.max.reduce.memory.mb,
		if the scheduler supports the feature. The value of -1 indicates that this feature is turned off.
<pre>mapred.job.map.memory.mb, mapred.job.reduce.memory.mb</pre>	long	A number, in bytes, that represents the default VMEM task-limit associated with a map/reduce task. Unless overridden by a job's setting, this number defines the VMEM task-limit. These properties replace the old deprecated property, mapred.task.default.maxvmem.
<pre>mapred.cluster.max.map.memory.mb, mapred.cluster.max.reduce.memory.ml</pre>		A number, in bytes, that represents the upper VMEM task-limit associated with a map/reduce task. Users, when specifying a VMEM task-limit for their tasks, should not specify a limit which exceeds this amount. These properties replace the old deprecated property, mapred.task.limit.maxvmem.

In addition, the following parameters can also be configured.

Name	Type	Description
mapred.tasktracker.taskmemorymanager.monitoring-	long The time interval, in milliseconds, between whi	
interval	TT checl	ks for any memory violation. The default value
	is 5000 n	nsec (5 seconds).

Here's how the memory monitoring works for a TT.

- 1. If one or more of the configuration parameters described above are missing or -1 is specified , memory monitoring is disabled for the TT.
- 2. Periodically, the TT checks the following:
 - If any task's current VMEM usage is greater than that task's VMEM task-limit, the task is killed and reason for killing the task is logged in task diagonistics. Such a task is considered failed, i.e., the killing counts towards the task's failure count.

• If the sum total of VMEM used by all tasks and descendants is greater than the node-limit, the TT kills enough tasks, in the order of least progress made, till the overall VMEM usage falls below the node-limit. Such killed tasks are not considered failed and their killing does not count towards the tasks' failure counts.

Schedulers can choose to ease the monitoring pressure on the TT by preventing too many tasks from running on a node and by scheduling tasks only if the TT has enough VMEM free. In addition, Schedulers may choose to consider the physical memory (RAM) available on the node as well. To enable Scheduler support, TTs report their memory settings to the JobTracker in every heartbeat.

A TT reports the following memory-related numbers in every heartbeat:

- The total VMEM available on the node.
- The remaining VMEM available on the node.
- The total RAM available on the node.
- The remaining RAM available on the node.

Slaves

Typically you choose one machine in the cluster to act as the NameNode and one machine as to act as the JobTracker, exclusively. The rest of the machines act as both a DataNode and TaskTracker and are referred to as *slaves*.

List all slave hostnames or IP addresses in your conf/slaves file, one per line.

Logging

Hadoop uses the <u>Apache log4j</u> via the <u>Apache Commons Logging</u> framework for logging. Edit the <code>conf/log4j.properties</code> file to customize the Hadoop daemons' logging configuration (log-formats and so on). Edit conf/task-log4j.properties file to customize the logging configuration for MapReduce tasks.

History Logging

The job history files are stored in central location <code>hadoop.job.history.location</code> which can be on DFS also, whose default value is <code>\${HADOOP_LOG_DIR}/history</code>. The history web UI is accessible from job tracker web UI.

The history files are also logged to user specified directory hadoop.job.history.user.location which defaults to job output directory. The files are stored in "_logs/history/" in the specified directory. Hence, by default they will be in "mapred.output.dir/_logs/history/". User can stop logging by giving the value none for hadoop.job.history.user.location

User can view the history logs summary in specified directory using the following command

\$ bin/hadoop job -history output-dir

This command will print job details, failed and killed tip details.

More details about the job such as successful tasks and task attempts made for each task can be viewed using the following command \$bin/hadoop job -history all output-dir

Once all the necessary configuration is complete, distribute the files to the HADOOP_CONF_DIR directory on all the machines, typically \${HADOOP_HOME}/conf.

Cluster Restartability

MapReduce

The job tracker restart can recover running jobs if mapred.jobtracker.restart.recover is set true and <u>lobHistory logging</u> is enabled. Also mapred.jobtracker.job.history.block.size value should be set to an optimal value to dump job history to disk as soon as possible, the typical value is 3145728(3MB).

Hadoop Rack Awareness

The HDFS and the Map/Reduce components are rack-aware.

The NameNode and the JobTracker obtains the rack id of the slaves in the cluster by invoking an API resolve in an administrator configured module. The API resolves the slave's DNS name (also IP address) to a rack id. What module to use can be configured using the configuration item topology.node.switch.mapping.impl. The default implementation of the same runs a script/command configured using topology.script.file.name. If topology.script.file.name is not set, the rack id /default-rack is returned for any passed IP address. The additional configuration in the Map/Reduce part is mapred.cache.task.levels which determines the number of levels (in the network topology) of caches. So, for example, if it is the default value of 2, two levels of caches will be

constructed - one for hosts (host -> task mapping) and another for racks (rack -> task mapping).

Hadoop Startup

To start a Hadoop cluster you will need to start both the HDFS and Map/Reduce cluster.

Format a new distributed filesystem:

\$ bin/hadoop namenode -format

Start the HDFS with the following command, run on the designated ${\tt NameNode}$:

\$ bin/start-dfs.sh

The bin/start-dfs.sh script also consults the \${HADOOP_CONF_DIR}/slaves file on the NameNode and starts the DataNode daemon on all the listed slaves.

Start Map-Reduce with the following command, run on the designated JobTracker:

\$ bin/start-mapred.sh

The bin/start-mapred.Sh script also consults the \${HADOOP_CONF_DIR}/slaves file on the JobTracker and starts the TaskTracker daemon on all the listed slaves.

Hadoop Shutdown

Stop HDFS with the following command, run on the designated NameNode:

\$ bin/stop-dfs.sh

The bin/stop-dfs.sh script also consults the $\{HADOOP_CONF_DIR\}/slaves$ file on the NameNode and stops the DataNode daemon on all the listed slaves.

\$ bin/stop-mapred.sh

The bin/stop-mapred.sh script also consults the \${HADOOP_CONF_DIR}/slaves file on the JobTracker and stops the TaskTracker daemon on all the listed slaves.

Last Published: 08/04/2013 13:43:21

Copyright © 2008 The Apache Software Foundation.