

NAME

Pod::Html - module to convert pod files to HTML

SYNOPSIS

```
use Pod::Html;
pod2html([options]);
```

DESCRIPTION

Converts files from pod format (see *perlpod*) to HTML format. It can automatically generate indexes and cross-references, and it keeps a cache of things it knows how to cross-reference.

FUNCTIONS

pod2html

```
pod2html("pod2html",
    "--podpath=lib:ext:pod:vms",
    "--podroot=/usr/src/perl",
    "--htmlroot=/perl/nmanual",
    "--recurse",
    "--infile=foo.pod",
    "--outfile=/perl/nmanual/foo.html");
```

pod2html takes the following arguments:

backlink

```
--backlink
```

Turns every head1 heading into a link back to the top of the page. By default, no backlinks are generated.

cachedir

```
--cachedir=name
```

Creates the directory cache in the given directory.

CSS

```
--css=stylesheet
```

Specify the URL of a cascading style sheet. Also disables all HTML/CSS style attributes that are output by default (to avoid conflicts).

flush

```
--flush
```

Flushes the directory cache.

header

```
--header
--noheader
```

Creates header and footer blocks containing the text of the NAME section. By default, no headers are generated.

help

--help



Displays the usage message.

htmldir

```
--htmldir=name
```

Sets the directory to which all cross references in the resulting html file will be relative. Not passing this causes all links to be absolute since this is the value that tells Pod::Html the root of the documentation tree.

Do not use this and --htmlroot in the same call to pod2html; they are mutually exclusive.

htmlroot

```
--htmlroot=name
```

Sets the base URL for the HTML files. When cross-references are made, the HTML root is prepended to the URL.

Do not use this if relative links are desired: use --htmldir instead.

Do not pass both this and --htmldir to pod2html; they are mutually exclusive.

index

```
--index
--noindex
```

Generate an index at the top of the HTML file. This is the default behaviour.

infile

```
--infile=name
```

Specify the pod file to convert. Input is taken from STDIN if no infile is specified.

outfile

```
--outfile=name
```

Specify the HTML file to create. Output goes to STDOUT if no outfile is specified.

poderrors

```
--poderrors
--nopoderrors
```

Include a "POD ERRORS" section in the outfile if there were any POD errors in the infile. This section is included by default.

podpath

```
--podpath=name:...:name
```

Specify which subdirectories of the podroot contain pod files whose HTML converted forms can be linked to in cross references.

podroot

```
--podroot=name
```

Specify the base directory for finding library pods. Default is the current working directory.

quiet

```
--quiet
```

--noquiet



Don't display *mostly harmless* warning messages. These messages will be displayed by default. But this is not the same as verbose mode.

recurse

```
--recurse
```

Recurse into subdirectories specified in podpath (default behaviour).

title

```
--title=title
```

Specify the title of the resulting HTML file.

verbose

```
--verbose
--noverbose
```

Display progress messages. By default, they won't be displayed.

htmlify

```
htmlify($heading);
```

Converts a pod section specification to a suitable section specification for HTML. Note that we keep spaces and special characters except ",? (Netscape problem) and the hyphen (writer's problem...).

anchorify

```
anchorify(@heading);
```

Similar to htmlify(), but turns non-alphanumerics into underscores. Note that anchorify() is not exported by default.

ENVIRONMENT

Uses \$Config{pod2html} to setup default options.

AUTHOR

Marc Green, <marcgreen@cpan.org>.

Original version by Tom Christiansen, <tchrist@perl.com>.

SEE ALSO

perlpod

COPYRIGHT

This program is distributed under the Artistic License.