
Chapter 9

Subprograms



### Chapter 9 Topics

- Introduction
- Fundamentals of Subprograms
- Design Issues for Subprograms
- Local Referencing Environments
- Parameter-Passing Methods
- Parameters That Are Subprograms
- Overloaded Subprograms
- Generic Subprograms
- Design Issues for Functions
- User–Defined Overloaded Operators
- Coroutines

#### Introduction

- Two fundamental abstraction facilities
  - Process abstraction
    - Emphasized from early days
  - Data abstraction
    - Emphasized in the 1980s

### Fundamentals of Subprograms

- Each subprogram has a single entry point
- The calling program is suspended during execution of the called subprogram
- Control always returns to the caller when the called subprogram's execution terminates

#### **Basic Definitions**

- A *subprogram definition* describes the interface to and the actions of the subprogram abstraction
  - In Python, function definitions are executable; in all other languages, they are non-executable
- A subprogram call is an explicit request that the subprogram be executed
- A subprogram header is the first part of the definition, including the name, the kind of subprogram, and the formal parameters
- The parameter profile (aka signature) of a subprogram is the number, order, and types of its parameters
- The protocol is a subprogram's parameter profile and, if it is a function, its return type

#### Basic Definitions (continued)

- Function declarations in C and C++ are often called prototypes
- A subprogram declaration provides the protocol, but not the body, of the subprogram
- A formal parameter is a dummy variable listed in the subprogram header and used in the subprogram
- An actual parameter represents a value or address used in the subprogram call statement

# Actual/Formal Parameter Correspondence

#### Positional

- The binding of actual parameters to formal parameters is by position: the first actual parameter is bound to the first formal parameter and so forth
- Safe and effective

#### Keyword

- The name of the formal parameter to which an actual parameter is to be bound is specified with the actual parameter
- Advantage: Parameters can appear in any order, thereby avoiding parameter correspondence errors
- Disadvantage: User must know the formal parameter's names

#### Formal Parameter Default Values

- In certain languages (e.g., C++, Python, Ruby, Ada, PHP), formal parameters can have default values (if no actual parameter is passed)
  - In C++, default parameters must appear last because parameters are positionally associated
- Variable numbers of parameters
  - C# methods can accept a variable number of parameters as long as they are of the same type—the corresponding formal parameter is an array preceded by params
  - Ruby and Python also support variable numbers of parameters. In Ruby, the actual parameters are sent as elements of a hash literal and the corresponding formal parameter is preceded by an asterisk.
  - In Python, the actual is a list of values and the corresponding formal parameter is a name with an asterisk

### Ruby Blocks

- Ruby includes a number of iterator functions, which are often used to process the elements of arrays
- Iterators are implemented with blocks, which can also be defined by applications
- Blocks are attached methods calls; they can have parameters (in vertical bars); they are executed when the method executes a yield statement

```
def fibonacci(last)
  first, second = 1, 1
  while first <= last
     yield first
     first, second = second, first + second
  end
end

puts "Fibonacci numbers less than 100 are:"
fibonacci(100) {|num| print num, " "}
puts</pre>
```

#### Procedures and Functions

- There are two categories of subprograms
  - Procedures are collection of statements that define parameterized computations
  - Functions structurally resemble procedures but are semantically modeled on mathematical functions
    - They are expected to produce no side effects
    - In practice, program functions have side effects

### Design Issues for Subprograms

- Are local variables static or dynamic?
- Can subprogram definitions appear in other subprogram definitions?
- What parameter passing methods are provided?
- Are parameter types checked?
- If subprograms can be passed as parameters and subprograms can be nested, what is the referencing environment of a passed subprogram?
- Can subprograms be overloaded?
- Can subprogram be generic?


### Local Referencing Environments

- Local variables can be stack-dynamic
  - Advantages
    - Support for recursion
    - Storage for locals is shared among some subprograms
  - Disadvantages
    - Allocation/de-allocation, initialization time
    - Indirect addressing
    - Subprograms cannot be history sensitive
- Local variables can be static
  - Advantages and disadvantages are the opposite of those for stack-dynamic local variables

#### Semantic Models of Parameter Passing

- In mode
- Out mode
- Inout mode

### Models of Parameter Passing



### Conceptual Models of Transfer

- Physically move a path
- Move an access path

### Pass-by-Value (In Mode)

- The value of the actual parameter is used to initialize the corresponding formal parameter
  - Normally implemented by copying
  - Can be implemented by transmitting an access path but not recommended (enforcing write protection is not easy)
  - Disadvantages (if by physical move): additional storage is required (stored twice) and the actual move can be costly (for large parameters)
  - Disadvantages (if by access path method): must writeprotect in the called subprogram and accesses cost more (indirect addressing)

### Pass-by-Result (Out Mode)

- When a parameter is passed by result, no value is transmitted to the subprogram; the corresponding formal parameter acts as a local variable; its value is transmitted to caller's actual parameter when control is returned to the caller, by physical move
  - Require extra storage location and copy operation
- Potential problem: sub (p1, p1);
   whichever formal parameter is copied back will represent the current value of p1

### Pass-by-Value-Result (inout Mode)

- A combination of pass-by-value and pass-by-result
- Sometimes called pass-by-copy
- Formal parameters have local storage
- Disadvantages:
  - Those of pass-by-result
  - Those of pass-by-value

### Pass-by-Reference (Inout Mode)

- Pass an access path
- Also called pass-by-sharing
- Advantage: Passing process is efficient (no copying and no duplicated storage)
- Disadvantages
  - Slower accesses (compared to pass-by-value) to formal parameters
  - Potentials for unwanted side effects (collisions)
  - Unwanted aliases (access broadened)

### Pass-by-Name (Inout Mode)

- By textual substitution
- Formals are bound to an access method at the time of the call, but actual binding to a value or address takes place at the time of a reference or assignment
- Allows flexibility in late binding

### Implementing Parameter-Passing Methods

- In most language parameter communication takes place thru the runtime stack
- Pass-by-reference are the simplest to implement; only an address is placed in the stack
- A subtle but fatal error can occur with pass-by-reference and pass-by-valueresult: a formal parameter corresponding to a constant can mistakenly be changed

## Parameter Passing Methods of Major Languages

- · C
  - Pass-by-value
  - Pass-by-reference is achieved by using pointers as parameters
- C++
  - A special pointer type called reference type for pass-byreference
- Java
  - All parameters are passed by value
  - Object parameters are passed by reference
- Ada
  - Three semantics modes of parameter transmission: in, out, in out; in is the default mode
  - Formal parameters declared out can be assigned but not referenced; those declared in can be referenced but not assigned; in out parameters can be referenced and assigned

## Parameter Passing Methods of Major Languages (continued)

- Fortran 95
  - Parameters can be declared to be in, out, or inout mode
- C#
  - Default method: pass-by-value
  - Pass-by-reference is specified by preceding both a formal parameter and its actual parameter with ref
- PHP: very similar to C#
- Perl: all actual parameters are implicitly placed in a predefined array named @\_\_
- Python and Ruby use pass-by-assignment (all data values are objects)

### Type Checking Parameters

- Considered very important for reliability
- FORTRAN 77 and original C: none
- Pascal, FORTRAN 90, Java, and Ada: it is always required
- ANSI C and C++: choice is made by the user
  - Prototypes
- Relatively new languages Perl, JavaScript, and PHP do not require type checking
- In Python and Ruby, variables do not have types (objects do), so parameter type checking is not possible

#### Multidimensional Arrays as Parameters

 If a multidimensional array is passed to a subprogram and the subprogram is separately compiled, the compiler needs to know the declared size of that array to build the storage mapping function

### Multidimensional Arrays as Parameters: C and C++

- Programmer is required to include the declared sizes of all but the first subscript (e.g. the no. of columns) in the actual parameter
- Disallows writing flexible subprograms
- Solution: pass a pointer to the array and the sizes of the dimensions as other parameters; the user must include the storage mapping function in terms of the size parameters

#### Multidimensional Arrays as Parameters: Ada

- Ada not a problem
  - Constrained arrays size is part of the array's type
  - Unconstrained arrays declared size is part of the object declaration

### Multidimensional Arrays as Parameters: Fortran

- Formal parameter that are arrays have a declaration after the header
  - For single-dimension arrays, the subscript is irrelevant
  - For multidimensional arrays, the sizes are sent as parameters and used in the declaration of the formal parameter, so those variables are used in the storage mapping function

## Multidimensional Arrays as Parameters: Java and C#

- Similar to Ada
- Arrays are objects; they are all singledimensioned, but the elements can be arrays
- Each array inherits a named constant
   (length in Java, Length in C#) that is set to
   the length of the array when the array
   object is created

## Design Considerations for Parameter Passing

- Two important considerations
  - Efficiency
  - One-way or two-way data transfer
- But the above considerations are in conflict
  - Good programming suggest limited access to variables, which means one-way whenever possible
  - But pass-by-reference is more efficient to pass structures of significant size

## Parameters that are Subprogram Names

- It is sometimes convenient to pass subprogram names as parameters
- Issues:
  - 1. Are parameter types checked?
  - 2. What is the correct referencing environment for a subprogram that was sent as a parameter?

## Parameters that are Subprogram Names: Parameter Type Checking

- C and C++: functions cannot be passed as parameters but pointers to functions can be passed and their types include the types of the parameters, so parameters can be type checked
- FORTRAN 95 type checks
- Ada does not allow subprogram parameters; an alternative is provided via Ada's generic facility
- Java does not allow method names to be passed as parameters

# Parameters that are Subprogram Names: Referencing Environment

- Shallow binding: The environment of the call statement that enacts the passed subprogram
  - Most natural for dynamic-scoped languages
- Deep binding: The environment of the definition of the passed subprogram
  - Most natural for static-scoped languages
- Ad hoc binding: The environment of the call statement that passed the subprogram

### Overloaded Subprograms

- An overloaded subprogram is one that has the same name as another subprogram in the same referencing environment
  - Every version of an overloaded subprogram has a unique protocol
- C++, Java, C#, and Ada include predefined overloaded subprograms
- In Ada, the return type of an overloaded function can be used to disambiguate calls (thus two overloaded functions can have the same parameters)
- Ada, Java, C++, and C# allow users to write multiple versions of subprograms with the same name

### Design Issues for Functions

- Are side effects allowed?
  - Parameters should always be in-mode to reduce side effect (like Ada)
- What types of return values are allowed?
  - Most imperative languages restrict the return types
  - C allows any type except arrays and functions
  - C++ is like C but also allows user-defined types
  - Ada subprograms can return any type (but Ada subprograms are not types, so they cannot be returned)
  - Java and C# methods can return any type (but because methods are not types, they cannot be returned)
  - Python and Ruby treat methods as first-class objects, so they can be returned, as well as any other class

# User-Defined Overloaded Operators


- Operators can be overloaded in Ada, C++, Python, and Ruby
- An Ada example

```
function "*" (A,B: in Vec_Type): return Integer
is
   Sum: Integer := 0;
   begin
   for Index in A'range loop
    Sum := Sum + A(Index) * B(Index)
   end loop
   return sum;
end "*";
...
c = a * b; -- a, b, and c are of type Vec_Type
```


#### Coroutines

- A coroutine is a subprogram that has multiple entries and controls them itself
- Also called symmetric control: caller and called coroutines are on a more equal basis
- A coroutine call is named a resume
- The first resume of a coroutine is to its beginning, but subsequent calls enter at the point just after the last executed statement in the coroutine
- Coroutines repeatedly resume each other, possibly forever
- Coroutines provide quasi-concurrent execution of program units (the coroutines); their execution is interleaved, but not overlapped


### Coroutines Illustrated: Possible Execution Controls



### Coroutines Illustrated: Possible Execution Controls



## Coroutines Illustrated: Possible Execution Controls with Loops



### Summary

- A subprogram definition describes the actions represented by the subprogram
- Subprograms can be either functions or procedures
- Local variables in subprograms can be stackdynamic or static
- Three models of parameter passing: in mode, out mode, and inout mode
- Some languages allow operator overloading
- Subprograms can be generic
- A coroutine is a special subprogram with multiple entries