

How to enable the Intelligent Input Bus (IBus)

Contents

Input Methods (IM) can be used if you regularly use languages that have large number of characters or complex characters, for example Asian languages like Chinese, Japanese or Korean, but IBus can also be used for Latin languages.

When installing OpenIndiana, you entered a keyboard model for the text console (the keyboard that is used without installing MATE or X11).

See:

```
# man kbd
```

The configured keyboard can be retrieved by the command:

```
# svcprop -p keymap/layout keymap
French
```

HAL, the hardware abstraction layer daemon, can probe the layout of self-identifying keyboards but it also uses different methods to figure out the XkbLayout of a keyboard :

```
> $ lshal | grep XkbLayout
> input.x11_options.XkbLayout = 'fr' (string)
```

Because X11 auto-configuration can query HAL for the keyboard type, it is useful to check the keyboard type in the lshal output. HAL uses among other things, the X Keyboard Configuration Database package :

```
x11/keyboard/data-xkb
```

This package provides the file:

```
/usr/X11/lib/X11/xkb/xkbttable.map
```

Also a default keyboard type (the US keyboard) for HAL is defined in a file provided by xorg itself :

```
/etc/hal/fdi/preprobe/10osvendor/10-x11-input.fdi
```

When using MATE and X11, the configured keyboard for X11, which is possibly auto-configured based on the HAL database, because X11 uses HAL on OpenIndiana, can be retrieved by the command:

```
# setxkbmap -query
rules:      base
model:      sun_type6_euro_usb
layout:     fr
```

By default IM (Input Methods) are not enabled, and you can configure the keyboard for MATE in the MATE Preferences for Keyboard Hardware. Choosing a layout there, is usually sufficient for languages that have a smaller number of characters, for example languages using Latin characters as English, Spanish, French, Dutch, German, etc.

IM provides a more complex mechanism for composing characters, and it can be used also for Latin languages.

In the MATE System Menu, under Preferences, select Other and choose Input Method Selector. There is a checkbox to enable the Input Method Framework. You can choose an available Input Method Framework, where you have to select the only option, namely IBus - The Intelligent Input Bus.

After clicking OK, the system alerts you to the fact that you have to logout and login again, to apply the new setting :




Figure 1: enableinput

Note that after enabling the Input Method Framework, there is a `$HOME/.imf` file in your home directory :

```
# more $HOME/.imf
```

The `$HOME/.imf` file sets the variable `GTK_IM_MODULE` to `ibus` and sets `XMODIFIERS` to `@im=ibus` to set the IM framework to `ibus`.

The file `/etc/X11/xinit/xinitrc` sources the `$HOME/.imf` file in your home directory by running the `0210.im` script in the `/etc/X11/xinit/xinitrc.d` directory.

After logout and login, you can see that MATE has automatically started a `ibus-daemon -xim` process.

The IM framework is now enabled (after logout/login) and you can select specific input methods :

The above screenshot shows for example the Dutch-Belgian input method. Additional input methods such as Spanish or other input methods can be added without a need to login or logoff.

If you disable the IM , the `$HOME/.imf` file in your home directory will be replaced by an empty file that is created and maintained by the Input Method selector tool. In order to apply the new `$HOME/.imf` file, you have to logout and login again.

The OpenIndiana default is not to run IM.




Figure 2: inputmethod